



You are viewing the **v4 (stable)** documentation. [Switch to v5 \(alpha\) →](#)

System Controls

Manage your hardware and system state directly through the shell.

Audio Management

Function	Command	Description
Volume Up	<code>volume increase</code> 	Increase output volume
Volume Down	<code>volume decrease</code> 	Decrease output volume
Mute Output	<code>volume muteOutput</code> 	Toggle output mute
Input Up	<code>volume increaseInput</code> 	Increase input volume
Input Down	<code>volume decreaseInput</code> 	Decrease input volume
Mute Input	<code>volume muteInput</code> 	Toggle input mute
Toggle Panel	<code>volume togglePanel</code> 	Toggle audio panel
Open Panel	<code>volume openPanel</code> 	Open audio panel
Close Panel	<code>volume closePanel</code> 	Close audio panel

Media Controls

Function	Command	Description
You are viewing the v4 (stable) documentation. Switch to v5 (alpha) →		
Play	<code>media play</code> 	Play media
Pause	<code>media pause</code> 	Pause media
Next	<code>media next</code> 	Next track
Previous	<code>media previous</code> 	Previous track
Seek Rel.	<code>media seekRelative \$offset</code> 	Seek by seconds
Seek By Ratio	<code>media seekByRatio \$position</code> 	Seek to position (0.0-1.0)
Toggle Panel	<code>media toggle</code> 	Toggle media panel

Network & Connectivity

Function	Command	Description
WiFi Toggle	<code>wifi toggle</code> 	Toggle WiFi
WiFi Enable	<code>wifi enable</code> 	Enable WiFi
WiFi Disable	<code>wifi disable</code> 	Disable WiFi
Network Panel	<code>network togglePanel</code> 	Toggle network panel
BT Toggle	<code>bluetooth toggle</code> 	Toggle Bluetooth
BT Enable	<code>bluetooth enable</code> 	Enable Bluetooth
BT Disable	<code>bluetooth disable</code> 	Disable Bluetooth
BT Panel	<code>bluetooth togglePanel</code> 	Toggle Bluetooth panel
Airplane Mode Toggle	<code>airplaneMode toggle</code> 	Toggle Wi-Fi and Bluetooth (rfkill)
Airplane Mode Enable	<code>airplaneMode enable</code> 	Block Wi-Fi and Bluetooth (rfkill)

Function	Command	Description
You are viewing the v4 (stable) documentation. Switch to v5 (alpha) →		

Display & Brightness

Function	Command	Description
Brightness Up	<code>brightness increase</code> 	Increase brightness
Brightness Down	<code>brightness decrease</code> 	Decrease brightness
Set Brightness	<code>brightness set <value></code> 	Set brightness (0-100)
NightLight	<code>nightLight toggle</code> 	Toggle night light
Monitors On	<code>monitors on</code> 	Turn all monitors on
Monitors Off	<code>monitors off</code> 	Turn all monitors off

Battery Panel

Function	Command	Description
Battery Panel	<code>battery togglePanel</code> 	Toggle battery panel

Power Profile Management

Function	Command	Description
Power Profile	<code>powerProfile cycle</code> 	Cycle power profiles
Power Saver	<code>powerProfile set powersaver</code> 	Set Power Saver mode
Balanced	<code>powerProfile set balanced</code> 	Set Balanced mode

Function	Command	Description
You are viewing the v4 (stable) documentation. Switch to v5 (alpha) →		
		mode
Toggle Noctalia Performance	<code>powerProfile toggleNoctaliaPerformance</code> 	Toggle Noctalia Performance mode
Enable Noctalia Performance	<code>powerProfile enableNoctaliaPerformance</code> 	Enable Noctalia Performance mode
Disable Noctalia Performance	<code>powerProfile disableNoctaliaPerformance</code> 	Disable Noctalia Performance mode