

On This Page >



settings

Attribute: `clan.core.settings`

Settings of the clan.

This is a read-only attribute-set available to the machines of the clan.

Type: `submodule`

Declared in: [nixosModules/clanCore/state-version](#)

directory

Attribute: `clan.core.settings.directory`

the location of the flake repo, used to calculate the location of vars and secrets

Type: `absolute path`

Declared in: [nixosModules/clanCore/settings.nix](#)

domain

Attribute: `clan.core.settings.domain`**Readonly**

the domain for the clan

Type: string matching the pattern `^[a-z0-9]([a-z0-9]{0,61}[a-z0-9])?(\.[a-z0-9]([a-z0-9]{0,61}[a-z0-9])?)*$`

Declared in: [nixosModules/clangCore/settings.nix](#)

icon

Attribute: `clang.core.settings.icon`

Readonly

the location of the clan icon

Type: null or absolute path

Declared in: [nixosModules/clangCore/settings.nix](#)

machine

Attribute: `clang.core.settings.machine`

Settings of the machine.

This is a read-only attribute-set available to the machines of the clan.

Type: submodule

Default:

`{ }`

Declared in: [nixosModules/clangCore/settings.nix](#)

description

Attribute: `clang.core.settings.machine.description`

the description of the machine

Type: `null or string`

Default:

`null`

Declared in: [nixosModules/clangCore/settings.nix](#)

icon

Attribute: `clang.core.settings.machine.icon`

the location of the machine icon

Type: `null or absolute path`

Default:

`null`

Declared in: [nixosModules/clangCore/settings.nix](#)

name

Attribute: `clang.core.settings.machine.name`

Readonly

the name of the machine

Type: `string`

Declared in: [nixosModules/clangCore/settings.nix](#)

machine-id

Attribute: `clang.core.settings.machine-id`

enable

Attribute: `clan.core.settings.machine-id.enable`

Whether to enable machine ID generation. Sets the `/etc/machine-id` and exposes it as a nix option. This unique ID that is not dependent on ephemeral or variable data, such as hostnames, MAC addresses or IP addresses.

See <https://www.freedesktop.org/software/systemd/man/latest/machine-id.html> for details. .

Type: `boolean`

Default:

`false`

◆ Example

`true`

Declared in: [nixosModules/clanCore/machine-id](#)

name

Attribute: `clan.core.settings.name`

Readonly

the name of the clan

Type: `string`

Declared in: [nixosModules/clanCore/settings.nix](#)

state-version

Attribute: `clan.core.settings.state-version`

enable

Attribute: `clan.core.settings.state-version.enable`

Whether to enable automatic state-version generation.

The option will take the specified version, if one is already supplied through the config or generate one if not.

Type: `boolean`

Default:

`false`

◆ Example

`true`

Declared in: [nixosModules/clanCore/state-version](#)

tld

Attribute: `clan.core.settings.tld`

Readonly

the TLD for the clan

Type: `string matching the pattern [a-z]+`

Declared in: [nixosModules/clanCore/settings.nix](#)

← Previous

postgresql

Next →
sops

Need help? Reach out to [our community](#).