


REG NO.: 192411079

SCHEMATIC CAPTURE



SOURCE CODE

EXP8 | Arduino 1.8.19

File Edit Sketch Tools Help

EXP8

```
#define GreenLed 13
#define Sensor A0

void setup() {
  pinMode(13, OUTPUT);
  pinMode(12, OUTPUT);
  pinMode(A0, INPUT);
  Serial.begin(9600);
}

void loop() {
  int value = analogRead(A0);
  Serial.print("Analog Value coming from the sensor : ");
  Serial.println(value);
  delay(100);
  if(value>600){
    digitalWrite(GreenLed,HIGH);
    delay(250);
  }
  else{
    digitalWrite(GreenLed,LOW);
    delay(250);
  }
  delay(20);
}
```

Done compiling.

```
C:\Program Files (x86)\Arduino\hardware\arduino\avr
C:\Program Files (x86)\Arduino\hardware\arduino\avr

are\tools\avr/bin/avr-g++ -c -g -O2 -w -std=gnu++11 -fpermissive -fno-exceptions -ffunction-sections -fdata-sections -fno-threadsafe-statics -Wno-error=narrowing -fno-PI -DP_C
are\tools\avr/bin/avr-g++ -c -g -O2 -w -std=gnu++11 -fpermissive -fno-exceptions -ffunction-sections -fdata-sections -fno-threadsafe-statics -Wno-error=narrowing -fno-PI -DP_C
-builder\ctags\5.8-arduino\ctags -u --language-force=c++ -f - --c++-kinds=svpf --fields=KSTZns --line-directives "C:\Users\tej\AppData\Local\Temp\arduino_build_952700\preproc\ctags_target_for_gcc_
are\tools\avr/bin/avr-g++ -c -g -O2 -w -std=gnu++11 -fpermissive -fno-exceptions -ffunction-sections -fdata-sections -fno-threadsafe-statics -Wno-error=narrowing -MMD -fno-PI -DP_C -U16000000L

Data\Local\Temp\arduino_cache_631844\core\core_arduino_avr_uno_0c812075a070eb4a3b385d8fb077540.a

are\tools\avr/bin/avr-gcc -w -O2 -g -fno-fuse-linker-plugin -Wl,-gc-sections -mmcu=atmega328p -o "C:\Users\tej\AppData\Local\Temp\arduino_build_952700\EXP8.ino.elf" "C:\Users\tej\AppData\Local\T
are\tools\avr/bin/avr-objcopy -O ihex -j .eeprom --set-section-flags=.eeprom=alloc,load --no-change-sections --change-section-lma .eeprom=0 "C:\Users\tej\AppData\Local\Temp\arduino_build_952700\EXP8.ino
are\tools\avr/bin/avr-objcopy -O ihex -R .eeprom "C:\Users\tej\AppData\Local\Temp\arduino_build_952700\EXP8.ino.elf" "C:\Users\tej\AppData\Local\Temp\arduino_build_952700\EXP8.ino.hex"
are\tools\avr/bin/avr-size -A "C:\Users\tej\AppData\Local\Temp\arduino_build_952700\EXP8.ino.elf"

Storage space. Maximum is 32256 bytes.
Dynamic memory, leaving 1820 bytes for local variables. Maximum is 2048 bytes.
```

1 |

Arduino IDE

OUTPUT

