

PASSWORD



Router0

PC0

Question 1: Basic Router Security Setup

Topology

1 Router (R1)
1 PC connected via console

Requirements

Configure on R1:

Console password → cisco
AUX password → aux123
Enable password → enable123
Enable secret → secret123
VTY (0-4) password → telnet123

Tasks

1. Configure all passwords correctly
2. Enable login wherever required
3. Save configuration

Verification

Try entering privileged mode → which password works?

Use show running-config → check encryption

```
Router(config)#line console 0
Router(config-line)#password cisco
Router(config-line)#login
Router(config-line)#exit

Router(config)#line aux 0
Router(config-line)#password aux123
Router(config-line)#login
Router(config-line)#exit

Router(config)#enable password enable123


Router(config)#enable secret secret123

Router(config)#line vty 0 4
Router(config-line)#password telnet123
Router(config-line)#exit
```

```
Router#sh ru
Building configuration...

Current configuration : 748 bytes
!
version 15.1
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname Router
!
enable secret 5 $1$mERr$GyX25SY.KCP/5HlmX5hsg0
enable password enable123
!
!
!
!
!
!
line con 0
password cisco
login
!
line aux 0
password aux123
login
!
line vty 0 4
password telnet123
login
!
!
```

Q2



Question 2: Remote Access + Security Priority

Topology

- 1 Router (R1)
- 2 PCs (PC1, PC2) via switch

Requirements

On R1:
Set hostname → SECURE-R1
Console password → local123
Enable password → weakpass
Enable secret → strongpass
VTY password → remote123

Allow Telnet access

Tasks

1. Configure IP on router interface
2. Configure IP on PCs (same network)
3. Test Telnet from PC → Router

Questions (Important)

Which password is used when entering privileged mode?
Why is one password ignored?

```
R1(config)#hostname SECURE-R1
SECURE-R1(config)#enable secret strongpass
SECURE-R1(config)#enable password weakpass

SECURE-R1(config)#line console 0
SECURE-R1(config-line)#password local123
SECURE-R1(config-line)#login
SECURE-R1(config-line)#exit

SECURE-R1(config)#line vty 0 4
SECURE-R1(config-line)#password remote123
SECURE-R1(config-line)#login
SECURE-R1(config-line)#exit

SECURE-R1(config)#int fa0/0
SECURE-R1(config-if)#ip address 192.168.119.1 255.255.255.0
SECURE-R1(config-if)#no shut
SECURE-R1(config-if)#ex
```

```
SECURE-R1#
SECURE-R1#exit

[Connection to 192.168.119.1 closed by foreign host]
C:\>ping 192.168.119.1

Pinging 192.168.119.1 with 32 bytes of data:

Reply from 192.168.119.1: bytes=32 time<1ms TTL=255
Reply from 192.168.119.1: bytes=32 time<1ms TTL=255
Reply from 192.168.119.1: bytes=32 time<1ms TTL=255
Reply from 192.168.119.1: bytes=32 time<1ms TTL=255

Ping statistics for 192.168.119.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>telnet 192.168.119.1
Trying 192.168.119.1 ...Open

User Access Verification

Password:
Password:
SECURE-R1>en
Password:
SECURE-R1#
```