Kickbase 0.3 – test list

Format: **Do this** → expected result. Tick the box when it matches. Report anything that does not.

Before you start

Click inside the plugin window first so it has keyboard focus (otherwise your DAW may take Ctrl+Z, Ctrl+S and similar shortcuts before Kickbase does).

Older presets and projects may sound slightly different in 0.3. That is expected; note anything that sounds clearly wrong.

Menu and project

- [ ] **Menu > New Project with unsaved changes** → asks whether to save first, then starts an empty project.
- [ ] **Ctrl+S** → the project is saved, a green confirmation appears, the project name is in the title.
- [ ] **Menu > Open and Menu > Save as** → open and save a .kbproj file; the three latest projects are listed.
- [ ] **Menu > Export** → export is in the menu (not a separate button).
- [ ] **Turn on Menu > Autosave every 3 min, change something, wait over 3 minutes, choose Open autosave** → an autosaved version can be opened.
- [ ] **Open an old project or preset** → sounds as before; JOG SPEED is 1x.

All tabs (general)

- [ ] **Click a dropdown, use the arrow keys, press Enter** → focus is visible, arrows change the choice, Enter selects.
- [ ] **Ctrl+Z after turning a knob, drawing a step, choosing a pattern template, a sub-preset, pasting a track** → each gesture is undone as one step.
- [ ] **Ctrl+Shift+Z or Ctrl+Y** → redoes the step.
- [ ] **Menu > History...** → lists the steps by name; clicking a step jumps to it.
- [ ] **Load a main preset or a project** → the history is cleared.
- [ ] **Move knobs, tabs, sliders and diagrams with the mouse** → dark knobs with shadow, pill-shaped tabs with glow, flat sub-tab strip, dark diagrams.
- [ ] **Look at the display at the top while switching tabs and inner tabs** → the path is shown, for example INSTRUMENT > INSTR 3 > OSC 2.

Instrument tabs (new order in 0.3)

- [ ] **Open an instrument and look at the tab strip** → order is INSTR | OSC 1, OSC 2, OSC 3, SAMPLE, FM | FILTER, MIX, TIMING, with a simple divider after INSTR and after FM.
- [ ] **Click every inner tab** → each tab opens and its HELP button opens the matching help text.
- [ ] **TIMING tab: set POS DELAY, LENGTH, MODE GATE / SHIFT, LENGTH SYNC and the repeat count (1-8) for a motor** → the diagram shows when each motor starts and stops; the sound follows the settings.
- [ ] **MIX tab: set a start delay (0-4000 ms, or synced to the beat) on one motor** → that layer enters later; 0 leaves old presets unchanged.
- [ ] **Use COLLISIONS in MIX** → strength is shown from blue to red depending on the gap.
- [ ] **Tabs INSTR, FILTER, SAMPLE and TIMING: knob sizes and spacing** → known issue: some knobs are small and labels sit far below the knobs (planned for 0.4). Note anything that is hard to use.

Preview (PREVIEW)

- [ ] **Switch tabs and press the preview button on the far right** → motor tab: only that motor; INSTRUMENT/FILTER/MIX: the whole instrument without pattern; PATTERN, ANALYZER, AI CHAT, LIVE CODE: the whole pattern; KICK: only the kick.
- [ ] **Start PREVIEW while your DAW plays notes** → PREVIEW runs in Kickbase's own loop and is not disturbed by the DAW's notes.
- [ ] **Stop PREVIEW** → the DAW takes over again; the first note is neither doubled nor dropped.
- [ ] **One-bar loop in the DAW, start PREVIEW** → the DAW loop does not control the preview.
- [ ] **Play any note on the MIDI keyboard during PREVIEW** → does not affect the preview.

Transport, JOG and LOOP (toolbar)

- [ ] **Double-click the tempo, type 150 during PREVIEW** → the tempo changes. While the DAW plays, tempo and bar are locked with the tip "controlled by DAW".
- [ ] **Scroll the mouse wheel over the bar counter during PREVIEW** → playback jumps to the chosen bar after the wheel has rested a moment.
- [ ] **LOOP is in the JOG panel: open it, LOOP on with bars 1-2, change to 2-3 while running, turn off** → loops strictly in the range; stop the DAW playback by hand. Close and reopen the panel: the LOOP button and bars show the right state.
- [ ] **BRAKE with curves VINYL, TAPE, HARD and SLOW in turn** → VINYL: turntable stop; TAPE: long, pitch slides down; HARD: short and straight; SLOW: slow brake and slow start. All return to the set JOG SPEED. Holding the wheel during the brake cancels it.
- [ ] **Press the LP button next to restart** → the JOG panel opens. The wheel is drawn as a record, the needle moves inward with the pattern and jumps out at the loop; a hand is shown over the record.
- [ ] **Mode STOP: start PREVIEW, hold the wheel** → the music stops; turn forward: it plays at the turning speed; release: normal tempo.
- [ ] **Mode KEEP GOING** → the music continues; forward = faster, backward = slower (never reversed).
- [ ] **Mode REC: set the JOG SPEED automation to Write/Touch/Latch, record and scratch** → the curve is drawn in the DAW; on playback the music follows the scratch; on release the curve returns to 1x.
- [ ] **Mode STOP, scratch** → no curve is written.
- [ ] **Drag JOG SPEED to 2** → double tempo, the LP icon lights.
- [ ] **Drag an LFO to JOG SPEED, then REMOVE AUTOMATION** → the status line shows the LFO; removal sets 1x.
- [ ] **Right-click JOG SPEED, draw an automation curve in the DAW** → the speed follows the curve.
- [ ] **Start the DAW playback with DAW SYNC and move the wheel** → the DAW's tempo and position do not change.
- [ ] **Close the panel while holding the wheel** → the tempo returns to normal.

INSTRUMENT, OSC and harmonic editor

- [ ] **Play C5 from the DAW with the piano roll open** → the pattern starts and plays (not just a live note).
- [ ] **OSC preset menu: delete the folder Documents\Kickbase\Presets\Oscillators, open the menu** → 14 starter presets in 6 categories (Sub, Bass, Reese, Acid, Growl, Layer); load one in each OSC.
- [ ] **Set OSC 1 WARP to RING (B)** → the shape knobs change to "RING: OSC 1 x OSC 2", "x OSC 3", "x OSC 2 x OSC 3"; AMOUNT blends dry (0) to full ring (1). The source must be ON, otherwise full ring is silent.
- [ ] **Drag WIDTH up from 1 while a note plays** → no clicks.

- [ ] **Right-click an oscillator's waveform > Edit harmonics** → a large window opens with the waveform on top and bars for strength and phase below.
- [ ] **Drag the bars, fast and slow** → the waveform follows the mouse immediately, no bars are skipped, the sound changes after a short moment.
- [ ] **Drag bar 1 all the way down** → the fundamental disappears. Double-click a bar resets it; double-click in the waveform resets everything.
- [ ] **Zoom 16 / 32 / 64 and Ctrl+wheel** → bars become wider and narrower.
- [ ] **Brushes DRAW, LINE, SMOOTH, RANDOM** → LINE draws a straight line, SMOOTH evens out, RANDOM gives new values on each drag.
- [ ] **Presets SAW, SQUARE, TRIANGLE, ODD, EVEN, BASS WARM** → the spectrum and waveform change and sound like the name.
- [ ] **Close the window, save the project, open it again** → the edited wave is still there.

SAMPLE and slicer

- [ ] **SHOW SLICES** → each slice is a coloured box with "Slice N" and a note; one click plays only that slice.
- [ ] **Wheel in the waveform, Shift+wheel** → zoom toward the mouse and scroll.
- [ ] **MANUAL + SLICES: drag a boundary, right-click, double-click** → moves, removes and adds a boundary.
- [ ] **CREATE (in Grid/Auto)** → calculated boundaries become manual markers and are shown as SLICES.
- [ ] **Create more than 16 slices** → the piano roll gets a slice row; there is no limit on the number of slices.
- [ ] **Open PATTERN with slices** → drawing a slice note sounds like that slice played directly.
- [ ] **Save and load the project with slices** → the slices and notes remain; Ctrl+Z undoes edits.
- [ ] **Sample editor: switch AMP and PITCH on, draw a curve** → the sample's volume and pitch follow the curve; off = the old sound.
- [ ] **Sample editor: REVERSE** → the sample plays backwards; per-note reverse also works.
- [ ] **Kick sample tools: cut, reverse, fade-out and click layers 2 and 3** → each tool changes the sound as named and can be undone.

KICK

- [ ] **Preview button on the KICK tab** → plays only the kick.
- [ ] **Point at nodes in the pitch curve** → note names appear at each point (C4 = 60).
- [ ] **Ask the AI chat about the kick's pitch nodes** → the AI can give note and Hz per node.
- [ ] **Use the MIX knob and the small SYNTH / SAMPLE buttons beside it** → blends the synthesised and sampled kick; the ENVELOPE tab shows the envelope.
- [ ] **Load the kick presets Clean Full-On, Clean Tight, Clean Deep, Clean Round, Clean Punchy, Clean Long, Clean Snappy, Clean Warm, Clean Sub, Clean Modern** → clean psytrance kicks, tail around 40-45 Hz, no clipping (Clean Warm is hottest, peak near 0 dB).
- [ ] **Load the Psy Clean C, C Tight, D, D Long, F Soft, F Sub, A Punch, G kicks** → clean sine kicks with a steep sweep; the tone is Fixed. Please tell us which tone and character works against your bass.
- [ ] **Load the bass instruments Rolling Tight, Rolling Deep, Rolling Bright, Rolling Fat, Rolling Soft, Rolling Snap together with a kick** → rolling bass that sits under the kick without getting muddy or clipping.
- [ ] **Load the main presets newest 1-10 one at a time and play E4 at the song's tempo** → ten different styles; kick and bass sit together, no clipping. Please note which should be fine-tuned.

PATTERN and piano roll

- [ ] **Play the pattern** → playing notes light up in the piano roll.
- [ ] **Kick in 2 bars and instrument 1 in 1 bar, Loop 1-2** → the loop stays within the range; the short track loops internally.
- [ ] **Pattern of 3 bars with a kick in every bar** → bar 3 has all hits; the length indicator matches the real length.
- [ ] **Glide note in the same bar as a chord** → all simultaneous notes glide equally far.
- [ ] **Glide note with a bar note on the same tick** → the bar note is heard.
- [ ] **Right-drag on an empty grid** → draws a glide line that can end on a note or at a free height, and also goes before a note.
- [ ] **Right-click without dragging** → the normal menu appears.
- [ ] **Save and load, export MIDI** → lines are kept when saving; the MIDI export approximates the glide.
- [ ] **Other rows' notes** → shown faintly (ghost notes) in the row's colour and cannot be clicked.
- [ ] **POP OUT in the bottom row of the piano roll** → the roll opens in its own resizable window; the steps remain in the main window.
- [ ] **DOCK or close the window** → the roll comes back.
- [ ] **LISTEN PIANO ROLL button** → appears immediately when the roll is shown, even at a low animation rate.
- [ ] **Parameter lanes under the piano roll: draw values per note (cutoff, pan, FX send)** → the sound follows the value at each note; Alt resets, Ctrl+Z undoes; the values survive copy, move, save and load.

MIX and combined waveform

- [ ] **Combined wave: mouse wheel, middle-button drag, scroll bar** → zooms around the mouse (0.1-32x), pans, time axis in ms.
- [ ] **WIDE/NARROW** → the wave gets the full width and returns.
- [ ] **Double-click in the wave** → resets zoom and position.
- [ ] **The MIX tab as a whole** → all controls respond and the sound follows.

FX, send matrix and sidechain

- [ ] **Open the send popup of an instrument** → a matrix shows the FX channels as rows; set a send amount to a channel and hear it.
- [ ] **Set the number of FX channels (up to 12)** → channels are added and removed; the FX page list scrolls.
- [ ] **M button on a channel** → mutes that channel.
- [ ] **Load an old preset that had a single FX link** → known issue: an extra "FX1" row may appear (planned fix in 0.4). Note what you see.
- [ ] **Remove the last FX channel on the FX page** → asks for confirmation when it has effects or sends.
- [ ] **Load an old project with a Maximizer** → Classic, not Smooth, and the MODE knob is right.
- [ ] **Maximizer MODE, KEEP/COMPARE, shimmer, Low Multiplier, AP/START, HALFTIME** → listening test: each mode sounds different and right, without clicks.
- [ ] **FX slot with SIDECHAIN CURVE** → ducks according to the kick's envelope / the curve from the SIDECHAIN tab.
- [ ] **FX slot with SIDECHAIN 2-BAND** → LOW and MID-HI duck separately with their own depth and release.

- [ ] **FX slot with PHASE ROTATION, FREQ 60 Hz, ROTATION 180 deg on a bass under the kick** → the bass fundamental changes phase against the kick (the sum gets stronger or weaker depending on the rotation), level otherwise unchanged.
- [ ] **Echo, Flanger, BAND DUCKER and the other FX2 types** → sound in all slots, no clicks or silence.

LIVE CODE

- [ ] **Type s("** → suggestions: bd/kick and i1...i10.
- [ ] **Type note(" or n("** → suggestions for note names and examples (chords, *4, ~, <>, @3).
- [ ] **Type $: on an empty line** → suggestions and a template.
- [ ] **Type lfo(" and env("** → parameter names are suggested.
- [ ] **s("i1").chord("major","c2",0,["1/4","4/4","2/4"])** → C2 short, E2 a whole cycle, G2 half.
- [ ] **Press FORMAT** → one chain per line, s("...") first, // lines untouched; Ctrl+Z undoes.
- [ ] **The editor** → dark theme with colour coding.
- [ ] **Run Live Code, then Ctrl+Z** → the run is undone as one step.

AI CHAT

- [ ] **Enter an OpenAI key (OPENAI button, SAVE), ask "make the kick shorter"** → the AI answers and changes the kick; the key is not shown in logs.
- [ ] **Start Ollama with a model that supports tools (e.g. qwen3), choose OLLAMA, SAVE** → the model list is fetched; the same request works without a key.
- [ ] **ANTHROPIC and GEMINI** → work as before.
- [ ] **Ask the AI to read the state** → the kick's pitch nodes with note and Hz are included.

Presets, USER category and files

- [ ] **Save your own preset without choosing a category** → it ends up in USER in the preset list.
- [ ] **Open the preset lists (kick, instrument, main)** → USER is its own category beside the factory categories and "Old".
- [ ] **Menu > Export MIDI after recording a pattern** → the file opens in the DAW with the right notes and lengths.