

TB Delay

USER MANUAL



Purpose

Creates repeating echoes, rhythmic space, and evolving feedback textures.

License: MIT License

This software is licensed under the MIT License. Copyright (c) 2026 TaebeumKim. See the repository LICENSE file for the full terms.

Controllable properties

Each control is listed by its panel name. Use the description to decide what to listen for, then make small changes in the context of the music.

Control and settings	What it changes
Age Range: 0 to 100 Default: 28	Makes repeats sound newer and cleaner or older, softer, and more worn.
Bypass Range: Off, On Default: Off	Turns the complete effect off or on for a direct before-and-after comparison.
Character Range: Clean, Tape, BBD, Digital Default: Tape	Chooses the repeat tone: clean, tape, bucket-brigade, or digital.
Color Space Bypass Range: Off, On Default: Off	Turns the tone and space section off while keeping the repeat timing active.
Delay Time Range: 10 to 8000 Default: 375	Sets the time between the original sound and the repeat when timing is free.
Density Range: 1 to 8 Default: 4	Sets how many granular fragments overlap inside the transformed repeats.
Diverge Range: 0 to 100 Default: 0	Makes the left and right repeat paths evolve differently over time.

Control and settings	What it changes
Division Range: 18 choices Default: 1/8 D	Chooses the note value used when the delay follows the song tempo.
Drive Range: 0 to 100 Default: 18	Sets how strongly the sound is pushed into harmonic color or distortion.
Duck Range: 0 to 100 Default: 25	Lowers the echoes while the dry sound is present, then lets them rise in the gaps.
Feedback Range: 0 to 110 Default: 48	Returns the processed sound into the effect to create a longer or stronger result.
Freeze Range: Off, On Default: Off	Holds the current effect tail so it continues without new input.
Grain Range: 0 to 100 Default: 0	Adds granular breakup and particle-like texture to the repeats.
Grain Size Range: 10 to 500 Default: 90	Sets the length of each granular fragment. Short values feel gritty; long values feel smoother.
Grain Transform Bypass Range: Off, On Default: Off	Turns the grain and pitch transformation section off while keeping the basic delay active.
High Cut Range: 500 to 20000 Default: 9000	Removes high frequencies from the current sound or effect layer.
Low Cut Range: 20 to 2000 Default: 120	Removes low frequencies from the current sound or effect layer.
Mix Range: 0 to 100 Default: 30	Blends the original sound with the processed sound.

Control and settings	What it changes
Mod Depth Range: 0 to 20 Default: 0.8	Sets how strongly the named process changes the sound.
Mod Rate Range: 0.02 to 10 Default: 0.25	Sets how quickly the named movement repeats.
Offset Range: -100 to 100 Default: 0	Moves one side earlier and the other later to create stereo separation.
Output Range: -18 to 6 Default: 0	Sets the final listening level after processing.
Pitch Range: -24 to 24 Default: 0	Moves the pitch of the processed sound up or down.
Program Range: 100 factory programs Default: Init	Loads a factory starting point. Adjust the controls afterward to fit the current sound.
Reverse Range: 0 to 100 Default: 0	Sets how often or how strongly the processed sound plays backward.
Shift Range: -2000 to 2000 Default: 0	Moves the frequency content of each repeat upward or downward for spiral-like motion.
Size Range: 2 to 120 Default: 32	Sets the apparent size of the diffuse space around the repeats.
Smear Range: 0 to 100 Default: 12	Softens the edges of the repeats so they blend into a more reverb-like cloud.
Spacing Range: 25 to 200 Default: 100	Expands or contracts the distance between multiple taps.

Control and settings	What it changes
Spray Range: 0 to 100 Default: 15	Spreads small pieces of each repeat in time for a looser, less predictable texture.
Stereo Bypass Range: Off, On Default: Off	Keeps the delay movement centered when enabled, useful for mono-safe repeats.
Style Range: Single, Dual, Ping Pong, Ratio Default: Ping Pong	Chooses the repeat layout, including single, dual, ping-pong, and ratio patterns.
Swing Range: -50 to 50 Default: 0	Moves alternating repeats earlier or later to create a looser groove.
Taps Range: 1, 2, 4, 8 Default: 1	Chooses how many repeat points are created for each echo cycle.
Time Change Range: Crossfade, Glide Default: Glide	Chooses whether delay-time changes crossfade cleanly or glide with a pitch bend.
Time Mode Range: Free, Sync, Tune Default: Sync	Chooses free milliseconds, song-tempo divisions, or tuned pitch intervals for the delay time.
Transform Route Range: Loop, Post Default: Loop	Places the creative transformations inside the feedback loop or after it.
Width Range: 0 to 200 Default: 130	Sets the stereo spread of the processed sound.