


TB Parallel Reverb

USER MANUAL



Purpose

Blends three different spaces to create body, bright reflections, and deep ambience.

License: MIT License

This software is licensed under the MIT License. Copyright (c) 2026 TaebeumKim. See the repository LICENSE file for the full terms.

Controllable properties

Each control is listed by its panel name. Use the description to decide what to listen for, then make small changes in the context of the music.

Control and settings	What it changes
Bright Color Range: 0 to 100 Default: 45	Moves this reverb layer from darker and softer toward brighter and more present.
Bright Decay Range: 1.5 to 2.5 Default: 2	Sets how long this reverb layer lasts.
Bright Diffusion Range: 0 to 100 Default: 70	Changes reflections from separate echoes into a smoother wash.
Bright Enabled Range: Off, On Default: On	Turns this reverb layer on or off.
Bright High Pass Range: 20 to 1800 Default: 450	Removes low frequencies from this reverb layer.
Bright Low Pass Range: 1200 to 20000 Default: 13500	Removes high frequencies from this reverb layer.
Bright Mode Range: Plate, Spring Default: Plate	Chooses the space character used by this reverb layer.

Control and settings	What it changes
Bright Modulation Depth Range: 0 to 20 Default: 1.5	Sets how much gentle pitch movement is added to this reverb layer.
Bright Modulation Rate Range: 0.02 to 5 Default: 0.02	Sets how quickly the gentle pitch movement changes.
Bright Plate Distance Spring Tension Range: 0 to 100 Default: 35	Changes plate distance or spring tension, depending on the selected Bright mode.
Bright Pre-Delay Range: 0 to 100 Default: 18	Sets the pause between the dry sound and this reverb layer.
Bright Send Gain Range: -60 to 6 Default: -15	Sets how much sound is sent into this reverb layer.
Bright Wide Range: 0 to 270 Default: 210	Sets the stereo width of this reverb layer.
Bypass Range: Off, On Default: Off	Turns the complete effect off or on for a direct before-and-after comparison.
Glue Color Range: 0 to 100 Default: 30	Moves this reverb layer from darker and softer toward brighter and more present.
Glue Damping Range: 0 to 100 Default: 60	Darkens this reverb layer as it decays.
Glue Decay Range: 0.5 to 1 Default: 0.75	Sets how long this reverb layer lasts.
Glue Diffusion Range: 0 to 100 Default: 65	Changes reflections from separate echoes into a smoother wash.

Control and settings	What it changes
Glue Early Late Mix Range: 0 to 100 Default: 45	Balances the first reflections against the later reverb tail.
Glue Enabled Range: Off, On Default: On	Turns this reverb layer on or off.
Glue High Pass Range: 20 to 1500 Default: 200	Removes low frequencies from this reverb layer.
Glue Low Pass Range: 1000 to 20000 Default: 9000	Removes high frequencies from this reverb layer.
Glue Mode Range: Room, Chamber Default: Room	Chooses the space character used by this reverb layer.
Glue Pre-Delay Range: 0 to 60 Default: 8	Sets the pause between the dry sound and this reverb layer.
Glue Send Gain Range: -60 to 6 Default: -12	Sets how much sound is sent into this reverb layer.
Glue Size Range: 0 to 100 Default: 50	Sets the apparent room size of this reverb layer.
Glue Wide Range: 0 to 180 Default: 150	Sets the stereo width of this reverb layer.
Program Range: 100 factory programs Default: Init Parallel	Loads a factory starting point. Adjust the controls afterward to fit the current sound.
Reverb Solo Range: Off, Glue, Bright, Space Default: Off	Lets you hear one reverb layer by itself while balancing the three spaces.

Control and settings	What it changes
Space Color Range: 0 to 100 Default: 25	Moves this reverb layer from darker and softer toward brighter and more present.
Space Decay / Length Range: 0.25 to 10 Default: 3.2	Sets how long this reverb or impulse response lasts.
Space Diffusion Range: 0 to 100 Default: 72	Changes reflections from separate echoes into a smoother wash.
Space Enabled Range: Off, On Default: On	Turns this reverb layer on or off.
Space Hall Type Range: Church, Auditorium, Concert Hall, Studio Hall Default: Church	Chooses the basic hall character.
Space HF Damping Range: 0 to 100 Default: 45	Softens high frequencies as the reverb fades.
Space High Pass Range: 20 to 1500 Default: 300	Removes low frequencies from this reverb layer.
Space Low Pass Range: 1000 to 20000 Default: 7500	Removes high frequencies from this reverb layer.
Space Mode Range: Hall, IR Default: Hall	Chooses the space character used by this reverb layer.
Space Pre-Delay Range: 0 to 200 Default: 60	Sets the pause between the dry sound and this reverb layer.
Space Send Gain Range: -60 to 6 Default: -22	Sets how much sound is sent into this reverb layer.

Control and settings	What it changes
Space Shimmer Range: 0 to 100 Default: 15	Adds a bright rising tone to the long reverb layer.
Space Wide Range: 0 to 360 Default: 240	Sets the stereo width of this reverb layer.
Wet/Dry Mix Range: 0 to 100 Default: 100	Blends the original sound with all enabled reverb layers.