

TB Vocoder

USER MANUAL



Purpose

Places the rhythm and articulation of one sound onto the tone of another sound.

License: MIT License

This software is licensed under the MIT License. Copyright (c) 2026 TaebeumKim. See the repository LICENSE file for the full terms.

Controllable properties

Each control is listed by its panel name. Use the description to decide what to listen for, then make small changes in the context of the music.

Control and settings	What it changes
Attack Range: 0.1 to 200 Default: 3	Sets how quickly the effect reacts when a sound begins. Faster values control the front; slower values keep more punch.
Bands Range: 8 to 64 Default: 32	Sets how many frequency slices carry the speech shape. More bands sound clearer; fewer bands sound more vintage.
Bypass Range: Off, On Default: Off	Turns the complete effect off or on for a direct before-and-after comparison.
Carrier Count Range: 2 to 100 Default: 3	Sets how many internal carrier voices are layered together.
Carrier Resonance Range: 0 to 100 Default: 50	Changes the sharpness and tonal focus of the internal carrier voices.
Carrier Tune Range: -24 to 24 Default: 0	Chooses the main note or tonal area used by this control.
Color Range: 0 to 100 Default: 30	Changes the overall brightness and tonal character.

Control and settings	What it changes
Detail Range: 0 to 100 Default: 65	Sets how much fine speech and transient detail is transferred.
Floor Range: -90 to -30 Default: -70	Sets how quiet the input can be before the transferred movement closes down.
Imprint Range: 0 to 100 Default: 100	Sets how strongly the articulation and rhythm of the input are printed onto the carrier.
Mix Range: 0 to 100 Default: 100	Blends the original sound with the processed sound.
Output Range: -18 to 6 Default: 0	Sets the final listening level after processing.
Pressure Range: 0 to 100 Default: 25	Adds density and firmness to the transferred envelope.
Program Range: 120 factory programs Default: Init	Loads a factory starting point. Adjust the controls afterward to fit the current sound.
Range High Range: 2000 to 18000 Default: 14000	Sets the highest frequency used to transfer articulation.
Range Low Range: 40 to 500 Default: 90	Sets the lowest frequency used to transfer articulation.
Release Range: 5 to 2000 Default: 50	Sets how quickly the effect relaxes after the sound becomes quieter.
Shift Range: -24 to 24 Default: 0	Moves the selected pitch or frequency structure upward or downward.

Control and settings	What it changes
Sibilance Range: 0 to 100 Default: 50	Restores or emphasizes consonants such as S and T for clearer words.
Sidechain Range: Off, On Default: Off	Uses an external sound as the carrier instead of the internal carrier.
Tone Range: -100 to 100 Default: 0	Makes the vocoder result darker or brighter.
Type Range: Vocoder, Whisper, Morph, Ring Mod, Invert Default: Vocoder	Chooses the sound character or processing style.
Warp Range: -100 to 100 Default: 0	Stretches or shifts the transferred frequency shape for a different vocal character.
Whiten Range: 0 to 100 Default: 75	Evens out the carrier spectrum so speech details transfer more clearly.
Width Range: 0 to 200 Default: 100	Sets the stereo spread of the processed sound.