Installing EVE-NG Client Pack:

EVE-NG Windows client pack installs everything necessary for working on/building labs on EVE-NG. It includes Wireshark installation, UltraVNC installation, PuTTY (used as default Telnet client), Plink (for Wireshark), and all necessary wrappers. Also, it will modify Windows registry files for proper work. First, you need to download the client pack to your PC from https://mega.nz/file/G5liXYzK#oaSC1Jrh5m0HaNkReirurtrXhIHGw6NOZX3jgus1xqo

Windows Client Side


Below one can find a Windows client side pack that will install everything necessary for running telnet, vnc, wireshark, rdp applications when working on/building labs on EVE-NGIt includes:

- · Wireshark 3.0.6.0 installation
- · UltraVNC 1.2.3.1 installation
- · putty 0.73 (used as default telnet client)
- · plink 0.73 (for wireshark)
- · all necessary wrappers
- · It will modify windows registry files for proper work
- . It will save all the files on the local PC if one would like to modify for example, using SecureCRT instead of default Putty.
- Windows 8 and 10 reg files to support tabbed SecureCRT
- . Auto detection of Windows version (7, 8, 10) (x64 only supported)


Download links:

Windows integration pack
Windows integration pack mirror

Run the installer. You do not need to install Wireshark or UltraVNC if you already installed.







License Agreement

Please read the following important information before continuing.



Please read the following License Agreement. You must accept the terms of this agreement before continuing with the installation.

GNU GENERAL PUBLIC LICENSE
Version 2, June 1991

Copyright (C) 1989, 1991 Free Software Foundation,
Inc. 59 Temple Place - Suite 330, Boston, MA
02111-1307, USA Everyone is permitted to copy and
distribute verbatim copies of this license
document, but changing it is not allowed.


Preamble

I do not accept the agreement


Next > Cancel



Even if you chose to install UltraVNC, only Viewer is required. By default, 3 components (Server, Viewer, Repeater) are checked for installation. You can uncheck the other two.



Once the installation is completed, the wrapper scripts are installed in C:\Program Files\EVE-NG as shown below.



Make sure remove NPCAP from Add or Remove Program and install WinPcap. It can be download from this link: https://www.winpcap.org/install/



Go to Add or remove programs make sure WinPcap is install.

