



Router0

Physical Config CLI Attributes

IOS Command Line Interface

```
Cisco Internetwork Operating System Software
IOS (tm) C2600 Software (C2600-I-M), Version 12.2(28), RELEASE SOFTWARE (fc5)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2005 by Cisco Systems, Inc.
Compiled Wed 27-Apr-04 19:01 by mhwang

Cisco 2621 (MPC860) processor (revision 0x200) with 253952K/8192K bytes of memory
.
Processor board ID JAD05100MTZ (4292891495)
M860 processor: part number 0, mask 49
Bridging software.
X.25 software, Version 3.0.0.
4 Ethernet/IEEE 802.3 interface(s)
2 FastEthernet/IEEE 802.3 interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>enable
Router#show ip interface brief


```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	unassigned	YES	unset	administratively down	down
FastEthernet0/1	unassigned	YES	unset	administratively down	down
Ethernet1/0	unassigned	YES	unset	administratively down	down
Ethernet1/1	unassigned	YES	unset	administratively down	down
Ethernet1/2	unassigned	YES	unset	administratively down	down
Ethernet1/3	unassigned	YES	unset	administratively down	down

Router#

Copy Paste

☐ Top



Router0

--- System Configuration Dialog ---

```
Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>enable
Router#show ip interface brief

```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	unassigned	YES	unset	administratively down	down
FastEthernet0/1	unassigned	YES	unset	administratively down	down
Ethernet1/0	unassigned	YES	unset	administratively down	down
Ethernet1/1	unassigned	YES	unset	administratively down	down
Ethernet1/2	unassigned	YES	unset	administratively down	down
Ethernet1/3	unassigned	YES	unset	administratively down	down

```
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface fastEthernet0/0
Router(config-if)#ip add 50.0.0.1 255.0.0.0
Router(config-if)#no shutdown


Router(config-if)#
%LINK-3-UPDOWN: Interface FastEthernet0/0, changed state to down

```

Router(config-if)#

Copy Paste

☐ Top



```
Router0

Press RETURN to get started.

Router>enable
Router#show ip interface brief
Interface      IP-Address      OK? Method Status        Protocol
FastEthernet0/0 50.0.0.1        YES manual    up            up
FastEthernet0/1 unassigned      YES unset     administratively down down
Ethernet1/0      unassigned      YES unset     administratively down down
Ethernet1/1      unassigned      YES unset     administratively down down
Ethernet1/2      unassigned      YES unset     administratively down down
Ethernet1/3      unassigned      YES unset     administratively down down
Router#
```





```
Router0

Press RETURN to get started.

Router>ping 50.0.0.10

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 50.0.0.10, timeout is 2 seconds:
..!!!!
Success rate is 80 percent (4/5), round-trip min/avg/max = 0/0/0 ms

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#use thanush password thanush
Router(config)#line console 0
Router(config-line)#login local
Router(config-line)#
```





```
Router0
Translating "enablr"...domain server (255.255.255.255)
% Unknown command or computer name, or unable to find computer address

Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#no user
% Incomplete command.
Router(config)#no username
% Incomplete command.
Router(config)#no username no password
Router(config)#line console 0
Router(config-line)#no login local
Router(config-line)#
```

Copy Paste

☐ Top



```
Router0

Press RETURN to get started.

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#line console 0
Router(config-line)#password thanush
Router(config-line)#login
Router(config-line)#
```

Copy Paste

☐ Top



```
Router0


Router con0 is now available

Press RETURN to get started.

User Access Verification
Password: |

Copy Paste

Top
```



```
Router0


User Access Verification
Password:

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#line console 0
^
% Invalid input detected at '^' marker.

Router(config)#line console 0
Router(config-line)#no password
Router(config-line)#no login
Router(config-line)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Copy Paste

Top
```



```
Router0

Router>
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#
Router(config)#enable secret router123
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#exit
```

Copy Paste

☐ Top



```
Router0


Router con0 is now available

Press RETURN to get started.

Router>enable
Password:
```

Copy Paste

☐ Top




```

Router0
Router>
Router>
Router>
Router>
Router>
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#line vty 0 4
Router(config-line)#password thanush
Router(config-line)#login
Router(config-line)#transport inout telnet
Router(config-line)#transport input telnet
Router(config-line)#exit
Router(config)#
  
```

Copy Paste

Top



```

PC0
Reply from 50.0.0.1: bytes=32 time<1ms TTL=255
Reply from 50.0.0.1: bytes=32 time<1ms TTL=255
Reply from 50.0.0.1: bytes=32 time<1ms TTL=255
Reply from 50.0.0.1: bytes=32 time<1ms TTL=255

Ping statistics for 50.0.0.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>tel 50.0.0.1
Invalid Command.

C:\>telnet 50.0.0.1
Trying 50.0.0.1 ...Open

[connection to 50.0.0.1 closed by foreign host]
C:\>telnet 50.0.0.1
Trying 50.0.0.1 ...Open

[connection to 50.0.0.1 closed by foreign host]
C:\>
C:\>telnet 50.0.0.1
Trying 50.0.0.1 ...Open

User Access Verification

Password:
Router>
  
```

Top