

Translating "confih"

Translating "confih"

% Bad IP address or host name

% Unknown command or computer name, or unable to find computer address

HO-EDGE#config

Configuring from terminal, memory, or network [terminal]? t

Enter configuration commands, one per line. End with CNTL/Z.

HO-EDGE(config)#int tunnel 1

HO-EDGE(config-if)#ip add

*Sep 21 14:42:14.193: %LINEPROTO-5-UPDOWN: Line protocol on Interface Tunnel1, changed state to down

HO-EDGE(config-if)#ip add 1.0.0.1 255.0.0.0

HO-EDGE(config-if)#tunnel source 20.0.0.1

HO-EDGE(config-if)#tunnel destination 30.0.0.2

HO-EDGE(config-if)#exi

*Sep 21 14:42:51.043: %LINEPROTO-5-UPDOWN: Line protocol on Interface Tunnel1, changed state to up

HO-EDGE(config-if)#exit

HO-EDGE(config)#

HO-EDGE(config)#

HO-EDGE(config)#

HO-EDGE(config)#ip route 192.168.1.0 255.255.255.0 tunnel 1

HO-EDGE(config)#exit

HO-EDGE#

HO-EDGE#

HO-EDGE#

*Sep 21 14:43:23.302: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)

HO-EDGE#

*Sep 21 14:43:23.953: %SYS-5-CONFIG_I: Configured from console by console

HO-EDGE#

DC-EDGE



```
DC-EDGE#
DC-EDGE#
DC-EDGE#
DC-EDGE#
DC-EDGE#
DC-EDGE#conf t
Enter configuration commands, one per line. End with CNTL/Z.
DC-EDGE(config)#ip route 0.0.0.0 0.0.
*Sep 21 14:45:43.417: %LINK-3-UPDOWN: Interface Ethernet0/2, changed state to down
*Sep 21 14:45:43.418: %LINK-3-UPDOWN: Interface Ethernet0/3, changed state to down
*Sep 21 14:45:44.417: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/2, changed state to down
*Sep 21 14:45:44.422: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/3, changed state to down
DC-EDGE(config)#ip route 0.0.0.0 0.0.0.0 30.0.0.1
DC-EDGE(config)#int tunnel 1
DC-EDGE(config-if)#ip ad
*Sep 21 14:46:06.966: %LINEPROTO-5-UPDOWN: Line protocol on Interface Tunnel1, changed state to down
DC-EDGE(config-if)#ip add 1.0.0.2 255.0.0.0
DC-EDGE(config-if)#tunnel source 30.0.0.2
DC-EDGE(config-if)#tunnel destination 20.0.0.1
DC-EDGE(config-if)#
*Sep 21 14:46:48.361: %LINEPROTO-5-UPDOWN: Line protocol on Interface Tunnel1, changed state to up
DC-EDGE(config-if)#exit
DC-EDGE(config)#
DC-EDGE(config)#ip route 10.0.0.0 255.0.0.0 tunnel 1
DC-EDGE(config)#exit
DC-EDGE#
*Sep 21 14:47:18.138: %SYS-5-CONFIG_I: Configured from console by console
DC-EDGE#
```

