

Router

```
*Aug 22 04:45:30.679: unix_l1_sock_notify: Invalid L1 socket file descriptor fd = 6
*Aug 22 04:45:30.679: unix_l1_sock_notify: Invalid L1 socket file descriptor fd = 6
*Aug 22 04:45:30.679: unix_l1_sock_notify: Invalid L1 socket file descriptor fd = 6
*Aug 22 04:45:30.679: unix_l1_sock_notify: Invalid L1 socket file descriptor fd = 6
*Aug 22 04:45:30.679: unix_l1_sock_notify: Invalid L1 socket file descriptor fd = 6
*Aug 22 04:45:30.679: unix_l1_sock_notify: Invalid L1 socket file descriptor fd = 6
*Aug 22 04:45:30.679: unix_l1_sock_notify: Invalid L1 socket file descriptor fd = 6

*Aug 22 04:45:36.778: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/0, changed state to up
*Aug 22 04:45:36.779: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/1, changed state to up
*Aug 22 04:45:36.779: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/2, changed state to up
*Aug 22 04:45:36.779: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/3, changed state to up
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#
*Aug 22 04:45:47.863: %LINK-3-UPDOWN: Interface Ethernet0/2, changed state to down
*Aug 22 04:45:47.864: %LINK-3-UPDOWN: Interface Ethernet0/3, changed state to down
*Aug 22 04:45:48.864: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/2, changed state to down
*Aug 22 04:45:48.864: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/3, changed state to down
Router(config)#int e0/0
Router(config-if)#ip add 50.0.0.1 255.0.0.0
Router(config-if)#no sh
Router(config-if)#exit
Router(config)#int e0/1
Router(config-if)#ip add 60.0.0.1 255.0.0.0
Router(config-if)#no sh
Router(config-if)#exit
Router(config)#
```

Router

```
*Aug 22 04:45:30.679: unix_l1_sock_notify: Invalid L1 socket file descriptor fd = 6
*Aug 22 04:45:30.679: unix_l1_sock_notify: Invalid L1 socket file descriptor fd = 6
*Aug 22 04:45:36.778: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/0, changed state to up
*Aug 22 04:45:36.779: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/1, changed state to up
*Aug 22 04:45:36.779: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/2, changed state to up
*Aug 22 04:45:36.779: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/3, changed state to up
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#
*Aug 22 04:45:47.863: %LINK-3-UPDOWN: Interface Ethernet0/2, changed state to down
*Aug 22 04:45:47.864: %LINK-3-UPDOWN: Interface Ethernet0/3, changed state to down
*Aug 22 04:45:48.864: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/2, changed state to down
*Aug 22 04:45:48.864: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/3, changed state to down
Router(config)#int e0/0
Router(config-if)#ip add 50.0.0.1 255.0.0.0
Router(config-if)#no sh
Router(config-if)#exit
Router(config)#int e0/1
Router(config-if)#ip add 60.0.0.1 255.0.0.0
Router(config-if)#no sh
Router(config-if)#exit
Router(config)#exit
Router#sjo
*Aug 22 04:47:37.488: %SYS-5-CONFIG_I: Configured from console by console
Router#show ip interface brief
Interface                IP-Address      OK? Method Status      Protocol
Ethernet0/0              50.0.0.1        YES manual up          up
Ethernet0/1              60.0.0.1        YES manual up          up
Ethernet0/2              unassigned      YES TFTP  down        down
Ethernet0/3              unassigned      YES TFTP  down        down
Router#
```

















