




Router0

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/1
Router(config-if)#ip add 50.0.0.1 255.255.255.0
Router(config-if)#no sh

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

Router(config-if)#ex
Router(config)#int fa0/0
Router(config-if)#ip add 50.0.1.198 255.255.255.252
Router(config-if)#no sh

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#
Router(config)#ex
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router#
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 50.0.1.0 255.255.255.128 50.0.1.197
Router(config)#ip route 50.0.1.128 255.255.255.192 50.0.1.197
Router(config)#
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#ex
```

Copy

Paste

☐ Top

DHCP Router — Router 0

Router0

Physical

Config

CLI

Attributes

IOS Command Line Interface

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip dhcp pool Sales
Router(dhcp-config)#network 50.0.0.0 255.255.255.0
Router(dhcp-config)#default-router 50.0.0.1
Router(dhcp-config)#dns-server 8.8.8.8
Router(dhcp-config)#exit
Router(config)#ip dhcp excluded-address 50.0.0.1 50.0.0.10
Router(config)#ex
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip dhcp pool Production
Router(dhcp-config)#network 50.0.1.0 255.255.255.192
Router(dhcp-config)#default-router 50.0.1.1
Router(dhcp-config)#dns-server 8.8.8.8
Router(dhcp-config)#exit
Router(config)#ip dhcp excluded-address 50.0.1.1 50.0.1.10
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console


Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip dhcp pool HR
Router(dhcp-config)#network 50.0.1.128 255.255.255.192
Router(dhcp-config)#default-router 50.0.1.129
Router(dhcp-config)#dns-server
% Incomplete command.
Router(dhcp-config)#dns-server 8.8.8.8
Router(dhcp-config)#exit
Router(config)#ip dhcp excluded-address 50.0.1.129 50.0.1.135
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#
Router#show ip dhcp binding
IP address      Client-ID/
                Hardware address
                Lease expiration
                Type
```

Copy

Paste

☐ Top



Router1

Physical Config CLI Attributes

IOS Command Line Interface

Press RETURN to get started!

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/0
Router(config-if)#ip add 50.0.1.1 255.255.255.128
Router(config-if)#no sh

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#ex
Router(config)#int fa0/1
Router(config-if)#ip add 50.0.1.194 255.255.255.252
Router(config-if)#no sh

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

Router(config-if)#ex
Router(config)#int fa0/2
%Invalid interface type and number
Router(config)#ip add 50.0.1.197 255.255.255.252
      ^
% Invalid input detected at '^' marker.

Router(config)#int e1/0
Router(config-if)#ip add 50.0.1.197 255.255.255.252
Router(config-if)#no sh

Router(config-if)#
%LINK-5-CHANGED: Interface Ethernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet1/0, changed state to up

Router(config-if)#ex
Router(config)#exi
Router#
%SYS-5-CONFIG_I: Configured from console by console
```

Copy

Paste

☐ Top

Router2

Physical Config CLI Attributes

IOS Command Line Interface

```
Router(config-if)#no sh

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#ex
Router(config)#int fa0/1
Router(config-if)#ip add 50.0.1.193 255.255.255.252
Router(config-if)#no sh

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

Router(config-if)#ex
Router(config)#
Router(config)#ex
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 50.0.1.0 255.255.255.128 50.0.1.194
Router(config)#ip route 50.0.0.0 255.255.255.0 50.0.1.194
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/0
Router(config-if)#ip helper address 50.0.0.1
      ^
% Invalid input detected at '^' marker.

Router(config-if)#ip helper-address 50.0.0.1
Router(config-if)#exit
Router(config)#
```

Copy

Paste

☐ Top

```
PC0
Reply from 50.0.0.11: bytes=32 time=15ms TTL=125
Reply from 50.0.0.11: bytes=32 time=8ms TTL=125

Ping statistics for 50.0.0.11:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 15ms, Average = 6ms

C:\>ipconfig

FastEthernet0 Connection:(default port)

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: FE80::290:2BFF:FED0:5825
    IPv6 Address . . . . .: ::
    IPv4 Address . . . . .: 50.0.1.136
    Subnet Mask . . . . .: 255.255.255.192
    Default Gateway . . . . .: ::
                                   50.0.1.129

Bluetooth Connection:

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: ::
    IPv6 Address . . . . .: ::
    IPv4 Address . . . . .: 0.0.0.0
    Subnet Mask . . . . .: 0.0.0.0
    Default Gateway . . . . .: ::
                                   0.0.0.0

C:\>
```

☐ Top

PC1

C:\>ipconfig /renew

IP Address.....: 50.0.1.137

Subnet Mask.....: 255.255.255.192

Default Gateway...: 50.0.1.129

DNS Server.....: 8.8.8.8

C:\>ipconfig

FastEthernet0 Connection:(default port)

Connection-specific DNS Suffix..:

Link-local IPv6 Address.....: FE80::2D0:D3FF:FE2E:9D78

IPv6 Address.....: ::

IPv4 Address.....: 50.0.1.137

Subnet Mask.....: 255.255.255.192

Default Gateway.....: ::

50.0.1.129

Bluetooth Connection:

Connection-specific DNS Suffix..:

Link-local IPv6 Address.....: ::

IPv6 Address.....: ::

IPv4 Address.....: 0.0.0.0

Subnet Mask.....: 0.0.0.0

Default Gateway.....: ::

0.0.0.0

C:\>

☐ Top

PC2

C:\>ipconfig /renew

IP Address.....: 50.0.1.11
Subnet Mask.....: 255.255.255.192
Default Gateway.....: 50.0.1.1
DNS Server.....: 8.8.8.8

C:\>ipconfig

FastEthernet0 Connection:(default port)

Connection-specific DNS Suffix...:
Link-local IPv6 Address.....: FE80::200:CFF:FEFE:8815
IPv6 Address.....: ::
IPv4 Address.....: 50.0.1.11
Subnet Mask.....: 255.255.255.192
Default Gateway.....: ::
50.0.1.1

Bluetooth Connection:

Connection-specific DNS Suffix...:
Link-local IPv6 Address.....: ::
IPv6 Address.....: ::
IPv4 Address.....: 0.0.0.0
Subnet Mask.....: 0.0.0.0
Default Gateway.....: ::
0.0.0.0

C:\>

☐ Top

PC3

C:\>ipconfig /renew

IP Address.....: 50.0.1.12
Subnet Mask.....: 255.255.255.192
Default Gateway...: 50.0.1.1
DNS Server.....: 8.8.8.8

C:\>ipconfig

FastEthernet0 Connection:(default port)

Connection-specific DNS Suffix...:
Link-local IPv6 Address.....: FE80::260:70FF:FE53:6743
IPv6 Address.....: ::
IPv4 Address.....: 50.0.1.12
Subnet Mask.....: 255.255.255.192
Default Gateway.....: ::
50.0.1.1

Bluetooth Connection:

Connection-specific DNS Suffix...:
Link-local IPv6 Address.....: ::
IPv6 Address.....: ::
IPv4 Address.....: 0.0.0.0
Subnet Mask.....: 0.0.0.0
Default Gateway.....: ::
0.0.0.0

C:\>|

☐ Top

PC4

```
C:\>ipconfig /renew

IP Address.....: 50.0.0.11
Subnet Mask.....: 255.255.255.0
Default Gateway...: 50.0.0.1
DNS Server.....: 8.8.8.8

C:\>ipconfig

FastEthernet0 Connection:(default port)

Connection-specific DNS Suffix...:
Link-local IPv6 Address.....: FE80::202:17FF:FEAE:497D
IPv6 Address.....: ::
IPv4 Address.....: 50.0.0.11
Subnet Mask.....: 255.255.255.0
Default Gateway.....: ::
                        50.0.0.1

Bluetooth Connection:

Connection-specific DNS Suffix...:
Link-local IPv6 Address.....: ::
IPv6 Address.....: ::
IPv4 Address.....: 0.0.0.0
Subnet Mask.....: 0.0.0.0
Default Gateway.....: ::
                        0.0.0.0

C:\>
```

☐ Top

PC5

C:\>ipconfig /renew

IP Address.....: 50.0.0.12
Subnet Mask.....: 255.255.255.0
Default Gateway...: 50.0.0.1
DNS Server.....: 8.8.8.8

C:\>ipconfig

FastEthernet0 Connection:(default port)

Connection-specific DNS Suffix...:
Link-local IPv6 Address.....: FE80::20A:41FF:FE07:2953
IPv6 Address.....: ::
IPv4 Address.....: 50.0.0.12
Subnet Mask.....: 255.255.255.0
Default Gateway.....: ::
50.0.0.1

Bluetooth Connection:

Connection-specific DNS Suffix...:
Link-local IPv6 Address.....: ::
IPv6 Address.....: ::
IPv4 Address.....: 0.0.0.0
Subnet Mask.....: 0.0.0.0
Default Gateway.....: ::
0.0.0.0

C:\>

☐ Top