

```
HO-EDGE(config)#int e0/0
HO-EDGE(config-if)#ip add 10.0.0.1 255.0.0.0
HO-EDGE(config-if)#ip nat inside
HO-EDGE(config-if)#no sh
HO-EDGE(config-if)#ex
HO-EDGE(config)#
*Sep 16 08:47:07.488: %LINEPROTO-5-UPDOWN: Line protocol on Interface NVI0, changed state to up
HO-EDGE(config)#int e0/1
HO-EDGE(config-if)#ip add 20.0.0.1 255.0.0.0
HO-EDGE(config-if)#ip nat outside
HO-EDGE(config-if)#no sh
HO-EDGE(config-if)#ex
HO-EDGE(config)#exit
HO-EDGE#
HO-EDGE#
*Sep 16 08:47:29.201: %SYS-5-CONFIG_I: Configured from console by console
HO-EDGE#conf t
Enter configuration commands, one per line. End with CNTL/Z.
HO-EDGE(config)#ip route 0.0.0.0 0.0.0.0 20.0.0.2
HO-EDGE(config)#exit
HO-EDGE#
HO-EDGE#
HO-EDGE#
*Sep 16 08:47:46.792: %SYS-5-CONFIG_I: Configured from console by console
HO-EDGE#conf t
Enter configuration commands, one per line. End with CNTL/Z.
HO-EDGE(config)#access-list 10 permit 10.0.0.0 0.255.255.255
HO-EDGE(config)#ip nat inside source list 10 int e0/1 overload
HO-EDGE(config)#exit
HO-EDGE#
HO-EDGE#
HO-EDGE#
*Sep 16 08:48:25.866: %SYS-5-CONFIG_I: Configured from console by console
HO-EDGE#conf t
Enter configuration commands, one per line. End with CNTL/Z.
HO-EDGE(config)#ip dhcp pool Office
HO-EDGE(dhcp-config)#network 10.0.0.0 255.0.0.0
HO-EDGE(dhcp-config)#default-router 10.0.0.1
HO-EDGE(dhcp-config)#dns-server 8.8.8.8
HO-EDGE(dhcp-config)#exit
HO-EDGE(config)#exit
HO-EDGE#
HO-EDGE#
HO-EDGE#
HO-EDGE#
*Sep 16 08:49:16.764: %SYS-5-CONFIG_I: Configured from console by console
HO-EDGE#
*Sep 16 08:51:33.588: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
HO-EDGE#
```

DC-EDGE

```
Enter configuration commands, one per line. End with CNTL/Z.
DC-EDGE(config)#int e0/0
DC-EDGE(config-if)#ip add 192.168.1.1 255.255.255.0
DC-EDGE(config-if)#ip nat inside
DC-EDGE(config-if)#no sh
DC-EDGE(config-if)#
*Sep 16 08:58:02.156: %LINEPROTO-5-UPDOWN: Line protocol on Interface NVI0, changed state to up
DC-EDGE(config-if)#ex
DC-EDGE(config)#int e0/1
DC-EDGE(config-if)#ip add 30.0.0.2 255.0.0.0
DC-EDGE(config-if)#ip nat outside
DC-EDGE(config-if)#no sh
DC-EDGE(config-if)#ex
DC-EDGE(config)#exit
DC-EDGE#
*Sep 16 08:58:34.469: %SYS-5-CONFIG_I: Configured from console by console
DC-EDGE#show ip int brief
Interface                IP-Address      OK? Method Status        Protocol
Ethernet0/0              192.168.1.1     YES manual up            up
Ethernet0/1              30.0.0.2        YES manual up            up
Ethernet0/2              unassigned      YES TFTP  down          down
Ethernet0/3              unassigned      YES TFTP  down          down
NVI0                     192.168.1.1     YES unset up            up
DC-EDGE#
*Sep 16 08:58:57.181: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
DC-EDGE#conf t
Enter configuration commands, one per line. End with CNTL/Z.
DC-EDGE(config)#ip route 0.0.0.0 0.0.0.0 30.0.0.1
DC-EDGE(config)#exit
DC-EDGE#
DC-EDGE#
DC-EDGE#co
*Sep 16 08:59:26.517: %SYS-5-CONFIG_I: Configured from console by console
DC-EDGE#conf t
Enter configuration commands, one per line. End with CNTL/Z.
DC-EDGE(config)#ip nat inside source static 192.168.1.10 30.0.0.10
DC-EDGE(config)#ip nat inside source static 192.168.1.20 30.0.0.11
DC-EDGE(config)#exit
DC-EDGE#
DC-EDGE#
DC-EDGE#
DC-EDGE#
*Sep 16 09:00:36.608: %SYS-5-CONFIG_I: Configured from console by console
DC-EDGE#disable
DC-EDGE>ping 20.0.0.1
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 20.0.0.1, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms
```



