

AV Team — Deck Playback Guide

One PowerPoint file. Two playback modes: pre-event loop and event.

BEFORE DOORS OPEN — START THE PRE-EVENT LOOP

- 1 Open Deck.pptx in PowerPoint (desktop). Google Slides and Keynote do not support the auto-advance timings — use Microsoft PowerPoint.
- 2 Go to Slide Show menu › Set Up Slide Show.
- 3 Under Show slides, choose Custom show › Pre-Event Loop. Under Show options, check Loop continuously until 'Esc'. Under Advance slides, choose Using timings, if present. Click OK.
- 4 Press F5 (or Slide Show menu › From Beginning). Slides 1–5 will cycle every 15 seconds, hands-free, until you press Esc.

The two Custom Shows (Pre-Event Loop and Event) are already saved inside the deck. No setup needed — just pick them from the Custom show dropdown.

WHEN THE EMCEE IS READY TO START — SWITCH TO THE EVENT

- 1 Press Esc to exit the pre-event loop.
- 2 Go to Slide Show menu › Set Up Slide Show. Under Show slides, choose Custom show › Event. Under Show options, uncheck "Loop continuously." Under Advance slides, choose Manually. Click OK.
- 3 Press F5. The deck opens on slide 6 (emcee open). Click or press space to advance from here on out.

BREAK COUNTDOWN TIMERS

The break slides show a static number (20:00, 15:00). For a live countdown, open the companion timer page on a second laptop or a monitor visible to the emcee: eosnorthtexas.com/timer. Presets for 10 / 15 / 20 / 25 minutes; press spacebar to start/pause, R to reset, F for fullscreen.

QUICK REFERENCE

Deck file	Deck.pptx (27 slides, 16:9)
Playback app	Microsoft PowerPoint (desktop) — required for timings
Pre-event loop	Slides 1–5, auto-advance 15s, loop until Esc
Event show	Slides 6–27, manual click-to-advance
Break timer URL	eosnorthtexas.com/timer
Backup handoff	If timings misfire, click through slides 1–5 manually

IF SOMETHING GOES WRONG

- Slides don't auto-advance: Set Up Slide Show › Advance slides › select Using timings, if present.
- Loop doesn't restart: Set Up Slide Show › Show options › check Loop continuously until 'Esc'.
- Wrong slide range playing: Set Up Slide Show › Show slides › Custom show › pick the right one.
- PowerPoint online / Google Slides opened it: Download and open the file in desktop PowerPoint instead.