

# AV Team — Deck Playback Guide

One PowerPoint file. Two playback modes: pre-event loop and event.

## BEFORE DOORS OPEN — START THE PRE-EVENT LOOP

- 1 Open Deck.pptx in PowerPoint (desktop). Google Slides and Keynote do not support the auto-advance timings — use Microsoft PowerPoint.
- 2 Go to Slide Show menu › Set Up Slide Show.
- 3 Under Show slides, choose Custom show › Pre-Event Loop. Under Show options, check Loop continuously until 'Esc'. Under Advance slides, choose Using timings, if present. Click OK.
- 4 Press F5 (or Slide Show menu › From Beginning). Slides 1–5 will cycle every 15 seconds, hands-free, until you press Esc.

The two Custom Shows (Pre-Event Loop and Event) are already saved inside the deck. No setup needed — just pick them from the Custom show dropdown.

## WHEN THE EMCEE IS READY TO START — SWITCH TO THE EVENT

- 1 Press Esc to exit the pre-event loop.
- 2 Go to Slide Show menu › Set Up Slide Show. Under Show slides, choose Custom show › Event. Under Show options, uncheck "Loop continuously." Under Advance slides, choose Manually. Click OK.
- 3 Press F5. The deck opens on slide 6 (emcee open). Click or press space to advance from here on out.

## SPEAKER DECK HANDOFFS — TWO SESSIONS OPEN AN EXTERNAL FILE

Two sessions do not present from inside the master deck. When you reach their canvas slide, the slide itself will say OPEN PRESENTER DECK and name the file. Follow these steps:

- 1 When the emcee finishes the intro and you land on the OPEN PRESENTER DECK slide, press Esc to exit the show.
- 2 Double-click the named file inside the speaker-decks\ folder (same folder as Deck.pptx):
  - Walt Brown (12:00 lunch): Profit-Power-Deck.pptx
  - Mark C. Winters (4:45 closer): 10-Pillars-of-Visionary-Greatness.pptx
- 3 Press F5 in the speaker file to run their deck. The presenter drives it.
- 4 When the session ends, press Esc, close the speaker file, switch back to Deck.pptx, and resume the Event custom show on the next slide (press F5, then use 'By slide' or advance from the current slide).

Both speaker files must be copied to the presentation laptop before the event, in the speaker-decks\ folder sitting next to Deck.pptx. The master deck references them by filename only.

## BREAK COUNTDOWN TIMERS

The break slides show a static number (20:00, 15:00). For a live countdown, open the companion timer page on a second laptop or a monitor visible to the emcee: [eosnorthtexas.com/timer](https://eosnorthtexas.com/timer). Presets for 10 / 15 / 20 / 25 minutes; press spacebar to start/pause, R to reset, F for fullscreen.

## QUICK REFERENCE

|                        |                                                                       |
|------------------------|-----------------------------------------------------------------------|
| <b>Deck file</b>       | Deck.pptx (27 slides, 16:9)                                           |
| <b>Playback app</b>    | Microsoft PowerPoint (desktop) — required for timings                 |
| <b>Pre-event loop</b>  | Slides 1–5, auto-advance 15s, loop until Esc                          |
| <b>Event show</b>      | Slides 6–27, manual click-to-advance                                  |
| <b>Speaker decks</b>   | speaker-decks\ folder — Walt (slide 16), Winters (slide 26)           |
| <b>Break timer URL</b> | <a href="https://eosnorthtexas.com/timer">eosnorthtexas.com/timer</a> |
| <b>Backup handoff</b>  | If timings misfire, click through slides 1–5 manually                 |

## IF SOMETHING GOES WRONG

- Slides don't auto-advance: Set Up Slide Show › Advance slides › select Using timings, if present.
- Loop doesn't restart: Set Up Slide Show › Show options › check Loop continuously until 'Esc'.
- Wrong slide range playing: Set Up Slide Show › Show slides › Custom show › pick the right one.
- PowerPoint online / Google Slides opened it: Download and open the file in desktop PowerPoint instead.