
1. نصب و راه اندازی داکر و WLS

ابتدا نرم افزار docker را از لینک زیر دانلود و نصب کنید. مراحل نصب به شرح زیر میباشد.

https://www.docker.com/products/docker-desktop



O Installing Docker Desktop 4.31.1 (153621)

- o ×

Docker Desktop 4.31.1

Installing...

Deploying component: Use WSL 2 Instead of Hyper-V (recommended)
Deploying component: Create docker-users group
Unpacing file: System.Nim/David.Document.dll
Unpacing file: System.Nim/David.Document.dll
Unpacing file: System.Nim/David.dll
Unpacing file: System.Nim/Bavid.dll
Unpacing file: System.Nimerading.Time.dll
Unpacing file: System.Security.Cryptography.2509Certificates.dll
Unpacing file: System.Security.Cryptography.2509Certificates.dll
Unpacing file: System.Security.Cryptography.2607.dll
Unpacing file: System.Security.Cryptography


O Installing Docker Desktop 4.31.1 (153621)

- 0 X

Docker Desktop 4.31.1

Installation succeeded

Close and restart



Docker Subscription Service Agreement

Commercial use of Docker Desktop at a company of more than 250 employees OR more than \$10 million in annual revenue requires a paid subscription (Pro, Team, or Business). See subscription details ☑



Accept

Close



Finish setting up Docker Desktop

version 4.31.1 (153621)

Complete the installation of Docker Desktop.


Use recommended settings (requires administrator password)


Docker Desktop automatically sets the necessary configurations that work for most developers.


O Use advanced settings

You manually set your preferred configurations.

Finish







2. ساخت كانتينر مربوط به برنامه

- سپس در مسیر اصلی برنامه یک ترمینال باز کرده و دستور زیر را در آن اجرا میکنیم.

docker compose up --build

- در نهایت خروجی زیر در ترمینال نمایش داده میشود:

- به یاد داشته باشید که حتما دی ان اس 403.online بر روی نتورک سیستم تان فعال باشد.

دی ان اس های 403 به شرح زیر میباشند:

10.202.10.202 10.202.10.102

3 دريافت اطلاعات

- برای آپدیت کردن اطلاعات ذخیره شده روی سرور باید یک http request با متد GET به api داخلی /http://127.0.0.1:5000/update ارسال شود.
 - برای دریافت اطلاعات هواشناسی از طریق ریکوعست به api ی

در صورت وجود دریافت میشوند.