Other tips

This document describes some useful tips, which may be helpful in reproduction.

Page Heap

Page Heap is a kind of mechanism that Windows system implements to check if a software has heap overflow or other similar problems. Page Heap will slow down the execution of software greatly, so we only turn on Page Heap feature when fuzzing.

The detailed information could be found at (https://docs.microsoft.com/en-us/windows-hardwar e/drivers/debugger/gflags-and-pageheap)

how to use

turn on Page Heap (we use Adobe Reader as an example)

1. open cmd.exe

```
C:\Windows\system32\cmd.exe

Microsoft Windows [Version 6.3.9600]
(c) 2013 Microsoft Corporation. All rights reserved.


C:\Users\wxy>__

Local DISK (C:)
```

2. execute the following command


```
"C:\Program Files (x86)\Windows Kits\8.1\Debuggers\x86\gflags.exe" /p /enable "C:\Program Files (x86)\Adobe\Acrobat Reader DC\Reader\AcroRd32.exe"
```

3. click yes




turn off Page Heap

1. open cmd.exe



2. execute the following command

"C:\Program Files (x86)\Windows Kits\8.1\Debuggers\x86\gflags.exe" /p /disable
"C:\Program Files (x86)\Adobe\Acrobat Reader DC\Reader\AcroRd32.exe"



useful commands


```
turn on Page Heap on Adobe
"C:\Program Files (x86)\Windows Kits\8.1\Debuggers\x86\gflags.exe" /p /enable
"C:\Program Files (x86)\Adobe\Acrobat Reader DC\Reader\AcroRd32.exe"
turn off Page Heap on Adobe
"C:\Program Files (x86)\Windows Kits\8.1\Debuggers\x86\gflags.exe" /p /disable
"C:\Program Files (x86)\Adobe\Acrobat Reader DC\Reader\AcroRd32.exe"
turn on Page Heap on Foxit(version 10.1.1)
"C:\Program Files (x86)\Windows Kits\8.1\Debuggers\x86\gflags.exe" /p /enable
"C:\Program Files (x86)\Foxit Software\Foxit Reader\FoxitReader.exe"
turn off Page Heap off Foxit(version 10.1.1)
"C:\Program Files (x86)\Windows Kits\8.1\Debuggers\x86\gflags.exe" /p /disable
"C:\Program Files (x86)\Foxit Software\Foxit Reader\FoxitReader.exe"
turn on Page Heap on Foxit(version 11.2.1)
"C:\Program Files (x86)\Windows Kits\8.1\Debuggers\x86\gflags.exe" /p /enable
"C:\Program Files (x86)\Foxit Software\Foxit PDF Reader\FoxitPDFReader.exe"
turn off Page Heap on Foxit(version 11.2.1)
"C:\Program Files (x86)\Windows Kits\8.1\Debuggers\x86\gflags.exe" /p /disable
"C:\Program Files (x86)\Foxit Software\Foxit PDF Reader\FoxitPDFReader.exe"
```


Priviledge Location Setting in PDF Reader

Normally, some binding calls in the PDF Readers can not be called, in consideration of security risk, so we need to add our tool's path to priviledge location. Next we will talk about how to do it.


Adobe Reader

1. Open Adobe Reader, click Edit->Preference







3. click Add Folder Path



4. choose our tool's path and click OK




5. After it, we can see that our tool's path has been added to priviledge location, then click OK button




Foxit Reader


1. Open Foxit Reader, click File



2. click Preferences, then click Security



3. click Add Folder Path, choose our tool's path, and click OK button



4. now we can see that our tool's path has been added to priviledge location, then click OK button

