

-
-
-
-
-

Chapter 1

Maintenance



Drinks Transport Planning Maintenance Functions

As Drinks Transport Planning is an advanced application module, much of the primary data such as customers and items have already been set up as part of the base modules. There is, however, additional information which must be entered, for example to the Descriptions file in Drinks Inventory Management. This is described in the section, 'Drinks Transport Planning Configuration'.

In Drinks Transport Planning, the Company Profile and Planner Profiles are set up from the Utilities options.

The Maintenance options allow you to set up separate reference data per transport centre, allowing each the flexibility of defining its own routes, carriers, delivery points, areas and rating policies. There is the option (**F20**) to change the transport centre that you are dealing with.

Company Profile Maintenance



1/DTU

Company Profile Maintenance allows the maintenance of reference data that will control the processing of transport order requirements when the planner is signed onto a particular company.

Company Profile Maintenance Selection Screen



Select the Company Profile Maintenance option.

This displays the Selection Screen which is used to select the company to maintain.

Company Code

Transport company code. You may maintain details for an existing transport company or enter a new transport company.



Press **Enter** to display the first Company Profile Maintenance Detail Screen.

Company Profile Maintenance Details Screen 1



This screen is displayed when you have entered a valid company code into the Company Profile Maintenance Selection Screen and pressed **Enter**.

At the top of the Screen, the company code entered in the Company Profile Maintenance Selection Screen is displayed.

TP900B	User GALBRAIJ	11/09/95
		16:15:45
Maintain Company Profile		
Company code	HW	
Company name	Handy Wholesalers Ltd.	
Address	Unit 2, Telford Industrial Estate	
Post code		
Container decimals	0 (0-2)	
Weight decimals	2 (0-3)	
Volume decimals	2 (0-3)	
Load numbers per centre	1 (0=No,1=Yes)	
Load number prefix	H	
Load number range	1 999999	
F3=Exit F8=Update F11=Delete F12=Previous		
07-31	SE	MW KS IM II KENB20A PED171S1

Fields:

Company Name/ Address/ - Details for the selected code are displayed.

Post Code

Name, address and post code for the transport company.

Container Decimals

Indicate the number of decimal places that will be significant for transport containers. You may enter between 0 and 2 decimal places. Container capacities will be calculated and displayed according to this setting.

Weight Decimals

Indicate the number of decimal places that will be significant for transport weights. You may enter between 0 and 3 decimal places. Weight capacities will be calculated and displayed according to this setting.

Volume Decimals

Indicate the number of decimal places that will be significant for transport volumes. You may enter between 0 and 3 decimal places. Volume capacities will be calculated and displayed according to this setting.

Load Numbers per Centre

Indicate the level (transport company or transport centre) at which transport load references are to be generated.

0 - No. This indicates that load references will have a single alphanumeric prefix that will appear throughout the system together with a single incrementing numeric range. Load references will be unique within the transport company.

1 - Yes. This indicates that load references will have an alphanumeric prefix and incrementing numeric range that is defined to the transport centre. Load references will be unique within the transport centre only.

Load Number Prefix

This is the alphanumeric load reference prefix that is to precede all automatically generated load references.

Load Number Range From

This indicates the lower limit for the numeric portion of the transport load number reference. All automatically generated load numbers are incremented from this point.

To

This indicates the upper limit for the numeric portion of the transport load number reference. All automatically generated load numbers are incremented from this point. If the upper limit is reached transport load references will be reassigned from the lower limit.



Press **Enter**, to validate the details and proceed to Company Profile Maintenance Detail Screen 2.

Company Profile Maintenance Detail Screen 2



This screen is displayed when you have pressed **Enter** on the Company Profile Maintenance Details Screen 1.

The transport company code, as defined on the Select Screen and the company name, as defined in Company Profile Maintenance Detail Screen 1, are displayed at the top of this screen.

TP900B	User GALBRAIJ	11/09/95
		16:15:45
Maintain Company Profile		
Company code HW Handy Wholesalers Ltd.		
Order planning level	2	(1=Order,2=Lines)
Initial creation of transport requirements ..?	2	
Default sales company	HW	
General ledger company	ZM	
Default VAT code	S	
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous		
07-S1 SF MW KS IM II KENB20A PED171S1		

Fields:

Order Planning Level

This defines the level of planning at which transport details are to be reviewed for a sales order.

- 1 - Order. This specifies that the stockroom associated with the order header should be used for the retrieval of Drinks Transport Planning information.
- 2 - Lines. This specifies that the stockroom associated with each order line should be used for the retrieval of Drinks Transport Planning information.

In line level planning a particular sales order may be processed via a number of different transport centres.



Note: If you are not using option '1', then all stockrooms in a hunt group should be planned to the same Transport Centre.

Initial Creation of Transport Requirements

This is the point at which transport requirements are initially created. The point of creation is defined to the Inventory Management Descriptions file under a major type 'TPIC'.

These points are:

- 1 - Sales order creation.
- 2 - Sales order allocation.
- 3 - Pick note creation.
- 4 - Commit stock. Not Supported.
- 5 - Confirm pick. Not Supported.
- 6 - Confirm despatch of pick note.



Notes: Option '2' is recommended for Drinks.

Default Sales Company

This is the Sales or Inventory company that is to be associated with any Descriptions file entries. This field is mandatory but will not be validated.

General Ledger Company

This is the General Ledger company that is to be associated with the transport company. If a company code is entered, General Ledger is assumed to be attached and all VAT codes and General Ledger account codes must be defined to the ledger.

Default VAT Code

This represents the normal VAT rate charged by carriers for transporting goods.

You may enter a VAT code which must be defined to the General Ledger specified in the previous field if it is attached.

If a General Ledger company is not attached, the VAT code must be defined to the Inventory Management Descriptions file under major type 'VAT'.



Press **F8=Update** to update the file.

Planner Profile Maintenance



2/DTU

Planner profile maintenance allows the set up of reference data that will dictate the degree of processing of transport order requirements which the planner (as indicated by his/her user profile) is authorised to perform. A profile must be set up for every planner (user profile) who is to use Drinks Transport Planning.



Note: At least one Transport Centre must be created before any planners can be set up.

Planner Profile Maintenance Selection Screen



Select the Planner Profile option.

The system will display the Planner Profile Maintenance Selection Screen. This screen is used to select a user profile and company code.

```
TP903A                                User GALBRAIJ    11/09/95
                                      16:33:19

Maintain Transport Planners

Company code .....?.. █
User profile .....?.. _____

F3=Exit      F4=Prompt
05-30      Sf      MW      KS      IM      II      KENB20A  PED171S1
```

Fields:

Company Code

Transport company code. You must enter an existing transport company and may prompt on this field.

User Profile

All users must be authorised as planners within the module. User IDs can be authorised to one or more transport centres. You may prompt on this field.



Press **Enter** to display the Planner Profile Maintenance Details Screen.

Planner Profile Maintenance Maintain Transport Planner's Details Screen



This screen is displayed when you have entered a valid company and user code into the Planner Profile Maintenance Selection Screen and pressed **Enter**.

The transport company code, name and the user id and name as defined at the previous Screen, are displayed.

TP903B	User GALBRAIJ	11/09/95																									
		16:40:30																									
Maintain Transport Planners																											
Company code	HW	Handy Wholesalers Ltd.																									
User profile	GALBRAIJ	Jeanette Galbraith - Studley																									
Default centre	H001	Handy Wholesaler Depot 001																									
Planning time fence days ..	0																										
Release load	1	(0=No, 1=Yes)																									
Override capacity errors ..	1	(0=No, 1=Yes)																									
Authorise payments	1	(0=No, 1=Yes)																									
Authorise adjustments	1	(0=No, 1=Yes)																									
<table border="0"> <tr> <td>F3=Exit</td> <td>F4=Prompt</td> <td>F8=Update</td> <td>F11=Delete</td> <td>F12=Previous</td> </tr> <tr> <td>F13=Transport centres</td> <td></td> <td></td> <td></td> <td></td> </tr> <tr> <td>09-30</td> <td>SE</td> <td>HW</td> <td>KS</td> <td>IM</td> </tr> <tr> <td></td> <td></td> <td></td> <td>II</td> <td>KENB20A</td> </tr> <tr> <td></td> <td></td> <td></td> <td></td> <td>PED171S1</td> </tr> </table>			F3=Exit	F4=Prompt	F8=Update	F11=Delete	F12=Previous	F13=Transport centres					09-30	SE	HW	KS	IM				II	KENB20A					PED171S1
F3=Exit	F4=Prompt	F8=Update	F11=Delete	F12=Previous																							
F13=Transport centres																											
09-30	SE	HW	KS	IM																							
			II	KENB20A																							
				PED171S1																							

Fields:

Default Centre

This is the transport centre in which transport loads are planned, marshalled and despatched. Planners will normally operate within a default transport centre but are able to change to any centre within which they are authorised to process details. Press **F13=Transport Centres** to authorise the planner to transport centres. Transport centres are set up from the Maintenance options.

Planning Time Fence Days

Default planning time fence days associated with the planner. This will determine the planned ship date with which the planner will be concerned when reviewing order requirements and load details. The planned ship date is the current date plus number of days entered here and is used as the default 'to date' (with current date as the default 'from date' within Drinks Transport Planning).

Release Load

Indicate if the planner is authorised.

1 - Yes release loads.

0 - No don't release loads.

Override Capacity Errors

Indicate whether the planner is allowed to override any capacity errors (weight and volume) when assigning transport requirements to loads that have a vehicle type associated with them.

1 - Yes.

0 - No.

Authorise Payments

Indicate whether the planner is authorised to match carrier payments against calculated charges for loads.

1 - Yes.

0 - No.

Authorise Adjustments

Indicates if the planner is authorised to adjust carrier payments against the calculated charges for a load.

1 - Yes.

0 - No.

Functions:

F13

Transport centres. This displays transport centres for authorisation.



Press **F8=Update** to save the details to file, or
F13=Transport Centres to view transport centre
details.

Planner Profile Maintenance Centre Authorisation Screen (F13)

 This screen is displayed when you press **F13=Transport Centres** on the Planner Profile Maintenance Details Screen and allows you to select the transport centre(s) to which the planner will be authorised.

TP904

User GALBRAIJ11/09/9516:59:42

Authorise Planners To Transport Centres

Company code HWHandy Wholesalers Ltd.

User profile GALBRAIJJeanette Galbraith - Studley

Sel		Transport centre	Name
<u>1</u>	*	H001	Handy Wholesaler Depot 001

1=Select4=Delete

F3=ExitF12=PreviousF15=All centres

11-04SFMMKSIIMIIKENB20APED171S1

 Use **F15=All Centres** to authorise the planner to all centres defined for this company.

Fields:

Sel

- 1 - Select. Authorise planner to transport centre.
- 4 - Delete. Remove authorisation from transport centre.

 *Note: This enables, for example, a planner (or picker or packer) to be authorised only to his/her own depot, but a transport manager to be authorised to many (potentially all) transport centres.*

Functions:

F15

All centres. Authorise planner to all transport centres defined to the transport company.

 Enter '1' into the selection field to authorise a planner.

Transport Centre Maintenance



1/DTM

A number of control flags are maintained per transport centre, which condition the processing of transport requirements and loads.

This function enables the set-up of new transport centres and maintenance of existing centres. Transport centres represent delivery depots, where transport loads are planned, picked and despatched.

Transport Centre Maintenance Selection Screen



Select the Transport Centre option.

The system will display the Selection Screen.

Fields:

Transport Centre

Transport centre in which transport loads are planned, picked and despatched. Planners normally operate within a default transport centre but are able to change to any centre within which they are authorised to process details. A prompt is available for existing transport centres.



Note: If the Transport Centre is to be used in conjunction with Container Columns in the Build Loads function, the Centre cannot be more than 3 characters long. Please refer to Processing, Build Loads Order Selection for further details.



Press **Enter** to display the Transport Centre Maintenance Details Screen 1.

Transport Centre Maintenance Details Screen 1



This screen is displayed when you have entered a valid Transport Centre into the Transport Centre Maintenance Selection Screen and pressed **Enter**.

The transport centre code defined in the previous screen is displayed.

TP001B	HW - Handy Wholesalers Ltd	User GALBRAIJ	11/09/95 17:12:41
Maintain Transport Centre			
Transport centre..... H001			
Centre name Handy Wholesaler Depot 001			
Load number prefix H			
Load number range 1 999999			
Default freight payment method?... _			
Bill print conversion factor..... 1.00000			
Default rating conversion factor . 1.00000			
Default capacity on screens ...?.. 3 1T Containers			
Add orders immediately to load 0 (0=No,1=Yes)			
Allow load to be released before goods ready for loading . 0 (0=No,1=Yes)			
Print BoL/Load sheets immediately after load released 1 (0=No,1=Yes)			
Bypass confirm load despatch 0 (0=No,1=Yes)			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			
F13=Stockroom 07-37 SF MW KS IM II KENB20A PED171S1			

Fields:

Centre Name

You must enter a transport centre name for a new centre. For existing centres, this field may be maintained.

Load Number Prefix

This is the alphanumeric load reference prefix that is to precede all automatically generated load references.

Load Number Range

Indicates the boundaries for the numeric portion of the transport load number reference. All automatically generated load numbers (generated via creation of pending loads or load schedules) will be incremented by 1 starting at the lower limit, up to and including the upper limit.

If the upper limit is reached, transport load references will be reassigned from the lower limit.

Default Freight Payment Method

This is the freight payment method defined to the transport centre as a default and maintained against a load. Freight payment methods are defined to the

Inventory Management Descriptions file under a major type of 'TPPM' and are output on the bill of lading.

Bill Print Conversion Factor

This is the conversion factor associated with weight capacities on bill of lading documentation. The gross weight of the load is divided by this factor before being printed on the bill of lading. This is used typically where the carrier uses imperial rather than metric weight or vice-versa.

Default Rating Conversion Factor

This is the conversion factor associated with rating of loads. In accordance with the capacity type associated with the rating details, the load weight, volume or number of containers is divided by this factor before accessing a rate for a given quantity. Again, this is typically where the carrier uses an alternative unit of measure.

Default Capacity on Screens

The default capacity type associated with the transport centre is entered here. Capacities are defined for orders, drops and loads and are displayed by weight, volume or number of transport containers. Capacity types are defined to the Inventory Descriptions file under a major type of 'TPDC'.

- 1 - Weight.
- 2 - Volume.
- 3 - Number of containers/packs.

Add Orders Immediately to Load

Indicates whether order transport requirements, once created, should be added to suitable loads immediately i.e. loads of sufficient capacity with the same route, ship date, stockroom and vehicle type.

- 1 - Yes.
- 0 - No. If set to '0' the system suggests a suitable load number but does not automatically add the order to the load.

Allow Load to be Released Before Goods Ready for Loading

Indicate whether early release of a load via Maintain Loads is allowed before all the associated despatch notes have been confirmed as despatched via Drinks Sales Order Processing. This allows load documentation to be printed so that the load fill can commence in parallel with picking.

- 1 - Yes.
- 0 - No.

Print BoL/Load Sheets Immediately After Load Released

Indicates that Load Sheets and Bill of Lading documentation should be printed immediately as loads are released via Load Maintenance, and not via the Print Load option.



Note: Care must be taken with the setting of this field in conjunction with 'Bypass Confirm Despatch', and the use of Load Rating. If neither Rating nor 'Confirm Despatch' are being used,

this field should be set to No ('0') - otherwise, when the load is released, the Load Status skips all settings (Rating and Confirmation) through to Awaiting History. A load at this setting is NOT recognised in Drinks Sales Order Processing for picking.

Bypass Confirm Load Despatch

Indicate whether confirm despatch of individual loads is required.

The confirm load despatch transaction date and time-stamps the load, allowing any planner to view whether or not the load has left the premises (via the enquiries).

1 - Yes. Loads are automatically flagged as 'waiting to be dropped to history' at time of printing or after posting transport charge payments, depending on whether or not rating of the load is required.

0 - No.

Functions:

F13

Stockroom details. You use this option to specify which stockrooms are



Press **Enter** to continue to Transport Centre
Maintenance Details Screen 2.

Transport Centre Maintenance Stockrooms Screen (F13)

 This screen is accessed by pressing **F13=Stockroom** on Transport Centre Maintenance Details Screen 1.

It enables transport centres to plan transport on behalf of multiple sales companies and/or multiple stockrooms.

 The function allows you to allocate (**F9=Add**) and deallocate (**4**) stockrooms to the transport centre. Using **F15=All Stockrooms** you can allocate all stockrooms within all sales companies to the transport centre.

Any sales company/stockroom combination can only be used for one transport centre as this relationship is used to determine into which centre the requirements should be added.

TP002

HW - Handy Wholesalers Ltd

User GALBRAIJ

11/09/95
17:57:43

Maintain Transport Centre Stockrooms

Transport centre H001 Handy Wholesaler Depot 001

Sel	Sales company	Stockroom
-	ZM Multi-Currency Company	PC Duty Paid Depot PC
-	ZM Multi-Currency Company	PD Duty Paid Depot PD
-	ZM Multi-Currency Company	RS Richard's RS400 stockroom

4=Delete

F3=Exit

F9=Add

F12=Previous

F15=All stockrooms

08-04



MW

KS

IM

II

KENB20A

PED171S1

Fields:

Selection

4 - Delete sales company / stockroom combination.

 Use the function keys, or enter '4' to delete a sales company / stockroom combination.

Functions:

F9

Add sales company/stockroom combination. See Stockroom Addition section.

F15

All stockrooms. This assigns all Inventory stockrooms within all sales companies to this transport centre.



Note: Care should be taken when using this option.

Transport Centre Maintenance Stockroom Addition Window (F9)

 This Screen allows you to allocate a stockroom to a transport centre and is accessed by pressing **F9=Add** on the Transport Centre Maintenance Stockroom Screen.

TP002 HW - Handy Wholesalers Ltd User GALBRAIJ 11/09/95 17:57:43

Maintain Transport Centre Stockrooms

Transport centre H001 Handy Wholesaler Depot 001

Sel	Sales company	Stockroom
-	ZM Multi-Currency Company	PC Duty Paid Depot PC
-	ZM Multi-Currency Company	PD Duty Paid Depot PD
-	ZM Multi-Currency Company	RS Richard's RS400 stockroom

Addition

Sales company —

Stockroom?..

F4=Prompt F8=Update F12=Previous

21-38 SF HW KS IM II KENB20A PED171S1

Fields:

Sales Company

Sales company associated with the processing of sales orders.

Stockroom

Stockroom or sales depot associated with the allocation and despatch of sales items within the sales company defined above. When a sales company is input in this Screen, pressing **F4=Prompt** in this field allows you to choose a stockroom within that company.

 Press **F8=Update** to save the changes to the file.

Transport Centre Maintenance Details Screen 2



This screen is displayed when you press **Enter** on the Transport Centre Maintenance Details Screen 2. The transport centre and its name is displayed at the top of the Screen.

TP001B	HW - Handy Wholesalers Ltd	User GALBRAIJ	11/09/95 17:29:12
Maintain Transport Centre			
Transport centre H001 Handy Wholesaler Depot 001			
Default commodity code?.. 995		Alcoholic Drinks	
Default VAT code?.. S		17.50 %	
Temperatures _ _			
Fixed temperature message _____			
Temperature range message _____			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			
07-37 SF HW KS IM II KENB20A PED171S1			

Fields:

Default Commodity Code

This is the default commodity code associated with the transport centre. The code is used as a default when creating pending loads unless a based-on load is used. In the latter case, the commodity code of the based-on load is used.

Commodity codes are defined to the Inventory Descriptions file under major type 'TPCC' and the default is printed on all bills of lading.

Default VAT Code

The VAT code must be defined to the General Ledger if it is attached - i.e. the General Ledger company code defined to the transport company profile. If General Ledger is not attached, the VAT code must be defined to the Inventory Descriptions file under major type 'VAT'.

Temperature 1

This is the temperature associated with the shipment of temperature dependent goods. If a single temperature is maintained for the transport centre this will provide the default for created loads and the fixed temperature message defined to the transport centre will be printed on bill of lading documentation.

Temperature 2

This is the second temperature associated with the shipment of temperature dependent goods. If two temperatures are maintained for the transport centre they will provide the default for created loads and the temperature range message defined to the transport centre is printed on bill of lading documentation.

Fixed Temperature Message

This is the fixed temperature message (associated with Temperature 1) that is to be associated with a transport centre concerned with the shipment of temperature dependent goods. This temperature message is printed on the bill of lading documentation along with the first temperature if only one temperature is entered against a load header, e.g. 'set thermostat to ...'.

Temperature Range Message

This is the temperature range message (associated with Temperatures 1 and 2) that is to be associated with a transport centre concerned with the shipment of temperature dependent goods. This temperature message is printed on the bill of lading documentation along with both temperatures if two temperatures are entered against a load header, e.g. 'temperature range must be ...'.



Press **F8=Update** to save the file details.

Transport Node Maintenance



2/DTM

This option enables the definition of nodes for the transport centre currently in use. A node is a geographical location where one or more routes start or end. This is typically a company distribution centre, but may be a location used by the carrier as a depot, or a location where bulk loads are broken down.

Transport Node Maintenance Selection Screen



Select the Transport Nodes option.

Fields:

Transport Node

Enter a new or existing transport node or geographical location that is to be associated with routes as origins or destinations. Existing nodes can be prompted on.



Press **Enter** to display the Transport Node Maintenance Details Screen.

Transport Node Maintenance Details Screen

 This screen is displayed when you have entered a valid transport node into the Transport Node Maintenance Selection Screen and pressed **Enter**.

If the node entered on the previous Screen already exists, its details will be displayed here, but may be maintained. For a new node, enter its details.

TP027B

HW - Handy Wholesalers Ltd
Handy Wholesaler Depot 001

User GALBRAIJ

12/09/95
9:52:37

Maintain Transport Nodes

Transport node MID

Name Midlands Central Depot

County?.. MIDL Midlands

F3=Exit

F4=Prompt

F8=Update

F11=Delete

F12=Previous

09-32

SF

MW

KS

IM

II

KENB20A

PED171S1

Fields:

Name

Node name.

County

County or state associated with the transport node. Counties are defined to the Inventory Descriptions file under a major type 'TPCY'. This is used for memo purposes only.

 Press **F8=Update** to update the files.

Vehicle Types Maintenance

1... **2...** 3/DTM

This function enables the definition of vehicle types and their associated capacities (gross weight and volume) to the transport centre currently being used. By assigning a vehicle type to a load, the system keeps a check on its current load size, ensuring that it does not exceed the maximum values assigned here.

Vehicle Type Maintenance Selection Screen



Select the Vehicle Types option.

Fields:

Vehicle Type

Enter a new or existing type of vehicle that is to be associated with a load. Vehicle types have gross weight and volume capacities defined to them. Existing vehicle types can be prompted on.



Press **Enter** to display the Vehicle Type Maintenance Details Screen.

Vehicle Type Maintenance Details Screen

 This screen is displayed when you have entered a valid vehicle type into the Vehicle Type Maintenance Selection Screen and pressed **Enter**.

The vehicle type entered on the Vehicle Type Maintenance Selection Screen is displayed.

TP012B	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95
	Handy Wholesaler Depot 001		9:59:19
Maintain Vehicle Types			
Vehicle type PKP			
Description <u>Pickup Truck</u>			
Maximum weight capacity .. <u>999.99</u>			
Maximum volume capacity .. <u>999.99</u>			
F3=Exit F8=Update F11=Delete F12=Previous			
07-29  MW KS IM II KENB20A PED171S1			

Fields:

Description

Vehicle type description.

Maximum Weight Capacity

Maximum gross weight capacity for vehicle type.

Maximum Volume Capacity

Maximum volume capacity for vehicle type.

 Press **F8=Update** to update the file.

Carrier Rates Maintenance



4/DTM

This function enables the maintenance of tables in order to automatically rate loads, i.e. calculate carrier freight charges. A rate code should be set up for each set of charges to be applied to a group of carriers, an individual carrier, or an individual route covered by the carrier. Rates are assigned in the Carrier Maintenance option within Drinks Transport Planning. The rate code and description should clearly describe when these charges are to be applied.

The calculated load charge will be used as the basis for matching the carrier's invoice. (See Invoice Details for more information.)

Carrier Rates Maintenance Selection Criteria Screen



Select the Carrier Rates option.

TP015A	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95
	Handy Wholesaler Depot 001		10:38:29
Maintain Carrier Rates			
Rate method?.. _			
Rate code?.. _____			
Effective date?.. <u>12/09/95</u>			
F3=Exit F4=Prompt			
05-28 SF MW KS IM II KENB20A PED171S1			

Fields:

Rate Method

The method of rating that is associated with a particular rate code. Rate methods are defined to the Inventory Management Descriptions file under a major type 'TPRM', as follows:

- 01 - Load and rate table. Charges are calculated based on the load's gross weight, volume or number of containers using a rating table.
- 02 - Drop and rate table. Charges are calculated based on each drop's gross weight, volume or number of containers using a rating table.
- 03 - Fixed rate per area. Charges are calculated based on the gross weight, volume or number of containers dropped into each area using a fixed rate.
- 04 - Area and rate table. Charges are calculated based on the gross weight, volume or number of containers for each area using a table.

Rate Code

This is the rate code that is associated with a particular rating method. It defines rating criteria that are effective from a given date. It may then be associated with one or more carriers, or individual carrier/route combinations.

Effective Date

(Defaults to current date). Date from which the rating information will be effective. Multiple dates may be set up for any one rate code. The system will automatically

move to the next date when it is no longer in the future, allowing new rates to be added to the system prior to them coming into effect.



Press **Enter** to display the relevant table, depending on what you have entered into the Carrier Rates Maintenance Rate Method field.

Carrier Rates Maintenance Rating By Load And Rate Table (Method '01') Screen



This screen is displayed when you have entered '01' into the Rate Method field on the Carrier Rates Maintenance Selection Criteria Screen and allows maintenance of information required in order to rate loads by total gross capacity (weight, volume or number of containers) as defined in a table.

The rate method, rate code and effective date as entered on the previous screen are displayed

TP015B	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95																									
	Handy Wholesaler Depot 001		10:47:22																									
Maintain Carrier Rates																												
Rate method	01 01																											
Rate code	JK9HD																											
Effective date	12/09/95																											
Description	Load/Rate by Container																											
Capacity type	Containers																											
VAT code	?																											
Drop charge rate		.00																										
Minimum drop charge		.00																										
Maximum drop charge		.00																										
Surcharge %	.00																											
Surcharge value		.00																										
Minimum load charge		.00																										
Number of free drops	1																											
<table border="0"> <tr> <td>F3=Exit</td> <td>F4=Prompt</td> <td>F8=Update</td> <td>F11=Delete</td> <td>F12=Previous</td> </tr> <tr> <td>F13=Charge structure</td> <td>F14=Volume</td> <td>F15=Containers</td> <td>F16=Weight</td> <td></td> </tr> <tr> <td>00-50</td> <td>82</td> <td>MW</td> <td>KS</td> <td>IM</td> </tr> <tr> <td></td> <td></td> <td></td> <td>II</td> <td>KENB20A</td> </tr> <tr> <td></td> <td></td> <td></td> <td></td> <td>PED171S1</td> </tr> </table>				F3=Exit	F4=Prompt	F8=Update	F11=Delete	F12=Previous	F13=Charge structure	F14=Volume	F15=Containers	F16=Weight		00-50	82	MW	KS	IM				II	KENB20A					PED171S1
F3=Exit	F4=Prompt	F8=Update	F11=Delete	F12=Previous																								
F13=Charge structure	F14=Volume	F15=Containers	F16=Weight																									
00-50	82	MW	KS	IM																								
			II	KENB20A																								
				PED171S1																								

Fields:

Description

Description to be associated with the level of rating information. For example you could enter the carrier(s) and route(s) to which it is applied.

Capacity Type

On setting a rate code up for the first time, the description of the default capacity set up for the transport centre will be entered here. You may change this capacity at this point only. Press **F14=Volume** to set it to volume, **F15=Containers** to set it to containers or **F16=Weight** to set it to weight.

VAT Code

This is the VAT code to be associated with the calculation of VAT on load charges. It is not applied until the invoice is transferred to Accounts Payable.

Drop Charge Rate

This is the fixed charge for each drop on a load.

Minimum Drop Charge

This is the minimum charge for each drop on a load.

Maximum Drop Charge

This is the maximum charge for each drop on a load.

Surcharge %

This is a percentage that can be applied to calculated load or area charges in order to accommodate unforeseen extras e.g. government fuel tax charges.

Surcharge Value

This is a value that can be applied to calculated load or area charges in order to accommodate unforeseen extras e.g. government fuel tax charges.



Note: Either a surcharge percentage or value can be entered but not both.

Minimum Load Charge

The minimum charge for a load.

Number of Free Drops

This is the number of drops that will be considered free of charge when calculating load charges.

Functions:

F13

Charge structures.

F14

Volume. Set capacity type to volume.

F15

Containers. Set capacity type to number of containers.

F16

Weight. Set capacity type to weight.



*Note: **F14=Volume**, **F15=Containers** and **F16=Weight** are used to define the capacity type that is to be associated with the rating information. The capacity type can only be changed whilst adding a new rate method/rate code/effectivity date combination and is fixed for the details thereafter.*



Use one of the function keys or press **F8=Update** to update the file with any changes you have made.

Carrier Rates Maintenance Rating By Drop And Capacity Table Screen (Method '02')



This screen is displayed when you have entered '02' into the Rate Method field on the Carrier Rates Maintenance Selection Criteria Screen and allows maintenance of information required in order to rate loads by drop capacity as defined in a capacity table.

Charges are calculated based on each drop's gross weight, volume or number of containers according to a rating table. The rate method, rate code and effective date as entered on the previous screen are displayed.

TP015C	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95																									
	Handy Wholesaler Depot 001		12:37:42																									
Maintain Carrier Rates																												
Rate method	02 1T Rating Method 02																											
Rate code	JK9VV																											
Effective date	12/09/95																											
Description	█																											
Capacity type	Containers																											
VAT code	?																											
Drop charge rate	.00																											
Minimum drop charge	.00																											
Maximum drop charge	.00																											
Surcharge %	.00																											
Surcharge value	.00																											
Minimum load charge	.00																											
Number of free drops	1																											
<table border="0"> <tr> <td>F3=Exit</td> <td>F4=Prompt</td> <td>F8=Update</td> <td>F11=Delete</td> <td>F12=Previous</td> </tr> <tr> <td>F13=Charge structure</td> <td>F14=Volume</td> <td>F15=Containers</td> <td>F16=Weight</td> <td></td> </tr> <tr> <td>00-20</td> <td>SW</td> <td>MW</td> <td>KS</td> <td>IM</td> </tr> <tr> <td></td> <td></td> <td></td> <td>II</td> <td>KENB20A</td> </tr> <tr> <td></td> <td></td> <td></td> <td></td> <td>PED171S1</td> </tr> </table>				F3=Exit	F4=Prompt	F8=Update	F11=Delete	F12=Previous	F13=Charge structure	F14=Volume	F15=Containers	F16=Weight		00-20	SW	MW	KS	IM				II	KENB20A					PED171S1
F3=Exit	F4=Prompt	F8=Update	F11=Delete	F12=Previous																								
F13=Charge structure	F14=Volume	F15=Containers	F16=Weight																									
00-20	SW	MW	KS	IM																								
			II	KENB20A																								
				PED171S1																								

Fields:

Description

Description to be associated with the level of rating information. For example you could enter the carrier(s) and route(s) to which it is applied.

Capacity Type

On setting a rate code up for the first time, the description of the default capacity set up for the transport centre will be entered here. You may change this capacity at this point only. Press **F14=Volume** to set it to volume, **F15=Containers** to set it to containers or **F16=Weight** to set it to weight.

VAT Code

This is the VAT code to be associated with the calculation of VAT on load charges. It is not applied until the invoice is transferred to Accounts Payable.

Drop Charge Rate

This is the fixed charge for each drop on a load.

Minimum Drop Charge

This is the minimum charge for each drop on a load.

Maximum Drop Charge

This is the maximum charge for each drop on a load.

Surcharge %

This is a percentage that can be applied to calculated load or area charges in order to accommodate unforeseen extras e.g. government fuel tax charges.

Surcharge Value

This is a value that can be applied to calculated load or area charges in order to accommodate unforeseen extras e.g. government fuel tax charges.



Note: Either a surcharge percentage or value can be entered but not both.

Minimum Load Charge

The minimum charge for a load.

Number of Free Drops

This is the number of drops that will be considered free of charge when calculating load charges.

Functions:

F13

Charge structures.

F14

Volume. Set capacity type to volume.

F15

Containers. Set capacity type to number of containers.

F16

Weight. Set capacity type to weight.



*Note: **F14**, **F15** and **F16** are used to define the capacity type that is to be associated with the rating information. The capacity type can only be changed whilst adding a new rate method/rate code/effectivity date combination and is fixed for the details thereafter.*



Use one of the function keys or press **F8=Update** to update the file with any changes you have made.

Carrier Rates Maintenance Methods '01' & '02' Charge Structures Window (F13)



This screen, accessed by pressing **F13=Charge Structures** from the Carrier Rates Maintenance Details Screen, allows you to set up and amend charge structures for the rate code.

TP015B	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95
	Handy Wholesaler Depot 001		10:47:22
Maintain Carrier Rates			
Rate method	01 01		
Rate code	JK9HD		
Effective date	12/09/95		
Description			
Capacity type			
VAT code	?		
Drop charge rate			
Minimum drop charge			
Maximum drop charge			
Surcharge %			
Surcharge value			
Minimum load charge			
Number of free drops			

Charge Structures		
Conversion factor		1.00000
Sel	Level break	Rate
-	2	20.00
Bottom		
1=Select 4=Delete		
F8=Update F9=Add F12=Previous		

F3=Exit	F4=Prompt	F8=Update	F11=Delete	F12=Previous
F13=Charge structure	F14=Volume	F15=Containers	F16=Weight	
11-32	SW	MW	KS	IM II KENB20A PED171S1

Fields:

Conversion Factor

This is the conversion factor associated with rating of loads (defaulted to that set using the Profile Maintenance options). The capacity is divided by this factor before accessing a rate for a given quantity. The capacity is in terms of load gross weight, volume or number of containers as specified in the previous Screen.

Sel

1 - Select for amendment.

4 - Delete break details.

Level Break

Each level break is a gross capacity (weight, volume or number of containers) to be associated with a particular rate. This is the capacity from which the associated rate will be charged.

Rate

This is the charge rate associated with the level break beside it.

Functions:

F9

Add charge structure details.



Press **F8=Update** to save the changes to the file.

Carrier Rates Maintenance Rating By Fixed Rate Per Area Screen (Method '03')



This screen is displayed when you have entered '03' into the Rate Method field on the Carrier Rates Maintenance Selection Criteria Screen and allows maintenance of information required in order to rate loads by capacities dropped into each area.

Charges are calculated based on the gross weight, volume or number of containers dropped into each area using a fixed rate. The rate method, rate code and effective date as entered on the previous screen are displayed.

TP015D	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95
	Handy Wholesaler Depot 001		12:43:35
Maintain Carrier Rates			
Rate method 03 1T Rating Method 03			
Rate code JK9HT			
Effective date 12/09/95			
VAT code?.. S			
Rating conversion factor. 1.00000			
Description Fixed by Container			
Sel	Area	Container rate	Area minimum
		Drop maximum	Surcharge value
			Drop minimum
			Surcharge %
1=Select 4=Delete			
F3=Exit F4=Prompt F8=Update F9=Add F11=Delete			
F12=Previous F14=Volumes F15=Containers F16=Weights			
08-28 S2 MW KS IM II KENB20A PED171S1			

Fields:

VAT Code

This is the VAT code to be associated with the calculation of VAT on load charges. It is not applied until the invoice is transferred to Accounts Payable.

Rating Conversion Factor

This is the conversion factor associated with rating of loads. The capacity is divided by this factor before accessing a rate for a given quantity. The capacity will be in terms of volume, number of containers or load gross weight, as determined when the rate is first defined.

Description

This is the description to be associated with the level of rating information. For example you could enter the carrier(s) and route(s) to which it is applied.

The area details for this rate code are displayed below these fields. These can be added to by using **F9=Add**.

Sel

1 - Select for amendment.

4 - Delete area details.

Area

The area code associated with the rating information.

Volume/ Container/ Weight Rate

Depending on the capacity type specified above, this rate will be multiplied by the quantity and applied to the calculated load or area charge.

Area Minimum

This is the minimum charge for the area.

Drop Minimum

This is the minimum charge for the drop.

Drop Maximum

This is the maximum charge for the drop.

Surcharge Value

This is a value that can be applied to calculate load or area charges in order to accommodate unforeseen extras, for example government fuel charges.

Surcharge %

This is a percentage that can be applied to calculated load or area charges in order to accommodate unforeseen extras for example government fuel charges.

Functions:

F9

Add area rate details.

F14

Volume. Set capacity type to volume.

F15

Containers. Set capacity type to number of containers.

F16

Weight. Set capacity type to weight.



*Note: **F14**, **F15** and **F16** are used to define the capacity type that is to be associated with the rating information. The capacity type can only be changed whilst adding a new rate method/rate code/effectivity date combination and is fixed for the details thereafter.*



Use one of the function keys or press **F8=Update** to update the file with any changes you have made.

Carrier Rates Maintenance Methods '03' Area Details Window (F9)



This window is accessed by pressing **F9=Add** to add new defaults, or by deleting an existing detail line.

This adds a line with the capacity type and quantity.

TP015E	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95
	Handy Wholesaler Depot 001		13:12:36
Maintain Carrier Rates			
Rate method 04 1T Rating Method 04			
Rate code JK9VT			
Effective date 12/09/95 Capacity type Containers			
VAT code ?.. S			
Rating conversion factor. 1.00000			
Description Variable Area Rate by Container			
Sel	Area	Maintain Area Rate	
-	NHPT	Area ?.. NHPT	
		Area minimum	.00
		Drop minimum	.00
		Drop maximum	.00
		Surcharge value ...	.00
		Surcharge %	.00
1=Select 4=De F4=Prompt F8=Update F11=Delete F12=Previous			
F3=Exit F4=Prompt F8=Update F9=Add F11=Delete			
F12=Previous 16-39 SF HW KS IM II KENB20A PED171S1			

Fields:

Area

This is the area code to be associated with rating information. For existing details this may not be amended.

Area Minimum

This is the minimum charge for area.

Drop Minimum

This is the minimum charge for each drop on a load.

Drop Maximum

This is the maximum charge for each drop on a load.

Surcharge Value

A value that can be applied to calculated load or area charges in order to accommodate unforeseen extras e.g. government fuel tax charges.

Surcharge Percentage

A percentage that can be applied to calculated load or area charges in order to accommodate unforeseen extras e.g. government fuel tax charges.



Note: Either a surcharge percentage or value can be entered but not both.

Functions:

F11

Delete the rating details (providing that the code is not defined to an outstanding load).



Press **F8=Update** to save any changes and return to the Carrier Rates Maintenance Rating By Fixed Rate Per Area Screen.

Carrier Rates Maintenance Rating By Area And Capacity Table Screen (Method '04')



This screen is displayed when you have entered '04' into the Rate Method field on the Carrier Rates Maintenance Selection Criteria Screen and allows maintenance of information required in order to rate loads by capacities dropped into each area.

Charges are calculated based on the gross weight, volume or number of containers for each area according to a capacity table.

TP015E	HW - Handy Wholesalers Ltd		User GALBRAIJ	12/09/95
	Handy Wholesaler Depot 001			12:58:40
Maintain Carrier Rates				
Rate method 04 1T Rating Method 04				
Rate code JK9VT				
Effective date 12/09/95		Capacity type Containers		
VAT code ?..				
Rating conversion factor. -		1.00000		
Description				
Sel	Area	Area minimum Surcharge value	Drop minimum Surcharge %	Drop maximum
1=Select 4=Delete 5=Charges				
F3=Exit		F4=Prompt	F8=Update	F9=Add
F12=Previous		F14=Volumes	F15=Containers	F16=Weights
08-28	82	MW	KS	IM II KENB20A PED171S1

Fields:

VAT Code

VAT code to be associated with the calculation of VAT on load charges. Not applied until the invoice is transferred to Accounts Payable. (Refer to Rate Loads Manually, Detail).

Rating Conversion Factor

Conversion factor associated with rating of loads. In accordance with the capacity type associated with the rating details, the load gross weight, volume or number of containers is divided by this factor before accessing a rate for a given quantity.

Description

Description to be associated with the level of rating information e.g. the carrier(s) and route(s) to which it is applied.

Sel

- 1 - Select for amendment.
- 4 - Delete area details.
- 5 - Charge structures.

Area

The area code associated with the rating information.

Area Minimum

This is the minimum charge for the area.

Drop Minimum

This is the minimum charge for the drop.

Drop Maximum

This is the maximum charge for the drop.

Surcharge Value

This is a value that can be applied to calculate load or area charges in order to accommodate unforeseen extras, for example government fuel charges.

Surcharge %

This is a percentage that can be applied to calculated load or area charges in order to accommodate unforeseen extras for example government fuel charges.

These can be added to by pressing **F9=Add**.

Functions:

F9

Add area rate details.

F11

Delete.

F14

Volume. Set capacity to volume.

F15

Containers. Set capacity to number of containers.

F16

Weight. Set capacity to weight.



*Note: **F14**, **F15** and **F16** are used to define the capacity type that is to be associated with the rating information. The capacity type can only be changed whilst adding a new rate method/rate code/effectivity date combination and is fixed for the details thereafter.*



Use one of the function keys or press **F8=Update** to update the file with any changes you have made.

Carrier Rates Maintenance Methods '04' Area Details Window (F9)



This window is accessed by pressing **F9=Add** to add new defaults, or by deleting an existing detail line.

TP015E	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95
	Handy Wholesaler Depot 001		13:12:36
Maintain Carrier Rates			
Rate method 04 1T Rating Method 04			
Rate code JK9VT			
Effective date 12/09/95 Capacity type Containers			
VAT code?.. S			
Rating conversion factor. 1.00000			
Description Variable Area Rate by Container			
Sel	Area	Maintain Area Rate	
-	NHPT	Area?.. NHPT	
Area minimum		.00	
Drop minimum		.00	
Drop maximum		.00	
Surcharge value ...		.00	
Surcharge %		.00	
1=Select 4=Delete F4=Prompt F8=Update F11=Delete F12=Previous			
F3=Exit F4=Prompt F8=Update F9=Add F11=Delete			
F12=Previous 16-39 S HW KS IH II KENB20A PED171S1			

Fields:

Area

This is the area code to be associated with rating information. For existing details this may not be amended.

Area Minimum

This is the minimum charge for area.

Drop Minimum

This is the minimum charge for each drop on a load.

Drop Maximum

This is the maximum charge for each drop on a load.

Surcharge Value

A value that can be applied to calculated load or area charges in order to accommodate unforeseen extras e.g. government fuel tax charges.

Surcharge Percentage

A percentage that can be applied to calculated load or area charges in order to accommodate unforeseen extras e.g. government fuel tax charges.



Note: Either a surcharge percentage or value can be entered but not both.

Functions:

F11

Delete the rating details (providing that the code is not defined to an outstanding load).



On addition, press **F8=Update** to display the Carrier Rates Maintenance Charge Structure Window, otherwise the system returns to the Carrier Rates Maintenance Rating By Area And Capacity Table Screen.

Carrier Rates Maintenance Method '04' Charges Structure Window (Option 5)



This Screen is reached by updating area details or by entering a '5' against an area detail line.

TP015E	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95
	Handy Wholesaler Depot 001		13:12:36
Maintain Carrier Rates			
Rate method 04 1T Rating Method 04			
Rate code JK9VT			
Effective date 12/09/95		Capacity type Containers	
VAT code ?..			
Rating conversion factor.			
Description			
Sel	Area	Area	Surchar
5	NHPT		

Charge Structures		
Conversion factor	1.00000	
Sel	Level break	Rate
-	2	22.00
Bottom		
1=Select 4=Delete		
F8=Update F9=Add F12=Previous		

1=Select	4=Delete	5=Charges
F3=Exit	F4=Prompt	F8=Update
F12=Previous		F9=Add
11-32	SA	MW
		KS
		IM
		II
		KENB20A
		PED171S1

Fields:

Conversion Factor

Conversion factor associated with rating of loads. In accordance with the capacity type associated with the rating details, the load gross weight, volume or number of containers is divided by this factor before accessing a rate for a given quantity.

Selection

- 1 - Select for amendment.
- 4 - Delete break details.

Functions:

F9

Add charge structure details.



Press **F8=Update** to save any changes, or press **F9=Add** to add new details.

Carrier Rates Maintenance Method '04' Charges Structure Addition Window (F9)



This screen is reached when you press **F9=Add** from the Method '04' - Carrier Rates Maintenance Charges Structure Window.

Fields:

Gross Capacity

Gross capacity (weight, volume or number of containers) to be associated with a particular rate. This is the capacity from which the associated rate will be charged.

Rate

Charge rate to be associated with a particular capacity.



Press **Enter** to save the additional details.

Carrier Maintenance



5/DTM

This function enables the entry of attributes for all carriers that are to be associated with the transportation of goods.



Note: All carriers, whether internal or external, must be defined to the system.

Carrier Maintenance Selection Screen



Select the Carriers from the Maintenance Screen.

Fields:

Carrier

Enter a reference code for either an internal or external carrier that will be associated with the handling of transport requirements. You may prompt on existing carriers for this transport centre.



Press **Enter** to display the Carrier Maintenance Details Screen.

Carrier Maintenance Details Screen



This screen is displayed when you have entered a valid carrier code onto the Carrier Maintenance Selection Screen and pressed **Enter**.

TP020B	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95
	Handy Wholesaler Depot 001		14:57:17
Maintain Carriers			
Carrier	MAERS		
Name	Maers Haulage		
Address	Maers Depot		
	Welling Industrial Estate		
	NORTHAMPTON.		
Carrier type	0001		
Contact name	Jerry Roberts		
Phone number	01604-599123		
FAX number	01604-599124		
Rating required	1 (0=No,1=Yes)		
Rate method	01		
Rate code	JK9HD		
Payables account	0001		
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			
F13=Routes F21=Text MW KS IM II KENB20A PED171S1			
21-26			

Fields:

Name/Address

Carrier name and address details, normally printed on the bill of lading as the consignee.

Carrier Type

Carrier type code. Carrier types are maintained on the Inventory Descriptions file under major type 'TPCT'. May be used for future analysis.

Contact Name

Carrier contact name.

Phone Number

Carrier telephone number.

FAX Number

FAX number associated with the carrier.

Rating Required

Indicates whether rating (calculation of transport charges) is appropriate or not for the carrier.

1 - Yes.

0 - No.

Rate Method

Method of automatic rating that is associated with the rate code. Rate methods are defined to the Inventory Descriptions file under major type 'TPRM', as follows:

01 - Load and rate table. Charges are calculated based on the loads gross weight, volume or number of containers according to a rating table.

02 - Drop and rate table. Charges are calculated based on each drop's gross weight, volume or number of containers according to a rating table.

03 - Fixed rate per area. Charges are calculated based on the gross weight, volume or number of containers dropped into each area.

04 - Area and rate table. Charges are calculated based on the gross weight, volume or number of containers for each area according to a capacity table.

Rate Code

Rate code that is associated with the rating method that defines rating parameters that are effective on a given date. This may be overridden by specifying a different rate code on the Carrier Route screen (for a particular route).

Payables Account

Accounts Payable supplier code associated with carrier.



Note: This must be a valid supplier defined to Accounts Payable if it is attached.

Functions:

F4

Prompt for valid parameters - Carrier type, Rate method, Rate code, Payables account.



Note: Payables account prompt is only available if Accounts Payable and General Ledger are installed.

F11

Delete the carrier (providing it is not defined to a delivery profile in this module.)

F13

Allows entry of carrier route restrictions and rating overrides.

F21

Allows entry of internal text for carriers.



*Note: **F13=Routes** or **F21=Text** will be highlighted if route restrictions or text exist respectively.*

Carrier Maintenance Route Selection Window (F13)



This window is displayed when you press **F13=Routes** from the Carrier Maintenance Detail Screen and allows you to restrict the carrier to certain routes.

If you do not specify routes, then the assumption is that the carrier can service any route defined to the transport centre.



Note: Specific routes need only be defined to the carrier to ensure that a carrier is not assigned to an inappropriate route or if the rates vary per route.

```

TP020B          HW - Handy Wholesalers Ltd          User GALBRAIJ      12/09/95
                  Handy Wholesaler Depot 001          16:00:25

Maintain Carriers

Carrier ..... MAERS
Restrict Carriers To Routes

  Sel  Route      Description                      Rate  Rate
   _   NHLT01     Northampton to Luton Route 01    04   JK9VT

1=Select      4=Delete
FS=Refresh    F8=Update    F9=Add      F12=Previous
F13=Routes    09-05      S#          MW          KS          IM          II  KENB20A  PED171S1

```

Fields:

Sel

- 1 - Select for amendment.
4 - Delete carrier route details.

Route

Select the Route code(s) on which the carrier will carry goods from this Transport Centre.

Description

The free-text description for the route.

Rate Method

Method of rating to be used when rating loads on this route. Rate methods are defined to the Inventory Descriptions file under major type 'TPRM', as follows:

01 - Load and rate table. Charges are calculated based on the loads gross weight, volume or number of containers according to a rating table.

02 - Drop and rate table. Charges are calculated based on each drops gross weight, volume or number of containers according to a rating table.

03 - Fixed rate per area. Charges are calculated based on the gross weight, volume or number of containers dropped into each area.

04 - Area and rate table. Charges are calculated based on the gross weight, volume or number of containers for each area according to a capacity table.

Rate Code

Rate code to be used when rating loads on this route. It is associated with the rating method.

Functions:

F9

Add carrier route details.



Select a route, or press **F9=Add** to add a new route, or press **F8=Update** to save the details to file.

Carrier Maintenance Route Addition Window (F9)



This is displayed when you press **F9=Add** on the Carrier Maintenance Route Selection Window and allows you to add Routes, Rate Methods and Rate Codes associated with the carrier.

```

TP020B      HW - Handy Wholesalers Ltd      User GALBRAIJ      12/09/95
              Handy Wholesaler Depot 001      16:00:25
Maintain Carriers

Carrier ..... MAERS

Restrict Carriers To Routes

  Sel  Route      Description              Rate  Rate
   _   NHLT01     Northampton to Luton Route 01    04  JK9VT

Addition

Route.....?..  _
Rate method....?..  _
Rate code.....?..  _

F4=Prompt      F8=Update      F12=Previous
1=Select       4=Delete

F5=Refresh      F8=Update      F9=Add      F12=Previous
F13=Routes      F21=Text
17-24          32          MW          KS          IM          II  KENB20A  PED171S1
  
```

Fields:

Route

Enter the Route code(s) on which the carrier will carry goods from this Transport Centre.

Rate Method

Enter the method of rating to be used when rating loads on this route. Rate methods are defined to the Inventory Descriptions file under major type 'TPRM', as follows:

01 - Load and rate table. Charges are calculated based on the loads gross weight, volume or number of containers according to a rating table.

02 - Drop and rate table. Charges are calculated based on each drops gross weight, volume or number of containers according to a rating table.

03 - Fixed rate per area. Charges are calculated based on the gross weight, volume or number of containers dropped into each area.

04 - Area and rate table. Charges are calculated based on the gross weight, volume or number of containers for each area according to a capacity table.

Rate Code

Enter the rate code to be used when rating loads on this route. It is associated with the rating method.



Press **F8=Update** the save additions you have made.

Carrier Maintenance Internal Text Screen (F21)



This screen is displayed when you press **F21=Text** on the Carrier Maintenance Details Screen and enables you to enter internal text for the carrier, purely for the planner's information.

TP020B	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95												
	Handy Wholesaler Depot 001		16:18:13												
Maintain Carriers															
Carrier MAERS															
Name	Maers Haulage														
Address	Maers Depot														
	Welling Industrial Estate														
	NORTHAMPTON.														
Carrier type	0001	Type													
Contact name	Jerry Robe														
Phone number	01604-5991														
FAX number	01604-5991														
Rating required	1	(0=No,1													
Rate method	04	1T R													
Rate code	JK9VT														
Payables account	CD01														
Lin Internal Text <table><tr><td>1</td><td>Three month trial with MAERS</td></tr><tr><td>2</td><td></td></tr><tr><td>3</td><td></td></tr><tr><td>4</td><td></td></tr><tr><td>5</td><td></td></tr><tr><td>6</td><td></td></tr></table> Position to ____ Insert ____ after ____ Delete ____ from ____				1	Three month trial with MAERS	2		3		4		5		6	
1	Three month trial with MAERS														
2															
3															
4															
5															
6															
F3=Exit F4=Prompt F8= F5=Refresh F8=Update F12=Previous															
F13=Routes F21=Text															
14-42 SA MW KS IM II KENB20A PED171S1															

Fields:

Text

Enter any text you wish to have associated with the carrier.

Position To

The cursor will position to the Line entered here.

Insert

Type the number of the lines that you wish insert.

After

Type in the line number you wish the inserted lines to follow.

Delete

Type in the number of the line that you wish to start the deletion from.

From

Enter the number of lines that you wish to delete from this text.



Note: This text is for the planner's information regarding the carrier only, and is not printed on any documentation.



Press **F8=Update** to save the changes to file.

Route Maintenance



6/DTM

This function enables the definition of journeys which are to be undertaken by carriers (internal or external) between two geographical locations. All routes must be defined to the module.



Note: Before defining routes, the 'nodes' representing the origins and destinations for routes must be defined (please refer to Maintenance - Transport Nodes and Routes).

Maintain Routes Selection Screen



Select the Routes option.

Route

Code to represent the journey between two geographical locations (known as transport nodes). A customer delivery point is assigned a particular drop sequence along a route, which may be amended as part of building the load.



Press **Enter** to display the Maintain Routes
Details Screen.

Maintain Routes Details Screen



This screen is displayed when you have entered a valid route code into the Maintain Routes Selection Screen and pressed **Enter**, and displays details of the route code selected.

TP023B	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95
	Handy Wholesaler Depot 001		16:28:06
Maintain Routes			
Route.....	NHLT01		
Description.....	Northampton to Luton Route 01		
Default carrier.....?	MAERS	Maers Haulage	
Default vehicle type.....?	1TON	1 Ton with lifting Tailgate	
Origin.....?	MIDC	Central Midlands Depot 01	
Destination.....?	MIDW	Midlands western Depot 01	
Bill of lading required.....	1	{0=No, 1=Yes}	
Bill of lading format.....?	01	1T Bill of lading format 01	
Number of copies.....	1		
Default ship time.....	1:30		
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous 07-31 SF HW KS IM II KENB20A PED171S1			

Fields:

Description

Free text route description.

Default Carrier

Reference code for the default internal or external carrier that will be associated with the handling of transport requirements for this route.

Default Vehicle Type

The default type of vehicle that is to be associated with a load for this route. Vehicle types have gross weight and volume capacities defined to them and are used to check that these are not exceeded when building loads for this type of vehicle.

Origin

Origin associated with the route that has been assigned to a load. Origins must be defined as transport nodes and are printed on the bill of lading.

Destination

Destination associated with a route that has been assigned to the load. Destinations must be defined as transport nodes and are printed on the bill of lading.

Bill of Lading Required

Indicates if bill of lading documentation is required for a given route or load, or whether a load sheet is sufficient.

1 - Bill of lading documentation is required.

0 - A load sheet is sufficient.

Bill of Lading Format

Format required for the bill of lading documentation.



Note: Four formats are supported and are defined to the Inventory Descriptions file against major type 'TPBL', as follows:

01 - One document per load. Capacity totals (gross weight, volume, number of containers) from load header. Despatch notes associated with load.

02 - One document per drop/delivery point on route. Capacity totals (gross weight, volume, number of containers) per drop/delivery point. Despatch notes associated with drop/delivery point.

03 - One document per load. Capacity totals (gross weight, volume, number of containers) from load header. One totals line per drop. Despatch notes for each drop/delivery point.

04 - One document per load. Capacity totals (gross weight, volume, number of containers) per area and totals for load. Despatch notes associated with load.

Number of Copies

Number of copies of the bill of lading documentation required.

Default Ship Time

Default ship time assigned to route (for information only).



Note: Bill of lading information assigned to the route provides the defaults when creating loads. This can be overridden via the Maintain Loads function.

Functions:

F11

Delete the route (providing it is not defined to a delivery profile in this module).



Press **F8=Update** to save the details to file.

Area Maintenance

1... 7/DTM **2...**

This function enables the definition of areas or zones which can be used to group load drops in order to rate loads and split load documentation by area. Areas are associated with customer delivery points.

Area Maintenance Selection Screen



Select the Area Maintenance option.



Fields:

Area

Area code or zone to be associated with delivery points for rating and printing of bill of lading details.



Press **Enter** to display the Details Screen.



Delivery Profiles Maintenance



8/DTM

This function enables the definition of profile details for each delivery point that is to be considered by the module. A delivery profile must be set up for each customer delivery point or distribution centre to be considered whilst planning transport from this transport centre.

Maintain Delivery Profile Selection Screen

 Select the Maintain Delivery Profile option.

This screen enables the selection of the delivery profile criteria.

TP024A	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95
	Handy Wholesaler Depot 001		16:43:25
Maintain Delivery Profiles			
Sales company.....?.. HW Handy Wholesalers Ltd			
Customer.....?.. 0002 001			
F3=Exit F4=Prompt			
07-32 SF MW KS IM II KENB20A PED171S1			

Fields:

Sales Company

Sales Order Processing company.

Customer (inc. Seq. Code)

Customer account code and delivery sequence code as defined to Accounts Receivable.

 *Note: Sales company must be entered in order to prompt on the associated customers, as a transport centre can plan transport on behalf of multiple sales companies.*

 Press **Enter** to display the Maintain Delivery Profile Details Screen.

Maintain Delivery Profile Details Screen



This screen is displayed after the selection of a valid profile criteria on the Maintain Delivery Profile Selection Screen.

```

TP024B          HW - Handy Wholesalers Ltd          User GALBRAIJ 12/09/95
                Handy Wholesaler Depot 001          16:51:02
Maintain Delivery Profiles

Sales company..... ZM Multi-Currency Company

Customer..... G00          000 Graham Johnson
                                Royal Building
                                St. Andrews Cross

Default planning parameters:
Route .....?..   
Drop .....?..   
Carrier .....?..   

Area .....?..   
Customer exclusive loads ... 0 (0=No,1=Yes)
Confirm delivery time slot . 0 (0=No,1=Yes)

Deliveries allowed: Mon Tue Wed Thu Fri Sat Sun
                   0  0  0  0  0  0  0  (0=No,1=Yes)

F3=Exit          F4=Prompt          F8=Update          F11=Delete          F12=Previous
F13=Delivery time slots          F21=Text
11-31          Sf          MW          KS          IM          II          KENB20A          PED171S1

```

character Accounts Receivable account code and three character delivery sequence).

Confirm Delivery Time Slot

Indicates to the planner that the delivery point requires the confirmation of an appropriate delivery time slot at the customer's depot. If this flag is set to '1' the build load function highlights the customer name and delivery point with a flashing asterisk so that the planner can review the delivery profile if required and contact the customer to book a time slot.

Deliveries Allowed

Days on which deliveries can take place ('1'). The cursor should be on the appropriate day in order to enter delivery time slots. These are used for memo purposes only.



Note: The appropriate days are highlighted if delivery time slots exist.

Functions:

F13

Allows entry of delivery time slot details (see Delivery Time Slots section).

F21

Allows entry of planner text for customers.



*Note: **F21=Text** will be highlighted if text exists.*

Maintain Delivery Profile Time Slots Window (F13)



This window is displayed when you press **F13=Delivery Time Slots** from the Maintain Delivery Profile Details Screen and shows the times available for delivery.

TP024B	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95
	Handy Wholesaler Depot 001		16:51:02
Maintain Delivery Profiles			
Sales company..... ZM Multi-Currency Company			
Customer.....	G00	000 Graham Johnson	
		Royal Building	
		St. Andrews Cross	
Default planning parameters:			
Route	NHPT01	Northampton to Luton Route 01	
Drop		Delivery Time Slots	
Carrier	MAERS	Day..... Monday	
Area	NHPT	Time slot 1..... 1000 1200	
Customer exclusive loads ...	0 (0=No	Time slot 2..... 1400 1600	
Confirm delivery time slot .	1 (0=No	Time slot 3..... 0:00 0:00	
Deliveries allowed: Mon Tue Wed Thu F		Time slot 4..... 0:00 0:00	
1 1 1 1		F8=Update F12=Previous	
F3=Exit	F4=Prompt	F8=Update	F11=Delete F12=Previous
F13=Delivery time slots		F21=Text	
18-60	SF	MW	KS IM II KENB20A PED171S1

Fields:

Time Slot 1-4

Time slots (according to the 24-hour clock) defining times between which deliveries will be accepted by the customer.



Press **F8=Update** to save the details to file.

Maintain Delivery Profile Customer Text Window (F21)



This window is displayed when you press **F21=Text** from the Maintain Delivery Profile Details Screen.

TP024B	HW - Handy Wholesalers Ltd	User GALBRAIJ	12/09/95														
	Handy Wholesaler Depot 001		16:51:02														
Maintain Delivery Profiles																	
Sales company..... ZM Multi-Currency Company																	
Customer.....	G00	000 Graham Johnson Royal Building St. Andrews Cross															
Default planning parameters:																	
Route	NHLT																
Drop																	
Carrier	MAER																
Area	NHPT																
Customer exclusive loads ...	0																
Confirm delivery time slot .	1																
Deliveries allowed: Mon Tue Wed T																	
	1	1	1														
Customer Text <table border="1"> <thead> <tr> <th>Lin</th> <th></th> </tr> </thead> <tbody> <tr> <td>1</td> <td>Staff training day - depot closed</td> </tr> <tr> <td>2</td> <td>until 1030</td> </tr> <tr> <td>3</td> <td></td> </tr> <tr> <td>4</td> <td></td> </tr> <tr> <td>5</td> <td></td> </tr> <tr> <td>6</td> <td></td> </tr> </tbody> </table> Position to ____ Insert ____ after ____ Delete ____ from ____				Lin		1	Staff training day - depot closed	2	until 1030	3		4		5		6	
Lin																	
1	Staff training day - depot closed																
2	until 1030																
3																	
4																	
5																	
6																	
F3=Exit	F4=Prompt	F8=	F5=Refresh F8=Update F12=Previous														
F13=Delivery time slots	F21=Text																
15-52	SW	MW	KS IM II KENB20A PED171S1														

Fields:

Text

Enter any text you wish to have associated with the customer.

Position To

The cursor will position to the line entered here.

Insert

Type the number of the lines that you wish insert.

After

Type in the line number you wish the inserted lines to follow.

Delete

Enter the number of lines that you wish to delete from this text

From

Type in the number of the line that you wish to start the deletion from.



Note: This contains internal text, for the planner's information only. It is not printed on any documentation.