

-
-
-
-
-

Chapter 10

Inventory Utilities



Company Profile Maintenance

This procedure has three purposes:

- To maintain company details and defaults for the Inventory application. (If you have activated Advanced Order Entry, these parameters are maintained within Inventory Management.)
- To create and maintain stockrooms for a company.
- To create and maintain usage profiles for a company.



Warning: If there is a Copy Company option within Utilities, JBA strongly recommend that you use this option to create a new company. You can use the Copy Company option to copy existing parameters and miscellaneous codes to your new company. You can amend these details using your maintenance and utility options.

Maintain Company Profile Selection Screen

1/INU

 Select Maintain Company.

Use this screen to select the company you want to maintain.

```

IN010                                User  GBJBARW2    8/11/95
                                      12:24:57

Maintain Company Profile
Sel  Company
-   AC  Acceptance test - Process
-   BJ  BJ
-   CP  Z1 QA company V3.2
-   JW  JW - Jeff's Company
-   JW  JW - Jeff's Company
-   MA  Mathews Company
-   MD  Repetitive Production
-   PM  Process Manufacturing Test Com
-   RP  JBA Production Company
-   RW  ROBS COMPANY
-   SF  Simon Fishers Test Company
-   SH  Steves Manufacturing Company
-   SS  Steve Hughes Test Company
-   ST  Style
-   S1  System Test One
-   TE  TE Base Test Company
-   TS  TESTPRO - TEST COMPANY
1=Select
F3=Exit
+

14-03  SF  MV  KS  IM  II  KENB20A  PET178S2
  
```

Fields:

Sel

Select. Enter 1 against the company you want to maintain. This displays the second screen.

 Select a company.

Maintain Company Profile Stockroom Screen



To display this screen enter 1 against the company you want to maintain on the Maintain Company Profile Selection screen.

Use this screen to select the aspect of the company profile you wish to maintain.

IN010	Neil Radford and Co. Ltd	User GBJBA1MS	6/13/96 9:23:19
Maintain Company Profile			
Press ENTER to process Company OR enter			
Stockroom code.....?.. █		OR enter	
Usage profile code...?.. _			
F3=Exit F4=Prompt F12=Previous			
07-27	SP	MW	KS IM II KENB20A PET178S2

Fields:

Stockroom Code

Enter a stockroom code, either an existing code for amendment or a new code for addition, and press **Enter** to maintain the stockroom profile. For more information see the fourth Maintain Company Profile screen.

Usage Profile Code

Enter the code of the usage profile you want to maintain using a two digit code.

You can either enter an existing code for amendment or a new code for addition. Press **Enter** to maintain the usage profile.

Inventory Management uses the Usage Profile to nominate historical data, by week or month, that is used to calculate average usage. Inventory Management uses this code to make reorder recommendations. You can define different usage profiles to reflect differing trends of usage. For more information see the Select Usage Code window.



Leave the stockroom and usage profile codes blank and press **Enter** to maintain company profile data for the selected company.

Maintain Company Profile Screen



To display this screen leave the stockroom and usage profile codes blank and press **Enter** on the Maintain Company Profile Stockroom screen.

Use this screen to maintain the company name and default parameters for the company.

```

IN010          Inventory Valuation test company..# User GBJBA1MS    20/10/99
                                           8:45:20

Maintain Company Profile

Company name..... Inventory Valuation test compa
Costing method (S,L,A,F)..... S          Extended Lot Details
Specification 1 description... Pallet Conv   Batch controlled..... 1 (0/1)
Specification 2 description... Volume       Lot controlled..... 0 (0/1)
Specification 3 description...              Serial controlled.... 0 (0/1)
General ledger account..... 310000
Sales GL account..... 701100          Packaging reporting.... 1 (0/1)
Cost of sales GL account..... 601100      Default Country...?.. ___
Price variance GL account..... 605000      Sales Channel.....?.. ___
Usage cycle..... W
Default reorder policy.....?.. 1 Upto MAX
Reorder quantity factor %..... 10
Stock carrying rate %..... 20.00
Order placement cost..... 3.00000
Purchasing in use..... 1 (0=No,1=Yes)
SOP in use..... 2 (0=No,1=SOP attached,2=A0E attached)
Date last changed..... 17/10/97

F3=Exit F4=Prompt F9=Sec.UOM F10=Extras F12=Previous
F15=Reference numbers F20=Packaging Countries
  
```

Fields:

Company Name

You cannot maintain the company name from within the Inventory Management application.

Costing Method

Enter one of the following to specify the company's costing method:

- L - Latest costing.
- A - Average costing.
- S - Standard costing.
- F - FIFO costing.

This costing method is the default method for each product within this company.

You can change it for individual products.

Specification N Description

Where n is 1 to 3. You can define three numeric specifications for each product, using up to 15 characters.

The description for each specification appears alongside the specification on the product maintenance screen. Typically you use these specifications to define some

dimension of a product not provided in the standard data. Standard Processing makes no use of the specifications.

General Ledger Account

Enter up to 12 alphanumeric characters. This is the default account number in the General Ledger to which purchase invoices are posted if the Purchase Management application is in use.

Sales GL Account

Enter up to 12 alphanumeric characters. This is the default account number in the General Ledger to which stock transaction values are posted.

Cost Of Sales GL Account

Enter up to 12 alphanumeric characters. This is the default account number in the General Ledger to which cost of sales transaction values are posted if the Sales Order Processing application is in use.

Price Variance GL Account

Enter up to 12 alphanumeric characters. This is the default account number in the General Ledger to which accruals are posted if the Purchase Management application is in use.

Usage Cycle

Enter one of the following to define the basis for Inventory to calculate average usage.

M - To maintain usage figures by month, and to express average usage as average usage/month.

W - To maintain usage figures by week, and to express average as average usage/week.

The system automatically records usage of all items at stockroom and company level.



Note: The usage figure is based on all types of Issue movements and Transfers Out. Four of the Reorder Policies make use of an average usage figure. To set the system to calculate this, you need to define usage profile codes.

Default Reorder Policy

Enter one of the following to specify the company's normal reorder policy:

1 - Up To Max. When expected stock drops below the reorder point the system suggests that an order be placed of sufficient size to take the stock level up to the maximum.

2 - Reorder Quantity (ROQ). When expected stock drops below the reorder point the application suggests that the reorder quantity be ordered.

You can set this quantity yourself, or it can be determined by the application. You can hold a Reorder Quantity Factor at stockroom level or as a default on the company profile. If the reorder quantity factor was 30%, the application recommends action to reorder enough stock to last through 30% of the lead time. If the factor was

200% the application recommends action to reorder enough stock to last through twice the lead time.

3 - Up To ROP. When expected stock drops below the reorder point the application suggests that you order enough to take the level up to the reorder point again. For example, if you set the reorder point to zero, this rule would re-order goods when there is demand for them, for example, from a customer or manufacturing order.

4 - Up To Min. When expected stock drops below the reorder point the system suggests that you order enough stock to take the balance back up to the minimum level.

5 - EOQ. When expected stock drops below the reorder point the system suggests that you place an order for the calculated or maintained economic order quantity.

This re-order policy is then the default for all products in all stockrooms, you can, however, change it for a particular product or stockroom.

Reorder Quantity Factor %

Define, as a percentage, the number of lead times worth of average usage you want re-ordered, for example, 100% is 1 lead times worth, 150% is 1.5 lead times worth.

This is used to calculate reorder quantity for those item/stockroom combinations where the reorder policy is ROP and you have not specified a reorder quantity.

Stock Carrying Rate %

Enter the percentage cost of carrying a stock item for a year using up to five numeric characters with two decimals. Inventory Management uses the rate in the economic order quantity calculations.

Order Placement Cost

Enter the cost in base currency of placing and processing a purchase order using up to five numeric characters with two decimals. Inventory used this in economic order quantity calculations.

Purchasing In Use

Enter one of the following:

- 0 - Purchase Management not in use.
- 1 - Purchase Management application is in use

SOP In Use

Enter one of the following:

- 0 - Sales Order Processing application is not in use.
- 1 - SOP Attached. Sales Order Processing is in use.
- 2 - AOE Attached. Advanced Order Entry is in use.

Extended Lot Details

There are three options:

- Batch controlled.
- Lot controlled.
- Serial controlled.

Enter one of the following:

0 - For the system to ignore extended detail control.

1 - To make extended detail control mandatory.

Packaging Reporting

Enter one of the following:

0 - To not report on the packaging usage.

1 - To report on the packaging usage for this company.

Default Country

Inventory Management displays this field when you start the packaging reporting flag.

Enter the default reporting country.

Sales Channel

This field is displayed when you set the packaging reporting flag.

Enter the sales channel you wish to use for packaging reporting.

Functions:

F9

Sec UOM. The Secondary UOM window is displayed.



Note: This function is displayed if Catchweight can be used. To use Catchweight, you must have a valid authorisation code.

F10

Extras. The Extended Options window is displayed.

F15

Reference Numbers. The Reference Number Entry window is displayed.

F20

Packaging countries. This function key is displayed if you have set the packaging reporting flag. Use this function to access the screens used to set up the packaging reporting information, for more information, see Country Details Maintenance in Packaging Requirements.



Once you have made the required amendments, press **Enter** to update the company profile.

Secondary UOM Window (F9)



To display this window select **F9=Sec** on the Company Profile Maintenance screen.



Note: This function is displayed if Catchweight can be used. To use Catchweight, you must have a valid authorisation code.

The Secondary UOM window is displayed.

Fields:

Secondary UOM

Enter an existing unit of measure. If you do not know what to enter, you can prompt the field and display the Units Of Measure window containing a list of configured units of measure. You can set these up using the Secondary UOM Maintenance option.

Tolerance %

When an item's secondary value is captured during a relevant transaction, the default plus or minus degree of deviation from the expected nominal value can be set by entering a percentage number in this field. If you exceed this percentage tolerance during a transaction, Inventory displays warning message. For example if you enter 5 in this field, any transaction that exceeds the expected nominal value by plus or minus 5%, will cause the warning message to display.

Tolerance Value

When an item's secondary value is captured during a relevant transaction, the default plus or minus degree of deviation from the expected nominal value can be set by entering an absolute value in this field. If you exceed this fixed value tolerance during a transaction, Inventory displays a warning message. For example if you enter 5 in this field, any transaction that exceeds the expected nominal value by plus or minus 5kg (if the UOM is kilos) will cause the warning message to display.



Note: Tolerance percentages or values are defined only for Catchweight item types 1 and 2. Default values can be displayed and amended during Catchweight item creation.



Note: You can enter a number in either the Tolerance percentage field or the Tolerance Value field, but you cannot enter a number in both.



Note: If both the Tolerance Percentage or Tolerance Value fields are empty, then there is no tolerance and a warning is displayed for anything other than the default.



Select **F8=Update** to save the selected entries in the Secondary UOM window, and display the Maintain Company Profile screen.

Extended Options Window (F10)



To display this window select **F10=Extras** on the Company Profile Maintenance screen.

Use this window to define the centralised processing of delivery documentation and designation of the default item search. If Advanced Order Entry is installed you can determine whether you can enter decimal quantities on orders.

```
IN010 Neil Radford's Test Company User GBJBANER 17/12/96 11:45:46
Maintain Company Profile
Company name..... Neil Radford's Test Company
Costing method (S,L,A,F)..... S Extended Lot Details
tion 1 description... pallet Conv Batch controlled..... 0 (0/1)
Specif Extended options
Specif
Genera Integer quantities..... 1 (0=No,1=Yes)
Sales Stockroom fiscal close..... 2 0=No,1=Month End,
Cost o 2=Manual
Price Latest and average cost calculation.. 2 1=Exclusive of misc.rec.
Usage 2=Inclusive of misc.rec.
Defaul Centralised delivery documents..... 0 0=No,1=Optional
Reorde 2=Mandatory
Stock Default item search option..... 1 1=Item reference
Order 2=Inventory description
Purcha 3=Purchasing description
SOP in 4=Alternative reference
Date 1 5=Search characteristics
F3=Exit F5=Refresh F12=Previous
10-50 SF MW KS IM II EDN400A PET165S2
```

Fields:

Integer Quantity

This field is displayed if Advanced Order Entry is live. Enter one of the following:

- 0 - To enter decimal quantities.
- 1 - Item quantities on orders can only be integers.

Stockroom Fiscal Close

Used in Inventory Revaluation. Enter one of the following:

- 0 - To not perform a stockroom fiscal close.
- 1 - To perform a stockroom fiscal close as part of Inventory's Period End process.
- 2 - To perform stockroom fiscal close manually.

Latest And Average Cost Calculation

Enter one of the following:

- 0 - To exclude miscellaneous receipts of stock from Latest and Average cost calculations.
- 1 - To include miscellaneous receipts of stock from Latest and Average cost calculations.

Centralised Delivery Documents

Enter one of the following:

- 0 - To generate separate despatch/delivery documentation by each function.
- 1 - To generate centralised delivery documentation where additional details have been specifically entered for the transaction.
- 2 - To generate centralised delivery documentation for all movement of goods.

Default Item Search Option

Enter one of the following to specify the search criteria on the item search facility:

- 1 - Item reference.
- 2 - Inventory description.
- 3 - Purchasing description.
- 4 - Alternative reference (only available if Advanced Order Entry live).
- 5 - Search characteristics (only available if Advanced Order Entry live).
- 9 - Search by base item (only available if Production and Configurator live).

Reference Number Entry Window (F15)



To display this window select **F15=Reference Numbers** on the previous company profile screen.

Use this screen to enter document processing reference numbers

IN010		Neil Radford and Co. Ltd		User GBJBA1MS		6/13/96	
						9:25:23	
Maintain Company Profile							
Com	Reference Number Entry						S
Cos							
Spe	Code.....	NR					. 1 (0/1)
Spe	Description..	Neil Radford and Co. Ltd					. 1 (0/1)
Spe							. 1 (0/1)
Gen							
Sal	Reference type		Reference		Last number		
Cos	Internal Transfer		Code(?)		Used		
Pri			1450 NRA				
Usa							
Def							
Reo							
Sto							
Ord	F4=Prompt F8=Update F12=Previous						
	Purchasing in use.....	1	(0=No,1=Yes)				
	SOP in use.....	1	(0=No,1=SOP attached,2=A0E attached)				
	Date last changed.....	6/12/96					
F3=Exit F4=Prompt F10=Extras F12=Previous F15=Reference numbers							
12-48		SA	MW	KS	IM	IT	KENB20A PET178S2

Fields:

Code

Company profile code.

Description

Company description.

Reference Type

This is the document processing option: invoice or credit notes.

Reference Code

Optionally enter a new reference number or select a default one.

Last Number Used

This is the reference number last used for the document processing option currently selected.

Maintain Company Profile Screen 2



To display this screen select to maintain a stockroom profile from the Company Profile Initial screen.

Use this screen to create and maintain stockroom profiles.

IN010	UK Demonstration Company	User GBJBALTW	3/06/98 12:56:35
Maintain Company Profile			
Stockroom.....	01	Central Stockroom	
Include in valuation.....	1	(0=No,1=Yes)	
Stockroom usage code.....?	G	General Stockroom	
Department.....?	A	Sales	
Stockroom site.....?	STUDLEY	Studley	
Transaction allowed (0=No,1=Yes)		Consignment Stock	
		EDI Updates (1/0)	
Receipts.....	1	0	
Issues.....	1	0	
Adjustments.....	1	0	
Consignment stock consumption.	0	0	
Inventory balance updates		0	
Transfers.....	1		
Supplier orders.....	1		
Sales orders.....	1		
Negative stock allowed.....	1	(0=No,1=Yes)	
F3=Exit F4=Prompt F10=Extras F12=Previous			

Fields:

Stockroom

Enter the stockroom name using up to 25 alphanumeric characters.

Include In Valuation

Enter one of the following:

0 - To exclude the stockroom from valuation.

1 - To include the stockroom in valuation.

Stockroom Usage Code

Enter the usage code associated with this stockroom. This standard application uses this code for information only. Stockroom usage codes are defined in the Descriptions file against major type STKU.

Department

Enter a department code associated with this stockroom. The standard application uses this data for information only. Department codes are defined on the Descriptions file against major type DEPT.

If the Production system, MRP Cellular Planning function is in use, then you must enter a three character cell code to indicate the cell manager responsible for the supply and demand requirements of this stockroom. For each cell code defined, you should define an equivalent department code on the Production Parameters file.

Stockroom Site

Use this to define the output print queue of the delivery documentation

Transaction Allowed:

Receipts

Enter one of the following:

- 0 - To exclude the stockroom from goods receiving activities.
- 1 - To receive goods at this stockroom.

Issues

Enter one of the following:

- 0 - To exclude the stockroom from goods issuing activities.
- 1 - To issue goods from this stockroom.

Adjustments

Enter one of the following:

- 0 -Adjustments may not be made at this stockroom.
- 1 - Adjustments may be made at this stockroom.

Consignment Stock Consumption

Enter one of the following:

- 0 - To allow consignment stock consumption in this stockroom.
- 1 - To not allow consignment stock consumption in this stockroom.

Transfers

Enter one of the following:

- 0 - To not initiate transfers from this stockroom.
- 1 - To initiate transfers from this stockroom.

Supplier Orders

Enter one of the following:

- 0 - To not initiate supplier orders from this stockroom.
- 1- To initiate supplier orders from this stockroom.

Sales Orders

Enter one of the following:

- 0 -To not take sales orders against this stockroom.
- 1 - To take sales orders against this stockroom.

Negative Stock Allowed

Enter 1 to enable negative item balances at this stockroom, otherwise 0.

Functions:

F10

Extras. To display additional order entry options if you are using Advanced Order Entry.



Press **Enter** to update the stockroom profile and to display the stock weeks matrix associated with this stockroom.

Advanced Order Entry Options Window (F10)



Note: This screen is displayed if Advanced Order Entry is in use.

Use this screen to enter the Advanced Order Entry Allocation options.

IN010	Neil Radford and Co. Ltd	User GBJBA1MS	20/06/96 14:08:02
Maintain Company Profile			
Stockroom.....	01	Neil's Stockroom 01	
Include in valuation.....	1	(0=No,1=Yes)	
Stockroom usage code.....?	-		
Department.....?	-		
Stockroom site.....?	CENTRAL	fftfyt	
Advanced order entry options			
Transaction			
Receipts...	Automatic lower level allocation...	0	(0=No, 1=Yes)
Issues.....	Manual lower level allocation.....	0	(0=No, 1=Yes)
Adjustments	Allocation at batch level.....	0	(0=No, 1=Yes)
Transfers..	Allocation at serial level.....	0	(0=No, 1=Yes)
Supplier or	Allocation at lot level.....	0	(0=No, 1=Yes)
Sales order	Alternative kit allocation.....	0	(0=No, 1=Yes)
F5=Refresh F12=Previous			
F3=Exit F4=Prompt F10=Extras F12=Previous			
13-53 SF MW KS IM II KENB20A PET166S2			

Fields:

Automatic Lower Level Allocation

Enter one of the following:

0 - Not required.

1 - To automatically allocate orders against specific lots, batches and/or serial numbers when you produce pick notes.

Manual Lower Level Allocation

Enter one of the following:

0 - Not required.

1 - To allocate against specific lots, batches or serial numbers at the time of order entry or when you amend an order. The ability to allocate against lot numbers depends on the settings of the allocate at flags described below.

The next three turn on each type of lower level allocation:

Allocation At Batch Level

Enter one of the following:

0 - Not required.

1 - If lower level allocations are to be valid for batches.

Allocation At Serial Level

Enter one of the following:

0 - Not required.

1 - Lower level allocations are to be valid for items controlled at serial number level.

Allocation At Lot Level

Enter one of the following:

0 - Not required.

1 - If lower level allocations are to be valid for lot controlled items.

Alternative Kit Allocation

Enter one of the following.

0 - To only allocate component items if you can allocate the whole kit.

1 - To allocate component items whether you can allocate the whole kit, or not.



Press **Enter** to display the third Maintain
Company Profile screen.

Maintain Company Profile Screen 3

-  To display this screen press **Enter** on the Maintain Company Profile screen 2.
-  Alternatively, select Regenerate ABC classification in Stock Counting.

```

IN010          Demonstration Company          User GJBAMV1   16/11/95
                                                14:43:37

Maintain Company Profile

Stockroom..... #P   Plymouth
V
A  0.000      +--- 1 ---+--- 2 ---+--- 3 ---+   Stock weeks code
L              | Class  A | Class  A | Class  A |   1 Low val/low usg.
U      to      | Min   .0 | Min   .0 | Min   .0 |   2  /med usg.
E              | Max   .0 | Max   .0 | Max   .0 |   3  /hi usg.
              +--- 4 ---+--- 5 ---+--- 6 ---+
              | Class  A | Class  A | Class  A |   4 Med val/low usg.
              | Min   .0 | Min   .0 | Min   .0 |   5  /med usg.
              | Max   .0 | Max   .0 | Max   .0 |   6  /hi usg.
              +--- 7 ---+--- 8 ---+--- 9 ---+
              | Class  A | Class  A | Class  A |   7 Hi val /low usg.
              | Min   .0 | Min   .0 | Min   .0 |   8  /med usg.
              | Max   .0 | Max   .0 | Max   .0 |   9  /hi usg.
              +---+---+---+
              0.0 to   .000 to   .000  USAGE  Last change 16/11/95

F3=Exit  F11=Delete  F12=Previous

00-29      SA      MW      KS      IM      II  KENB20A  PET129S1
  
```

Fields:

During the update routines (weekly or monthly) you are prompted to run the regenerate ABC classification, during which items are reviewed and re-classified accordingly and next count dates calculated.

A three by three matrix is displayed on the screen. The Y axis, labelled value, is the unit cost of the item held in the selected stockroom. The X axis, labelled usage, is the most recently calculated average usage for any item in the stockroom. This means each square relates to a value/usage category.

By specifying low/medium and medium/high boundaries you have defined nine cells that represent the following categories for items in this stockroom.

The minimum and maximum stock holdings for each category are expressed in number of weeks of average usage. The date the matrix was last changed is displayed.

Enter the following details for each cell:

Min

Enter three numeric characters, one decimal, to specify the minimum weeks stock to hold for the category.

Max

Enter three numeric characters, one decimal, to specify the maximum weeks stock to hold for the category.

Class

Enter A, B, C or Z to assign a classification to all items that fall within this value/usage category.

Historically A class items are high value/high usage, whereas C class items are low value/low usage.

You can request stock counting by ABC classification and define a profile so that higher value items are counted more frequently than lower value items.

If you enter the classification Z for items, ABC Classification count creation will ignore them.

Value 1

Enter fifteen numeric characters, five decimals, to specify the first value de-limiter. Any item with a unit cost less than or equal to this value are in categories 1, 2 or 3.

Value 2

Enter fifteen numeric characters, five decimals, to specify the second value de-limiter. Any item with a unit cost between this value and value 1 are in category 4, 5 or 6. Items with a unit cost over this value are in category 7, 8 or 9.

Usage Qty 1

Enter eleven numeric characters, three decimals, to specify the first usage de-limiter. Items with an average usage up to this quantity are in category 1, 4 or 7.

Usage Qty 2

Enter eleven numeric characters, three decimals, to specify the second usage de-limiter. Items with an average usage between quantity 1 and this quantity are in category 2, 5 or 8. Items with an average usage over this quantity are in category 3, 6 or 9.

During the Ad-hoc Update, for each included item, the system reviews the item's cost and average usage, thus identifying an appropriate square and then selecting the number of minimum and maximum weeks.

The system then calculates:

Reorder Point $(\text{Minimum Stock Weeks} + \text{Lead Time in Weeks}) \times \text{Average Usage}$

Maximum Stock $\text{Minimum Stock Weeks} \times \text{Average Usage}$

Economic Order Quantity

$$\sqrt{\frac{(2 \times \text{order placement cost} \times \text{annual usage})}{\text{inventory holding cost per year}}}$$



Note: Any stockroom balance records found without an associated item master or stockroom detail record are written to an exception report.

The Stockroom details record would now include the calculated figures. (In other words, as seen on the Inventory Maintenance screen.)



Press **Enter** to update the stockroom weeks matrix.

Select Usage Code Window



To display this window use the prompt facility in the Usage Profile Code field.

Use this window to select the usage code you require.

The screenshot shows a main window titled 'Maintain Company Profile' with the following text: 'IN010 Demonstration Company User GBJBAMV1 16/11/95 14:05:54', 'Press ENTER to process Company OR enter', 'Stockroom code.....?.. OR enter', and 'Usage profile code...?.. ?'. A sub-window titled 'Select Usage Code' is open, showing a table with three columns labeled 'Code'. Below the table, it says '1=Select Usage Code', 'F5=Refresh F12=Previous', and 'II KENB20A PET129S1'. The main window footer includes 'F3=Exit F4=Prompt F12=Previous', '08-28 SA MW KS IM', and 'II KENB20A PET129S1'.

Fields:

Usage Profile Code

You can add and edit a set of profiles that define the historical periods used in the calculation of average weekly or monthly usage. These are used for items with significant seasonal variations in sales.

Select the profile to display the weekly or monthly periods, depending on the usage cycle defined on the company profile. You can define the usage pattern for the current and previous 59 periods, so, depending on the period definition, the history can go back one and a quarter or five years.

To include a period in the average usage calculation enter 1 under it. The default, 0, omits the period from the calculation.

For example,

<u>-1</u>	<u>-2</u>	<u>-3</u>	<u>-4</u>	<u>-5</u>	<u>-6</u>	<u>-7</u>	<u>-8</u>	<u>-9</u>
<u>1</u>	<u>1</u>	<u>1</u>	<u>0</u>	<u>0</u>	<u>0</u>	<u>0</u>	<u>0</u>	<u>0</u>

The date the usage profile was last changed is displayed. The calculations are based on the last 3 weeks/months usage figures.

An appropriate usage profile code is then assigned to each item in the Stockroom details file.

Stockroom Site Maintenance



2/INU

Use this option to maintain stockroom sites. This in turn allows the definition of the output queue appropriate to the printing of delivery documentation.

Stockroom Site Maintenance Selection Screen



Select Stockroom site from the menu.

Use this screen to select the stockroom that you want to maintain.

IN975	NR - Neil's Test Company	User GJBANER	21/05/96
Stockroom Site Maintenance			11:32:20
Stockroom site....?.. █			
F3=Exit F4=Prompt			
05-24	SA	MW	KS IM II KENB20A PET178S1

Fields:

Stockroom Site

Enter a stockroom site to create or maintain. You can enter a maximum of 10 characters.



Press **Enter** to display the second screen.

Stockroom Site Maintenance Screen



To display this screen enter a Stockroom Site and press **Enter** on the Stockroom Site Maintenance Selection screen.

Use this screen to maintain the stockroom site details. Inventory Management displays any information for an existing stockroom site for amendment.



Tip: Once defined, you must assign stockroom sites to Inventory stockrooms through the second Stockroom Site Maintenance screen, if you wish to use centralised document processing.

IN975	NR - Neil's Test Company	User GJBANER	21/05/96 11:33:18
Stockroom Site Maintenance			
Stockroom site..... W1			
Site name.....			
Documentation output queues:			
Delivery Notes			
Output queue.....			
Library.....			
Combined Delivery Note/Invoice			
Output queue.....			
Library.....			
F3=Exit F8=Update F12=Previous F15=Reference numbers			
07-24 SA MW KS IM II KENB20A PET178S1			

Fields:

Site Name

Enter a description or name for the stockroom site.

Delivery Note

Enter a valid output queue and library for delivery note.

Combined Delivery Note/Invoice

Define a valid output queue for combined delivery notes/invoices. If left blank the fields default to the queue/library defined for delivery notes when you press **Enter**.



Tip: You cannot update a stockroom site until you have defined reference numbers for it. For further details see the Document Processing module.

Functions:

F15

Reference Numbers. Define reference code for the stockroom site. The Reference Number Entry window is displayed.



Press **F8=Update** to save the details you have entered.

Reference Number Entry Window (F15)

 To display this window select **F15=Reference Numbers** on the Stockroom Site Maintenance screen.

Use this screen to view reference numbers for amendment/information purposes. You can also view the type of documentation to which the reference number refers (see Reference Numbers).

IN975		Z1 - UK Demonstration Company		User GBJBANB4		4/02/98	
Stockroom Site Maintenance						12:04:48	
Sto							
Sit	Code..... CENTRAL						
Doc	Description.. central site						
Del	Reference type	Reference	Last number				
Ou	Container References	Code(?)	Used				
Li	Container References						
Com	Delivery Notes		B000210				
Ou							
Li							
F3=Exit F8=Update F12=Previous F15=Reference numbers							
12-40 SA MW KS CL IM DM II MARVIN KB PET087S1							

Fields:

Reference Code

Enter a defined reference code. This must be fully defined and held on the Inventory descriptions file.

 Select **F8=Update** to save any changes you make.

Reference Numbers



3/INU

Use this option to maintain reference numbers. Reference numbers are used to define separate sequences of despatch note references for each stockroom site.

Maintain Reference Numbers Selection Screen



Select Reference Numbers.

Use this screen to select the reference type and reference code that you want to maintain.

IN977	NR - Neil's Test Company	User GJBANER	21/05/96 11:38:04
Maintain Reference Numbers			
Reference type...?.. _____			
Reference code...?.. _____			
F3=Exit F4=Prompt			
05-23	SA	MW	KS
		IM	II
		KENB20A	PET178S1

Fields:

Reference Type

This should be defined to the descriptions file as a minor type, for example CREDITNOTE defined against major type RFTP.

Reference Code

This is a major type code as defined to the descriptions file RFCD.



Enter the details and press **Enter** to display the Maintain Reference Numbers screen.

Maintain Reference Numbers Screen



To display this screen enter the details and press **Enter** on the Maintain Reference Numbers Selection screen.

Use this screen to maintain the reference number information for amendment.

IN977	NR - Neil's Test Company	User GJBANER	21/05/96 11:40:08
Maintain Reference Numbers			
Reference type..... CREDITNOTE Credit Note			
Reference code.....			
Last number used.... 1			
Next number to use.. 2			
From reference:			
Prefix.. Number.. 1			
To reference:			
Prefix.. Number.. 99			
F3=Exit F8=Update F12=Previous			
10-23	SA	MW	KS IM II KENB20A PET178S1



Tip: Numbers may comprise an optional, single alpha character prefix and up to seven numeric characters.



Tip: If you wish to prefix the reference number to an alpha character, you must make the leftmost numeric character zero.

Fields:

Last Number Used

This is the number used for the last transaction for the displayed type of documentation (in this case a credit note).

Next Number To Use

The next sequential number.

From Reference

Define a start number range.

To Reference

Define an end number range.



Press **F8=Update** to save any details you have entered.

Document Text Profiles



4/INU

Use this option to maintain document text profiles.

Document Text Profile Maintenance Selection Screen



Select Document Text Profiles.

Use this screen to select the text profile you want to maintain.

IN046	NR - Neil's Test Company	User: GBJBANER	21/05/96 11:41:33
Document Text Profile Maintenance			
Sel	Document Class		
■	Acknowledgements		
-	Pick Notes		
-	Delivery Notes		
-	Invoices		
1=Select F3=Exit			
06-03	SA	MW	KS IM II KENB20A PET178S1

Fields:

Sel

Select. Enter 1 to select the type of documentation you want to define.

Document Class

The types of document that can be maintained from this screen are:

- Acknowledgements.
- Pick Notes.
- Delivery Notes.
- Invoices.



When you have selected a type of documentation press **Enter** to display the Document Text Profile Maintenance Details screen.

Document Text Profile Maintenance Details Screen



To display this screen select a type of documentation and press **Enter** on the Document Text Profile Maintenance Selection screen.

Use this screen to enter the text details.

IN046	NR - Neil's Test Company	User GJBANER	21/05/96 11:43:58
-------	--------------------------	--------------	----------------------

Document Text Profile Maintenance

Document Class.. Pick Notes

Sel	Text Type/Usage	Position	Seq.
_ 0 S	Order Header Text / Sales Office Memos	Header	1

Text type..?..	█
Text usage..?..	_
Position.....	_ 1=Header, 2=Detail, 3=Trailer
Sequence.....	_

1=Select 4=Delete
F3=Exit F4=Prompt F12=Previous

17-18	SA	MW	KS	IM	II	KENB20A	PET178S1
-------	----	----	----	----	----	---------	----------

Fields:

Sel

Select. Enter one of the following:

- 1 - To select for amendment.
- 4 - To select for deletion.

Text Type

Enter the type of text you wish to use on the documentation, for example Order Header.

Text Usage

Enter the code to define where you can use this text.

Position

Enter one of the following to define the position of the text on the document:

- 1 - Header.
- 2 - Detail.
- 3 - Trailer.

Sequence

This is the sequence in which the text is presented on the documentation.



Press **Enter** to save any details to file.

Default Text Types

5/INU

This option links the primary text type/usage code and the default or secondary text type/usage code. This screen displays default text (held in the descriptions file) for information or amendment.

IN052	NR - Neil's Test Company	User GJBANER	21/05/96
			11:45:36
Default text maintenance			
Sel	Text type/usage	Default text type/usage	
- 0 E	Order Header Text	C E Customer Text	
	External Text	External Text	
Text type.....?.. -			
Text usage.....?.. -			
Default text type..?.. -			
Default text usage.?.. -			
1=Select 4=Delete			
F3=Exit F4=Prompt			
06-03 SA MW KS IM II KENB20A PET178S1			

Fields:

Sel

Select. Enter one of the following:

1 - To amend.

4 - To delete.



Note: When you select amend, the current details are displayed in the fields at the bottom of the screen.

Text Type

Select the type of text you wish to use on the documentation, for example, Order Header.

Text Usage

Select the code to enable this field to be used as a memo field available for user defined records.

Default Text Type/Usage

These are the default values for the text type and usage, which are stored in the Descriptions file defined as major type USGC.



Press **Enter** to save any details you have

entered.

Copy Company



11/INU

This option is the only way to create a new company within Inventory Management. The option copies the company profile and Descriptions file. You can then complete the new company information using the company maintenance option.

From Company

Enter the company code of the company from which you want to copy data.

To Company

Enter the company code of the company to which you want data copied.



Note: This company code should not exist already within the application.

Rebuild Item Search



12/INU

Use this option to refresh the Item Master Scan.

You should run this option if:

- You have converted files from another system and therefore need the scan redefining.
- You have made changes to the item description and/or text and need to re-build the text.

Renumber Item Search Words



13/INU

This procedure renumbers the search words associated with each item.

The function is submitted directly from the menu, with no selections or parameters required.



Select **F8=Confirm Submit** to process the batch job.

Set Balance Quantities To Zero



14/INU

This option sets all the primary and secondary balances in the Stockroom Details file (INP60) to zero.

This should only be used in a test environment as no adjustment records are generated.



Select **F8=Confirm Submit** to process the batch job.

Build Item Deletion Logical Files



15/INU

You can use this option as part of the item deletion routine (see Item Deletion for more details).



Select **F8=Confirm Submit** to process the batch job.

Database Integrity

16/INU

The purpose of this procedure is to check the integrity of the items data across several files. These are:

- Item Master - INP35.
- Stockroom Balance - INP60.
- Stockroom Profile - INP20.
- Stock Location - INP80.
- FIFO Costs - INP83.

No automatic adjustments are made but a report is produced highlighting the errors for manual amendment.



Note: You should run this on a weekly basis initially, then run monthly, quarterly, and finally on an ad hoc basis. It is suggested that you run this option in the Bottom-Up Validation format.

```
IN900CLP                                User GBJBALTW      0/00/00
                                           13:05:06

Inventory Integrity Menu

1. Top-down validation.
2. Bottom-up validation.

Company code.... 01
Enter option.... 01
Message type.... 2      1 = warning and serious messages will print,

F3=Exit  F6=Messages
```

Fields:

Company Code

Enter the company code of the company for which this integrity processing should be done.

Enter Option

Enter one of the following:

- 1 - Validate using Top-Down Validation.
- 2 - Validate using Bottom-Up Validation.

Message Type

Enter one of the following:

- 1 - To print warning and serious messages.
- 2 - To only print serious messages. This is the default.

The routine processes as follows:

Top-Down Validation

This function reads the Item Master Records and performs the following integrity checks:

1. The procedure checks that each item has at least one item/stockroom record associated with it. A warning message is printed if this is not the case.
2. The procedure checks that a stockroom profile record exists for each stockroom defined on a stockroom balance record. A serious error message is printed if this is not the case.
3. The procedure checks that at least one FIFO cost record exists for stockroom balances associated with items for which FIFO costing is specified. A warning message is printed if this is not the case.
4. The procedure checks that for FIFO costed items, the sum of the FIFO balance quantities is equal to the stockroom balance physical stock. A serious error message is printed if this is not the case.
5. The procedure checks the presence of FIFO records for items which are not FIFO costed. If any such records are found, a serious error message is printed.
6. The procedure checks that for lot controlled items the sum of the balance is equal to the stockroom balance physical stock. A serious error message is printed if this is not the case.
7. The procedure checks for the presence of lot records for items which are not defined as lot controlled. If any such records are found, a serious error message is printed.

Bottom-Up Validation

This function is processed as above, but in reverse and a similar report is produced.

Reconciling Demand

There are two options which can be used to reconcile demand.

- Allocation Reconciliation - which reconciles stockroom balance record allocation totals to Sales, Transfer and Production orders.
- On Order Reconciliation - which reconciles stockroom balance record on order totals to Purchase and Production orders.



Note: These should be run on a weekly basis initially, then run monthly, quarterly, and finally on an ad hoc basis.

Allocation Reconciliation

17/INU

- This procedure updates the Stockroom Balance File (INP60).

 Select Allocation Reconciliation.

IN916P	Z1 - UK Demonstration Company	User GBJBALTW	3/06/98 13:05:26
Allocation Reconciliation			
Company..... Z1			
Do you wish the Reconciled quantity Allocated to be updated? <u>0</u> (0=No,1=Yes)			
Press Enter to submit report.			
F3=Exit			

Fields:

Do You Wish The Reconciled Quantity Allocated To Be Updated?

Enter one of the following:

0 - To just report the differences.

1 - To use the application calculated allocated quantity to update the stockroom balance record where differences are found.

 Press **Enter** to confirm your selection and submit the job.

On Order Reconciliation



18/INU

- This procedure updates the Stockroom Balance Record (INP60).



Select On Order Reconciliation.

IN917P	Z1 - UK Demonstration Company	User GBJBALTW	3/06/98 13:05:54
On Order Reconciliation.			
Company..... Z1			
Do you wish the Reconciled quantity On Order to be updated? 0 (0=No,1=Yes)			
Press Enter to submit report.			
F3=Exit			

Fields:

Do You Wish The Reconciled Quantity On Order To Be Updated?

Enter one of the following:

0 - To just report on the differences.

1 - To use the application calculated order quantity to update the stockroom balance record where differences are found.



Press **Enter** to confirm your selection and submit the job.

Audit Negative FIFO



19/INU

If an issue is carried out before the appropriate receipt has been made this may result in a negative figure in the FIFO record. This option prints a list of any records that have been created with negative costs.



Select **F8=Confirm Submit** to process the batch job.

Recalculate Nominal Sec Values



20/INU

This option recalculates the nominal secondary stock levels for Non-Catchweight items that have a secondary value when transactions have occurred. It can be used to reset existing values, but is intended to create secondary stock levels for Non-Catchweight items that have just had a secondary value assigned to them.

If no transactions have occurred then the secondary values are zero.



Select **F8=Confirm Submit** to process the batch job.

```

IN903                                     User SP1                               21/09/94
                                           12:00:15

Company Deletion

      Sel Co  Company name
      1  Z1  Demonstration Company

1=Delete
F3=Exit  F12=Previous

```

Delete History And Movements



22/INU

Use this option to purge data from the Stock Movement and Stock History files. A record is deleted from the appropriate file when its week number is prior to the current week being processed, modified by the number of weeks entered as a parameter.



Warning: Take care to control history deletion, as the Stock History Records are used to determine average usage.



Select Delete History And Movements.

IN039	Z1 - UK Demonstration Company	User GBJBALTW	3/06/98 13:06:41
Remove Obsolete Movement And/Or History Details			
No. of weeks movements to retain.... 060 (999 - Retain all)			
No. of weeks history to retain..... 060 (999 - Retain all)			
F3=Exit			

Fields:

No Of Weeks Movement To Retain

Enter up to three numeric characters to specify the number of weeks of Stock Movements to be retained. The default is 60 weeks. Enter 999 to retain all movements.

No Of Weeks History To Retain

Enter up to three numeric characters to specify the number of weeks of Stock History records to be retained. The default is 60 weeks. Enter 999 to retain all history records.



Press **Enter** to confirm the input parameters, and submit the job to remove movement and history records.

Delete FIFO/Lot Details

1...
2...

23/INU

This procedure purges data from the FIFO Details file (INP83). You also have the option to purge details from the batch/lot file (INP80).

FIFO records with zero balances, and batch/lot records with zero balances and no stock movements are deleted.



Select Delete FIFO/Lot Details.

```

IN910          Z1 - UK Demonstration Company      USER GJBALTW      3/06/98
                                                    13:07:11
FIFO and lot

Cut-off Date..... 3/06/98

Only FIFO cost records up to and
including the cut-off date with a
zero balance will be deleted

Location.(0=no,1=yes)..... 0

Cut-off Date for location. 3/06/98

F3=Exit
  
```

Fields:

Cut-Off Date

Enter the cut-off date for the FIFO details deletion. Only records up to and including the cut-off dates are considered for deletion.

Location

Enter one of the following:

- 1 - To delete batch/lot details.
- 0 - To retain batch/lot details.

Cut-Off Date For Location

Enter the cut-off date for the batch/lot details deletion.



Press **Enter** to confirm the selection criteria and submit the job to remove FIFO details and batch/lot records.

Purge Stock Counts

24/INU

Use this option to purge completed counts by individual count or by a count range basis.

The count headers and their associated count recommendations are deleted with full auditing to system standards. In addition the associated count lists and their details are deleted.

You can choose to purge incomplete outstanding counts, so associated items are taken off count (for item based counts) and associated locations are taken off count (for location based counts).



Select Purge Stock Counts.

IN921	Z1 - UK Demonstration Company	User GBJBALTW	3/06/98 13:07:24
Purge stock count			
Stockroom.....?.. _			
Count number from.....?.. _____ to.....?.. _____			
Purge incomplete count..... 0 0=No 1=Yes			
F3=Exit F4=Prompt F8=Submit			

Fields:

Stockroom

Enter the stockroom for which at least one count has been requested.

Count Number From To

Enter a range of count numbers. If you define a range, then the From and To count numbers need not exist.

If the To count number is left blank, it defaults to the From count number.

Enter a single count number. If you select a single count number then it must exist, be complete (reconciled) and the purge incomplete counts field should be set to 0.



Tip: You must enter 1 in Purge Incomplete Counts if you want to purge incomplete counts.

Purge Incomplete Counts

Enter one of the following:

0 - Do not purge incomplete counts as well as reconciled counts.

1 - Purge incomplete outstanding counts as well as reconciled counts.

Purge Count Details/Action Lists



25/INU



Select Purge Count Details/Action Lists.

Use this option to purge completed count list details, by date.

The count lists and all associated details are deleted when their date of creation is less than or equal to the date entered.



Tip: The date entered defaults to the period end date for the current period minus two.

IN927	Z1 - UK Demonstration Company	User GBJBALTW	3/06/98 13:07:38
Count Details and Action List Purge			
Stockroom.....?.. —			
Purge upto..... <u>28/02/98</u>			
F3=Exit F4=Prompt F8=Submit			

Fields:

Stockroom

Enter the stockroom code for which purge has been requested.

Purge Date

Enter the date up to which you wish to delete completed details.

Item Deletion



26/INU

Use this option to delete from the database those items previously flagged for deletion in Item Master Maintenance, using a batch job.

If you want to delete a large number of items this option may take a considerable time to run. So you can split this process into two separate stages as follows:

1. Take the Build Item Deletion Logical Files option to create the necessary technical requirements to allow the system to process the item deletion.
2. Take this option (Item Deletion) to physically remove the items from the database.



Note: To perform the item deletion as a single task just use this option alone.



Note: The overall performances of the two methods are approximately the same.

Fields:

Delete Items From Database

Enter one of the following:

- 1 - To produce a report of items for deletion.
- 2 - To physically delete the items from the database and produce a report of the items deleted.

Effectivity End Date

Specify an effectivity end date for the deletion. All items flagged for deletion with an effectivity end date on or before the entered date are deleted.



*Note: To prevent deletion of an item/stockroom with any existing stock movement, you should set up the code IDMP in the Descriptions file under Major Type MISC. The IDMP **Rate** field should specify the number of periods back from the current period, during which time you do not wish deletions to occur. If you have not defined IDMP in the Descriptions file, all items flagged for deletion will be deleted during the Item Deletion Routine.*

Delete Shipment Receipts



27/INU

Use this option to delete all confirmed shipment reports from the database.



Note: This function requires exclusive use of the module.



Select **F8=Confirm Submit** to process the batch job.

Audit File Purge Maintenance



28/INU

Use this housekeeping option to select audit files you want to include in the purge routine to free unnecessarily occupied space on your system.

Audit File Purge Maintenance Selection Screen



Select Audit File Purge Maintenance.

Use this screen to select the application to purge.

```
IN527          Distribution V3 -> V3 Financials 3F User GBJBA1MS      5/12/96
                                           16:10:59

Audit File Purge Maintenance

Application.....?.. ? (Leave blank for all)

Select application
MORE:  +
Sel  Application  Description
- AC             AC Fix environment V3.0
- CN             Configurator fix
- CR             Customer returns V3 Fix
- DR             DRP Version 3 FIX
- FC             Forecasting V3 fix
- IN             Inventory V3 fix environ
- OE             Sales order processing V
- PM             Purchase Management V3 F
- TP             Transport Planning V3 FI
- WH             warehousing V3 fix

1=Select
F12=Previous

F3=Exit  F4=Prompt

10-35    SF    MW    KS    IM    II    EDN400A    PET149S1
```

Fields:

Application

You can select to submit audit files to the purge routine in two ways:

- Enter a specific Application Code to display only audit files corresponding with a required Application.
- Leave the Application field blank to display all audit files corresponding with all applications.



Press **Enter** to display the Audit File Purge Maintenance Details screen.

Audit File Purge Maintenance Details Screen



To display this screen select the Application you want to purge and press **Enter** on the Audit File Purge Maintenance Selection screen.

Use this screen to select the audit files you want to submit to the purge routine.

IN527 Distribution V3 -> V3 Financials 3F User GBJBA1MS 6/12/96 10:40:14				
Audit File Purge Maintenance				
Include(0/1)	File	Description	Purge Date	Number of Days
1	INP01A	Product transaction control au	6/12/96	___
0	INP35A	Item maintenance audit log	0/00/00	___
0	INP36A	Item attributed audit	0/00/00	___
1	INP37A	Item/customer profile	6/12/96	___
0	INP38A	Alternative item reference aud	0/00/00	___
0	INP45A	Alternative parts- Amendment 1	0/00/00	___
0	INP46A	Supersessions	0/00/00	___
0	INP47A	Multi-sourcing rule header aud	0/00/00	___
0	INP48A	Multi-sourcing rule details au	0/00/00	___
0	INP50A	Search family attributes audit	0/00/00	___
0	INP51A	Count profile audit	0/00/00	___
0	INP52A	ABC class profile audit	0/00/00	___
0	INP54A	Count details audit	0/00/00	___
0	INP58A	Count header audit	0/00/00	___ +

F3=Exit F8=Update F12=Previous

08-05 **SF** MW KS IM II EDN400A PET149S2

Fields:

Include 0/1

Enter one of the following:

0 - To exclude it in the next purge routine.

1 - To include an audit file in the next purge routine.

File

The audit file's number. The files are listed in numerical order.

Description

The audit file's description.

Purge Date

Displays the date, calculated by the system, before which audit records have been purged.

Number of days

Enter the number of days before a run date that you want to keep audit file records. You can enter a maximum of 999 days.



Select **F8=Update** to update any changes and update the appropriate records to Inventory. To run the purge routine, select Submit Audit File

Purge.

Submit Audit File Purge



29/INU



Select the audit files you want to include in the purge routine using the Audit File Purge Maintenance option.

Use this housekeeping option to start the audit file purge routine.



Select Submit Audit File Purge.

Use this screen to select the application you require.

```

IN529          Distribution V3 -> V3 Financials 3F User GBJBA1MS    6/12/96
                                           11:25:04

Audit File Purge

Application.....?.. __

F3=Exit  F4=Prompt  F8=Submit

05-22    SF      MW      KS      IM      II  EDN400A  PET149S2
  
```

Fields:

Application

You can submit the previously selected audit files to the purge routine in two ways:

- Enter an application code to submit corresponding audit files.
- Leave blank to submit all audit files selected in the Audit File Purge Maintenance option.

The system calculates the purge date for each submitted audit file by subtracting the number of days entered from the current system date. Any audit file records created on or before the calculated purge date will be purged.



Tip: Submitted audit files will remain selected with the 1 flag after the purge routine has completed. This allows you to keep a fixed number of days' records and to run the purge routine without using the Audit File Purge Maintenance option.



Select **F8=Submit**.

Use this housekeeping option to routinely purge audit files via Application Manager. This is useful if your system does not have a space problem, as you only need to access the Audit File Purge Maintenance option once.

[illegible]

Fields:

Application

You can submit the previously selected audit files to the purge routine in two ways:

- Select the required application codes to submit audit files corresponding with specific applications.
- Leave blank to submit all audit files selected in the Audit File Purge Maintenance option.

The system will purge the files selected in the Maintenance option, with the same number of days audit records preserved each time the routine is run.



Select **F8=Submit**.

Processing Profiles



1/INW

Use this option to provide profile information for the Inventory interface program. These profiles provide both user defined Inventory updates as well as standard updates dictated via other Distribution products.

Inventory Processing Profile Maintenance Screen

 Select Processing Profiles.

 To display this screen enter a profile code that defines an instruction set.

Use this screen to view existing sequences within the profile, showing movement type and description.

IN085	Z1 - Demonstration Company	User SP1	21/09/94 9:54:43
Inventory Processing Profile Maintenance			
Profile code..... 001		<u>Adjust Physical Stock</u>	
1	Sequence	Type	Description
<u>1</u>	1	A	Stock Adjustment
1=Select			
F3=Exit F8=Addition F11=Delete F12=Previous			

Fields:

Profile Code

The screen displays the profile code, you can enter or amend the description.

Select

Enter 1 to select the sequence you want to maintain.

Sequence

The sequence number allocated to use in the profile.

Type

The movement type that is to be generated for a given item.

Description

A description of the movement type.

 Select a sequence to maintain and display the second Inventory Processing Profile Maintenance screen.

Inventory Processing Profile Maintenance Screen 2



This screen displays when you select to maintain a profile/sequence on the first Inventory Processing Profile Maintenance screen.

Use this screen to maintain part of the profile code you have selected.

IN005	NR - Neil Radford and Co. Ltd	User GBJBA1MS	30/07/96 12:45:03
Inventory Processing Profile Maintenance			
Profile code.....	001	Adjust Physical Stock	
Sequence.....	1		
Movement type..?	1	Stock Adjustment	
Stockroom.....	1	(1=From,2=To)	
Sign of quantity..	±		
Cost value calc.?	-		
Update for balance fields:			
Physical.....?	1	On order.....?	0
Allocated.....?	0	On back order.?	0
Frozen.....?	0	Bonded.....?	0
In-transit.....?	0	Forward.....?	0
Reserved.....?	0		
Other stock balance updates: (0=No,1=Yes)			
Recalculate		Update costs.....	0
Update usage.....	0	Date of issue.....	0
available.....	1	Date of receipt....	0
Stock history:			
Update for history...?	3		
F3=Exit F4=Prompt F5=Refresh F8=Update F11=Delete F12=Previous			
06-21 SF MW KS IM II KENB20A PET166S2			

Fields:

Sequence

Define the sequence of Inventory updates within the profile.

Movement Type

The movement type that is to be generated for a given item.

Stockroom

Enter one of the following:

1 - For the From stockroom.

2 - Use the To stockroom when two stockrooms are affected by the instruction set in this profile.

Sign Of Quantity

This specifies the sign that the quantity would normally be expressed in on the movement record.

Cost Value Calc

Any entry made is validated against the Inventory Descriptions file, against type CVLR

Update For Balance Fields

This specifies which of the balance fields are to be updated as a result of this transaction:

- Physical.
- On order.
- Allocated.
- On back order.
- Frozen.
- Bonded.
- In-transit.
- Forward Reserved

Enter one of the following:

- 0 - Update not required.
- 1 - Add quantity actually moved.
- 2 - Subtract quantity actually moved.
- 3 - Add quantity planned to move.
- 4 - Subtract quantity planned to move.

Recalculate Available

Enter one of the following:

- 0 - Available stock is not to be recalculated.
- 1 - Available Stock to be recalculated.

Update Costs

Enter one of the following:

- 0 - Latest, Average and FIFO costs are not to be updated.
- 1 - Latest, Average and FIFO costs to be updated.

Update Usage

Enter one of the following:

- 0 - Usage figures are not to be updated.
- 1 - Usage figures to be updated.

Date Of Issue

Enter one of the following:

- 0 - Date of last issue is not to be updated.
- 1 - Date of last issue to be updated.

Date Of Receipt

Enter one of the following:

0 - Date of last receipt is not to be updated.

1 - Date of last receipt to be updated.

Update For History

Enter one of the following to specify the balance to be updated for stock history:

0 - Update not required.

1 - Receipt.

2 - Issue.

3 - Adjustment.

4 - Transfer out.

5 - Supplier orders.

6 - Transfer in.



Select **F8=Update** to save any entries you have made.

Test

1... **2/INW**
2...

Use this option to run test extracts.

Inventory Trial Extract and Update Screen



Select Test.

Use this option to take a trial extract of data from Inventory Management and create a General Ledger journal. Note that no actual updating of data takes place, either within Inventory Management or General Ledger. This is simply a simulation of the effect of creating the specified journals for the nominated company. You can generate three reports:

- General Ledger Postings - A list of the postings generated.
- Exceptions Report - Displaying, for example, any balancing postings automatically created for an unbalanced journal.
- Error Report - Displayed error conditions encountered.

```
FIS10                      Advanced Financial Integrator  User GBJBA1MS  30/07/96
                             Prompt for Inventory Trial Extract and Update  13:04:05

Source company . . . . . ? 01
EITHER: work with inventory movements not yet processed 1 (1/0)

OR      : work with inventory movements from . ? _____ to _____

Type of Journal definition to use: 1  1=Under Test
                                   2=LIVE
                                   3=Both

Consolidate postings? . . . . . 0 (1/0)

-----
F3=Exit  F4=Prompt  F8=Proceed  F12=Previous

07-39    SF      MW      KS      IM      II  KENB20A  PET166S2
```

Fields:

Source Company

Enter the source company whose data you wish to use for this trial extraction.

Work With Inventory Movements Not Yet Processed

Enter one of the following:

- 0 - To specify a range of transaction numbers on which you wish to base the trial.
- 1 - To use data that has not been extracted in live operation mode by AFI.

Work With Inventory Movements From And To

This is only relevant if the previous response was 0. Specify here the range of transaction dates in the source application you want to use in this trial. If you wish to use only the inventory movements that occurred on a single day, specify the same date in the From and To entries.

Transactions within the source application that can be used for this trial are displayed in a pop up window.

Type Of Journal Definition To Use

Enter one of the following:

- 1 - Use journal definitions that are specified as being under test.
- 2 - Use journal definitions that are specified as being live.
- 3 - Use both test and live journal definitions.

Consolidate Postings

Enter one of the following:

- 0 - For no consolidation to take place, even though you may have postings defined as consolidatable.
- 1 - For consolidation to take place on those postings defined as consolidatable.



Press **Enter** to validate the selection screen,
then **F8=Proceed**.

Live



3/INW



Select Live.

Use this option to initiate the extract of Inventory transactions from the Inventory movements file, for processing by AFI to create General Ledger journals.

INW	NR - Neil Radford and Co. Ltd	User GBJBA1MS	30/07/96 13:04:29
Inventory Processing Profile/AFI			
Processing Definition			
1. Processing profiles			
AFI Stock Move			
2. Test			
3. Live			
4. Install In			
Advanced Financial Integrator Inventory to General Ledger update Please nominate the company from which you wish to extract data to update the General Ledger: <u>Z1</u> Demonstration Company F4=Prompt F8=Proceed F12=Previous			
90. Signoff			
Option <u>3</u>			
Search _____			
F3=Exit F4=Prompt F6=Messages F12=Previous F16=Change company F18=Prints 14-20 SF MW KS IM II KENB20A PET166S2			

Fields:

Company

Specify the company code of the company for which you want Inventory transactions extracted.

Transactions are extracted according to the selection criteria set up on your journal condition.



Press **F8=Proceed** to continue with the extraction.

Install Inventory/AFI Link

1... **2...** 4/INW

Where AFI is linked to the Inventory Management application Inventory movements are extracted when the operator selects Install Inventory/AFI Link. Transactions are created in AFI for the Inventory movement types as defined on the journal conditions set up for the Inventory application. When the operator takes the AFI to General Ledger Update option, these are posted to the General Ledger as journals.

There is no facility to automatically extract transactions and post to the General Ledger without operator intervention within the Inventory application, unlike Sales Invoicing. It is more appropriate to control the extract of Inventory movement transactions on a manual basis, because of the wide range of Inventory movement types, and the likely number of transactions.

If AFI is not linked to the Inventory Management application (AFI is set to inactive), purchase receipts made within Purchase Management update General Ledger stock accounts when supplier invoices are matched to goods received notes and the logged invoices are confirmed in the Accounts Payable application.



Note: When you receive goods into Inventory AFI automatically posts details to the General Ledger Goods Purchased Account.

As well as the AFI link status being set to active, there must also be one or more live journals. The facility to set up a journal as live is part of the Journal Conditions Maintenance facility.



Note: You must set the Journal Condition field to test for a valid value when you want to read date from the source application. For example, you must set up the Journal Condition field to test for a specific Inventory movement type or range of types.

Data Dictionary

The following files, and their associated fields, are available for defining how selection and consolidation or both is to take place.

Item Master

- Company Number.
- Item Code.
- Item Type .
- Item Class.
- Division.
- Sub-Division .
- Item Group Major.
- Item Group Minor.
- VAT Code.
- Discount Group.
- Stock Source.
- General Ledger Stock Account.
- General Ledger Cost of Sales Account.
- General Ledger Sales Account.
- General Ledger Price Variance Account.
- Warranty Type.
- Storage Method.
- Costing Method.
- Sub-Contracted Item.
- Resource Code.

Inventory Movement

- Company Number.
- Item Code.
- Stockroom Code.
- Transaction Type.
- Reference Number.
- Movement Type.
- Movement Reason Code.
- Movement Source.

- To/From.

Stock Balance

- Item Type.
- Item Class.
- ABC Override.
- ABC Class.

Stockroom

- Stockroom Usage Code.
- Department Code.

The following fields are defined as quantities which are available to post, (refer to Quantity field to post within posting definitions).

Daily Movements

- Movement Quantity (Movement UOM).
- Movement Quantity (Item Master Issue UOM).

The following fields are available on the Inventory Movement file for posting as a value to the General Ledger.

- Total Movement cost (Good Cost plus Landed Cost).
- Secondary Cost (Landed Cost).
- Net Cost (Good Cost).

Below are the different Inventory Movement Types that the file may contain together with their normal sign (+ or -).

Adjustments follow the sign of the transaction, that is, a positive adjustment has a positive sign.

Description	Inventory Movement Type	Sign
Customer Order Issue	C	-
Sundry Issue	S	-
Purchase Order Receipt	P	+
Sundry Receipt	R	+
Adjust Physical Stock	A	+/-
Adjust Allocated Stock	L	+/-
Adjust Frozen Stock	F	+/-
Transfer Out	O	-

Description	Inventory Movement Type	Sign
Transfer In	I	+
Purchase Order	U	+
Production Issue	M	-
Production Receipt	N	+
Production Adjustment	W	+/-
Adjust In-Transit	T	+ (Transfer Out) - (Transfer In)
Direct Delivery	D	-
Frozen Transfer Out	G	-
Frozen Transfer In	H	+
Transformation	J	+/-
Frozen Issue	K	-
Back-to-back	Q	+

Activating The Link

JBA recommend that you set Journal Conditions to test, and use the AFI Test option to prove them before you activate AFI and set Journal Conditions to Live.

Inventory movements are not posted to the General Ledger until AFI is activated. When AFI is active, posting to the General Ledger are made each time Inventory movements are extracted.

You must take the following steps to activate AFI:

1. AFI Maintenance menu. Use the Maintain Journal Condition option to change the status of your journal conditions from inactive (0) or under test (1) to a status of live (2). You do not need to do this for all journal conditions - only those which you are ready to activate.
2. AFI Utilities menu. Use the Maintain Application option to change the status of the AFI link from inactive to active using **F8**. At the same time check the validity of your consolidation settings on this display.

AFI is now used to process Inventory movements to create General Ledger journals, according to your rules and definitions, from the point when you next create movements within the Inventory Management application and extract them.

Library List

A separate task level library list has been created within AFI to include all the Inventory files necessary to undertake a data extract of Inventory movements from the Inventory Management application into AFI.

Besides containing the necessary Inventory libraries, this includes the following AFI libraries:

OSLFIF3	AFI Data files
OSLFID3	AFI Printer and Display files
OSLFIP3	AFI Programs

Inventory Management also contains a task level library list for the stock movements audit report that includes the necessary Inventory and AFI libraries. A check is made to ensure that Inventory movements have been processed by AFI before these are cleared from the daily stock movements file (where clearance of data has been requested).