

-
-
-
-
-

Chapter 5

Utilities



Sub System Introduction



The Order Bank update activity is compatible with Work Management and can be run as part of a Business Process in System 21 Constructor and System 21 Explorer.

To maximise the speed in which orders are accepted via Telesales, and control the automatic scheduling of calls, certain functions run in a separate sub-system. These functions are known as 'sleepers' and are activated when required. The function of the sub-system is as follows:

- To update the standard order bank. When a call is closed, this 'sleeper' is activated and the order is written to the standard order bank. Once accepted these orders may be treated as an order in the Sales Order Processing base module.
- To activate the automatic call scheduler. Every 5 minutes this 'sleeper' reviews the call lists to decide whether or not calls have expired by time and whether they can be scheduled out to a later time.

Company Profile



1/TSU

You can operate Telesales for a number of companies, you maintain the characteristics of each company on a control file.

Before you can set up a Telesales company, you must install and configure Sales Order Processing and Inventory Management for the company. You can then maintain the control information.

Company Profile Company Selection Screen



Select Company Profile Maintenance to display the Company Profile Company Selection Screen.

Use this screen to select the company you want to maintain.

```

TS000                Company Profile Maintenance                USER SP1                9/09/94
                                                                10:24:37
    Company
    Code    Company Name
  1  Z1      Demonstration Company

1=Select Company
F3=Exit

```

Company Profile Maintain Controls Screen 1



To display this screen, on the Company Profile Company Selection Screen, select a company with option 1.

Use this screen to create and maintain the standard policy controls.

TS000	Z1 Demonstration Company	User: SP1	9/09/94 10:24:41
Company Profile - Maintain			
Default telesales type.....	<u>1</u>	1=Telesales, 2=Planned delivery, 3=Telemarketing	
Maintain performance statistics...	<u>1</u>	0=No, 1=Yes	
Message queue for break messages..	<u>QUSER</u>	Library..	<u>*LIBL</u>
Standard working day.....	<u>7.0</u>	(hours)	
Standard call duration.....	<u>5</u>	(mins)	
Standard rest period per hour....	<u>5</u>	(mins)	
Default buying list code.....?	<u> </u>		
No. of weeks per month.....	<u>4.0</u>	(3-5 for recommended stock calc)	
Pricing option.....	<u>2</u>	0=No pricing 1=Overnight 2=Interactive 3=Order create	
Stock checking/allocation.....	<u>2</u>	0=No stockcheck, place Backorder 1=Stockcheck place Backorder 2=Stockcheck/Allocate OR place Backorder	
F3=Exit F4=Prompt F5=Refresh F8=Update F15=Presentation design F16=Next call logic			

Fields:

Default Telesales Type

Enter the default type of order to use for call profiles and incoming calls with no call profile. Enter one of the following:

- 1 - Telesales. This is a prearranged call to a customer to discuss a predefined list of items and to take an expected order.
- 2 - Planned Delivery. The customer gives the current stock level of an item and Telesales suggests the order size required to cover the period until the next order.
- 3 - Telemarketing. The operator can view the available buying lists and selects the most appropriate list to discuss with the customer.

Maintain Performance Statistics

Enter one of the following:

- 0 - No. If you do not want to record the call time statistics.
- 1 - Yes. To record the time taken by the operator to make each phase of the call cycle.

Message Queue For Break Messages

Enter the name of the print queue to direct break messages to. For more information about queues, see the Machine Manager product information.

Library

Enter the library of the print queue.

Standard Working Day

Enter number of hours, between 0.0 and 24.0, worked by telesales operators to use as a default. This is optional and intended for use in work planning.

Standard Call Duration

Enter the length of a customer call, in minutes in the range 0 to 999, to use as a default. This is optional and intended for use in work planning.

Standard Rest Period Per Hour

Enter the standard rest period in minutes, in the range 0 to 15, to use as a default. This is optional and intended for use in work planning.

Default Buying List Code

Enter the buying list used to generate the base order details for incoming calls with no profile, or no buying list defined on the call profile or no buying list defined when you generate call lists.

Number Of Weeks Per Month

Enter the number used to convert period sales data to week sales data for the planned delivery calculations.

Pricing Option

Enter one of the following to determine at what level pricing is carried out:

- 0 - No pricing. There is no pricing carried out at all
- 1 - Overnight. The pricing is calculated overnight.
- 2 - Interactive. The pricing is carried out as you enter items.
- 3 - Order Create. The pricing is carried out when you create the order.

Stock Checking / Allocation

Enter one of the following:

- 0 - No stock check. Place stock on back order.
- 1 - Stock check. Place stock on back order.
- 2 - Stock check. Allocate stock if available, or place on back order as appropriate.

Functions:

F15

Presentation design. Use this function to display the Order Presentation Maintain Screen.

F16

Next Call Logic. Use this function to display the Maintain Next Call Logic Screen.



Press **Enter** to check the information and display the Company Profile Maintain Controls Screen 2.

Company Profile Maintain Controls Screen 2



To display this screen, press **Enter**, to check the information on the Company Profile Maintain Control Screen 1.

Use this screen to specify the standard policy controls of the company.



Tip: You must enter the contact type, text types and description IDs before you select **F8=Update**.



Note: Once you have entered and saved these controls, you cannot change them.

TS000 Z1 Demonstration Company		User: SP1	9/09/94 10:24:56
Company Profile - Maintain			
Contact type..... T/S			
Text type..... T/S			
Text Sub-types			
Operators..... OPS	Contacts..... CTC	Call profiles.. CPF	
Delivery profiles. DPF	Buying lists..... BLC	Promotions..... PRO	
Description Ids			
Promotions..... TSPR	Delivery routes.. TSDR		
Short Month Names			
January.... Jan	February... Feb	March..... Mar	April..... Apr
May..... May	June..... Jun	July..... Jul	August..... Aug
September.. Sep	October.... Oct	November... Nov	December... Dec
Short Day Names			
Monday..... MON	Tuesday.... TUE	Wednesday.. WED	Thursday... THU
Friday..... FRI	Saturday... SAT	Sunday..... SUN	
F3=Exit F5=Refresh F8=Update F15=Presentation design F16=Next call logic			

Fields:

Contact Type

Enter the type of contact used by Telesales.

Text Type

Enter the type of text maintained by Telesales.

Text Sub-Types

Enter a code to classify the text used by Telesales.

Description Id's

Enter the keys used in the description file for allowed promotions and delivery routes.

Short Names

Enter three character short names for the months and days of the week.

Functions:

F15

Presentation design. Use this function to display the Order Presentation Maintain Screen.

F16

Next Call Logic. Use this function to display the Maintain Next Call Logic Screen.



Select **F8=Update**, to check and save any changes. The initial menu is then redisplayed.

Order Presentation Maintain Screen



To display this screen, on either of the Company Profile Maintain Controls Screens, select **F15=Presentation Design**.

Use this screen to tune the format of the Order Line Entry screen to simplify the operator's task. You can change the format of item numbers and descriptions, edit order quantities and change the display of previous order history.

TS080 Demonstration Company		User: SP1	9/09/94
Order Presentation - Maintain			10:25:03
Item style Details:			
Header.....	Item Description		
Item pos from.....	1 to 4		
Separator.....	-		
Desc pos from.....	1 to 25		
Order quantity details:			
Heading.....	QTY	Telesales/Telemarketing	
Heading.....	Quantity	Planned delivery	
Format.....	1	0=8(0), 1=6(1), 2=6(2), 3=6(3)	
Previous Order Detail:			
Date format.....	1	1=dd/mm/yy, 2=ddmm yy, 3=mmm ddy	
Which qty.....	1	1=Order, 2=Delivered	
No.of orders.....	13	0-13	
By date/week.....	1	1=Date, 2=Week	
F5=Refresh F8=Update F12=Previous			

Fields:

Item Style Header

Enter the heading to display over the list of items.

Item Pos From/To

Enter the elements of the item code to display, in the form nn, where nn is a number between 1 and 15.

Separator

Enter the character to print between the item code and item description.

Desc Pos From/To

Enter the elements of the item description code to display, in the form nn.



Note: The combined length of the item and description masks cannot exceed 30 characters.

Quantity Heading

Enter the heading to display over the order quantity field (Telesales, Telemarketing).

Quantity Heading

Enter the heading to display over the customer stock quantity (Planned Delivery).

Quantity Format

Enter one to specify the number of decimal places allowed on the entry field:

- 0 - 8(0). Eight digits with no decimal places.
- 1 - 6(1). Six digits with one decimal place.
- 2 - 6(2). Six digits with two decimal places.
- 3 - 6(3). Six digits with three decimal places.

Previous Orders Date Format

Enter one of the following to specify the format of the date of previous orders:

- 1 - dd/mm/yy.
- 2 - ddmmm yy.
- 3 - mmm ddy.

Which Qty

Enter one of the following to specify how the order history is displayed:

- 1 - Order Quantity. To display the order quantity.
- 2 - Delivered Quantity. To display the delivered quantity.

Number Of Orders

Enter the number of orders or weeks' history to display when entering orders.

By Date / Week

Enter one of the following:

- 1 - Date. To display the previous orders by Date.
- 2 - Week. To display the previous orders by Week



Select **F8** to validate and save the changes.

Maintain Next Call Logic Screen



To display this screen, select **F16=Next Call Logic** on either of the Company Profile Maintain Controls Screens.

Use this screen to control the sequence in which calls are considered.

TS081	Demonstration Company	User: SP1	9/09/94 10:25:34
Maintain Next Call Logic			
Enter below the order in which the call list should be viewed in order to select the next logical call.			
The order is defined by entering 'A' against the 1st view, 'B' against the 2nd view and so on.			
Times	<-----	Dates	----->
	Past	Today	Future
Earlier....	<u>D</u>	<u>B</u>	<u>G</u>
Current....	<u>E</u>	<u>A</u>	<u>H</u>
Later.....	<u>F</u>	<u>C</u>	<u>I</u>
Untimed....	<u>J</u>	<u>K</u>	<u>L</u>
F5=Refresh F8=Update F12=Previous			

Fields:

You use the displayed table to categorise calls by day and time.

To establish the call sequence enter a letter from A to L. Identify the first call displayed on the list with A and the last call to display on the list as L.



Note: You can only enter characters A to L and you must complete all positions in the table.



To validate and save the changes select **F8=Update**.

Start Background Tasks

For orders which are to be placed in the standard order bank, the sub-system must be active.

To start the sub-system enter the following system command in the Option field:

STRSBS OSLTSP3/TSBACK3

Then press **Enter**. Once the sub-system is active, the Telesales background tasks may be started by selecting Start Background Tasks.

If the background tasks are already running when you attempt to start them, a window will display showing the date and time at which the background tasks were started together with the user ID of the person who started them.

End Background Tasks

To end the background tasks select End Background Tasks.

If the background tasks are not running when you take this option, a window will display informing you of this.

To end the sub-system in which the background tasks run, enter the following system command in the Option field:

ENDSBS TSBACK3