

-
-
-
-
-

Chapter 1

Company Maintenance



Company Maintenance



1/ASCO

For every company which exists on your system, you must create a company profile which holds the rules governing the operation of General Ledger.

This section describes how you create and maintain a company profile in the General Ledger. The maintenance of company profiles is performed using the same procedure and screens as those used in creating a company.

Hierarchy of Companies

If you are creating a hierarchy of companies, where several subsidiaries are reporting to a parent company, you must create a profile for the parent company first.

Exclusive Option

Control routines prevent the profile from being maintained when anyone else is using the module.



Warning: You should avoid changing existing company profiles once the module is in use, as this may corrupt your data. Changes should only be made under strict control.

New Company Profile

To set up a company within General Ledger you should take four basic steps:

- Maintain the first and second GL company profile screens.
- Set up ledgers, account level codes and report level codes from the GL Chart of Accounts Maintenance options.
- If Cash Management is installed, the GL account to be used as the default bank account must be defined as a bank account in Cash Management. This can only be done after the Cash Management company profile has been created. You may select available bank accounts when creating the Cash Management company profile. The bank name and address record must be created first.
- Re-enter the company profile to maintain the third screen.

Maintain General Ledger Company Profile Screen 1

 Select the General Ledger Company Profile option, enter the code of the company you wish to set up or maintain, and press **Enter**.

Create and maintain the first screen of settings for your company.

GL180		USER LOAN	21/11/96 13:41:54
Maintain General Ledger Company Profile			
Company	Z1	GB Demonstration Company	
Country	GB		
Periods per year	12	Current period	9602
Fiscal year-end	12	Alternative year-end	12
Use year-end journals?	0 (0/1)	Number of adjustment periods. 2	
Multi-currency?	1 (0/1)		
Exchange rate code	PERD	Currency	GBP
Maintain prime period balances? 1 (0/1)		Historical translation data . 1	
Prime period balance default ? 1 (0/1)		Translation method	1 (0/1)
Default forecast code	FBD	Default budget code	CBD
Quantity budget decimals . . . 1 (0/1)		Memo values to balance? . . . 1 (0/1)	
Use level codes?	1 (0/1)	Level code delimiter	/
Use account code extensions? . 1 (0/1)		Use level code security . . . 1 (0/1)	
Allow account sequencing? . . . 1 (0/1)			
Visualise structures ledger . ? VIS		Visualise account prefix . . . VIS	
F3=Exit F4=Prompt F12=Previous			
07-34	SP	MM	KS IM II EDN400A PET165S2

Fields:

Company

The first time a company is set up, enter a two character (alphanumeric) code to identify the company.

Once set up, the screen displays the company profile details and the company code may not be changed.

Country

Enter the code of the country - usually the country in which the company is situated.

Specific functions and menu options will be conditioned accordingly. The selection of a country code for a company will set various fields on and off throughout the system.

For example, if you select I or F as a country code, year end journals will be 'switched on' as the year end journal function is compulsory within Italy and France.

Periods Per Year

Enter the number of accounting periods in the year - up to a maximum of 99.

Current Period

Enter the current accounting period in the format YYPP. Once set up, it is then maintained by the Period Close routine.



Tip: Enter your opening balances into the current period. This would usually be one period prior to the first live period.

Fiscal Year-End

This is the period of the year end. Entry into this field is mandatory and must not be greater than the number of periods in the year.

Alternative Year-End

This gives the period number of the alternative year, if required.



Tip: It may apply, for example, where the company year-end is different from that of its parent company, thus necessitating the production of two sets of year-end accounts.

Leave blank if there is no alternative year-end and it will be set to equal the fiscal year-end.

Use Year-End Journals?

0 - Do not use year end journals for this company. This means, at year end, the P&L accounts will be totalled and zeroed, and the resulting total will be totalled and posted to the opening balance (retained profit) account.



Note: The year end period close option Year-Close Journal is the effective option used at your financial year end.

1 - Use year end journals. At year end, all balances in the balance sheet will be cleared down into one account, effectively totalling the balance sheet. At year open, these balances will be spread back into their previous accounts.

Year Close Journal

The year close (or end) journal passes through three stages before a year open journal takes over and opens up the new fiscal year:

- Profit and loss summary account.
- Profit account or loss account determined by positive or negative value.
- Summary closing account within the balance sheet, effectively zeroing each account.

The year close journal will post into the last adjustment period defined on the company profile. In this case the alternative year end must be the same as the fiscal year end. The number of adjustment periods must be at least 1.

Number Of Adjustment Periods

Enter the number of periods you want to make adjustment for, for this company at year end. You can enter from 0 to 9 (where 0 is for adjustment periods not being used).

Multi-Currency?

0 - Transactions can only be posted and held in base currency.

1 - Transactions may be posted in any valid currency.



You cannot change this setting once you have started using the General Ledger.



Note: You may operate General Ledger in single currency, and Accounts Payable and Accounts Receivable in multi-currency.

Exchange Rate Code

Enter an exchange rate code of up to 4 characters in length.

For a single currency ledger, a rate code may still be required for translation / consolidation purposes. Enter the rate code normally used for this purpose.

If the code has not previously been created, a window displays enabling you to set it up.

Currency

Displays the default currency code for the company profile country code.

You may select a different base currency.

No currency. A window displays with the option to Press **F10=Add** to add a currency from this screen.

Maintain Prime Period Balances?

0 - Balances for accounts to be held only as base values.

1 - Hold prime balances for accounts as well as base values.

Historical Translation Details

This indicator controls the way in which data items from a source company are translated or consolidated to a target company.

0 - The translation method (set up on this screen) is used to determine how balances are transferred. This is the most commonly used setting.

1 - Each transaction posted into the general ledger is translated into the currency of the target company. This translated value is held until a consolidation run takes place at which point they are transferred to the target company.



Note: The effect of this flag is not altered by the default translation method (set up on this screen). It is only effective when the Translation Method field is set to 1.



Warning: You cannot change this setting once you have started using your General Ledger.

Prime Period Balance Default

Enter the default value for maintaining prime balances when creating new sub-ledgers and accounts.

Translation Method

This field defines the default by which period base values are translated into a different currency.

0 - Translate cumulative values as at the end-of-period rate for the translation period.

1 - Depends on historical translation details for this company:

If maintained (set to 1), actual values are being transferred in the target currency.

If not being maintained (set to 0), posted values are translated at the mid-period rate.

Default Forecast Code

Enter the default forecast code of up to three characters in length.

You can create several forecast codes for an account. In maintenance, enquiry and reporting procedures, this default code is used when forecasts are called for.

Default Budget Code

Enter the default budget code of up to three characters in length. You can create several budget codes for an account. In maintenance, enquiry and reporting procedures, this default code is used when budgets are called for.

Quantity Budget Decimals

0 - Restrict budget quantities to whole numbers.

1 - Allow use of 2 decimal places in budget quantities.

Memo Values To Balance

0 - Postings made to memorandum accounts do not have to balance.

1 - Postings made to memorandum accounts must balance. If the system finds an unbalanced posting, a balancing entry will be made to the memorandum rounding errors account.

Use Level Codes?

0 - Build the chart of accounts by complete code. Level codes will not be validated in account maintenance and are not available for reports or for selection in the Financial Manager module.

1 - Build your chart of accounts from level codes. This would be the normal choice.



Warning: Not using level codes could severely restrict the analysis capabilities of your General Ledger.

Level Code Delimiter

Enter a suitable delimiter character which will be displayed on the screen to split account levels, so that divisions in the account structure are easy to identify.

Use Account Code Extensions?

0 - Extension codes are not required as part of your company's chart of accounts structure.

1 - Include extension codes as part of the chart of accounts structure.

Use Level Code Security

0 - Disable level code and other security features.

1 - Enable level code and other security features. A new field will appear in the Ledgers option, allowing you to secure account levels.

The setting of 1 also enables you to use the utility security facilities option and so lock certain users out of certain accounts.

The following options can use this facility:

- Transaction Detail Report.
- Account Enquiry.
- Account Balance Enquiry.
- Ledger Enquiry.
- Transaction Search.
- Account Search Window.
- Summary Transaction Report.
- Hierarchy Enquiry.
- User Defined Views Enquiry.
- Print User Defined Views.



Note: See also the section entitled Level Code Security - Options.

Allow Account Sequencing?

0 - Account sequencing will not appear as a method of semi-automatic account creation within chart of accounts maintenance.

1 - Make use of account sequencing, which allows you to create each account in level sequence without having to input accounts one at a time.

This facility may be switched on, initially while creating account codes en masse, and switched off later, if it is not be needed for ongoing maintenance.

Visualise Structures Ledger

The product Visualise operates by creating hierarchy accounts within the General Ledger. These hierarchy accounts are all held within the sub-ledger defined here.

Visualise Acct Prefix

Enter a value, to be used as a prefix, to identify your Visualise hierarchy accounts.

Functions:

F10

Add. If the currency entered has not been created, a window displays with the option to add a currency. See Add A Currency Window for further details.

The **F10=Add** option is also available when you enter a new exchange rate code. You are prompted to select a currency rate code. See Exchange Rate Window for further details.



Press **Enter** to move to the next screen. Or, where appropriate you are prompted to select a new currency or exchange rate. See Add A

Currency Rate Code Window (**F10=Add**) for
further details.

Add A Currency Rate Code Window (F10=Add)



To enter a new exchange rate press **F10=Add** at the Select Currency Rate Code Window. A window displays for you to enter the new currency rate code details.

```

GL180                                USER GBJBA1MS    25/11/97
                                         9:01:41

Maintain General Ledger Company Profile

Company . . . . . : MB  PRODUCTION BASE COMPANY
Country . . . . . : GB
Periods per year . . . . . : 12      Current period . . . . . : 1197
Fiscal year-end . . . . . : 12      Alternative year-end . . . . . :
Use year-end journals? . . . . . : Q (0/1)  Number of adjustment periods : Q

Multi-currency      Select Currency Rate Code
Exchange rate      More:      ? GBP
Maintain prime
Prime period b

Default foreca
Quantity budget
Use level code
Use account co
Allow account
Visualise stru

Rate Code.....
Description.....
Effectivity Type, _ (P/D)
F8=Update  F12=Previous.
. Q (0/1)

1=Select
F10=Add  F12=Previous

F3=Exit      F4=Prompt      F12=Previous

14-41  SA  MW  KS  CL  IM  DM  II  STUD140  KB  PKH31251
  
```

Fields:

Rate Code (Display Only)

This is the four character rate code - as entered or selected. It cannot be changed. You can use any meaningful set of characters to define this set of rates.

Description

Enter a description for the rate code of up to 35 characters in length.

Effectivity Type

Enter a D for a calendar date, or a P for an accounting period.

Effectivity dates are entered when you set up the exchange rates.



Note: Exchange Rates are set up at the GL Currency Rates Maintenance option.



Having created the exchange rate code, press **F8=Update** to accept. Select the country to which it will apply from the window provided.

Add A Currency Window (F10)

If you have entered a currency which does not yet exist, a window displays with the option to add a currency.

- ➡ Select **F10=Add** at the Select a Currency Rate Code Window to display this window.
- ➡ Or, display it from the Add a Currency Rate Window by pressing **Enter=Add**.

GL100		USER FFV9	21/06/95
			9:40:30
Maintain General Ledger Company Profile			
Company code.....	V9	New Business Company - V9	
Number of periods per year.....	12	Current period.....	9506
Fiscal year-end.....	12	Alternative year-end.....	03
Multi-curr			01
Exchange r			01
Maintain p			(0/1)
Historical			BP
Level code			(0/1)
Account co			
Allow acco			
Country co			
Year-end journals?			
Number of adjustme			

Add a Currency

Currency Code.....: GBP

Description.....: Pounds Sterling

Short Description...: Pounds

Smallest Unit.....: .01

Movement Tolerance...: .00

F8=Update F12=Previous.

Description.....: Default Rate Code

Effectivity Type. P (P/D)

F8=Update F12=Previous.

F3=Exit F4=Prompt F12=Previous

13-37 SP MW KS IM II EDN400A PCET02S3

Fields:

Description

Enter a description for the new currency of up to 35 characters in length.

Short Description

Enter a short description for the currency, of up to 10 characters in length. The description will appear in the majority of screens and reports.

Smallest Unit

Enter a value for the smallest unit of the specified currency.

Example. In the US, the smallest unit of specified currency is 1 cent and this would be specified as 0.01.

Example. In Japan, the smallest unit of specified currency is 1 yen and this would be specified as 1.00.

Movement Tolerance %

If this currency is your base currency, a percentage of 0.00 would be entered, as exchange rate fluctuations would not be expected.

Otherwise, enter the percentage of variation you are prepared to accept in the exchange rate fluctuation between currencies.

Some currency exchange rates fluctuate wildly whereas others vary within a much smaller band. The movement % field allows you to specify a single plus or minus percentage for the exchange rate variation. Movements outside this range will cause a warning to be issued when exchange rate information is entered.

 Once all details have been accepted, press **F8=Update** and **Enter** to go to the second Company Profile screen.

Maintain General Ledger Company Profile Screen 2

This screen allows you to set up global level codes to be used across the ledgers of this company. Once a global level - or reserve level - is maintained, it will effectively lock that level for every ledger within the company's chart of accounts and may not be updated.

The global codes are not mandatory and can be avoided in the following two ways:

- By switching off the extension codes flag for the specific ledger. (Use Account Code Extensions?, GL Company Profile, Screen 1.)
- By leaving the Req'd field set against the global codes blank. (Selected at Ledgers Account Maintenance.)

Global level codes may only apply to level codes 5 to 9 of a ledger structure and must be entered sequentially: level 6 may not be used as a global level unless level 5 has been specified.

By default, global levels are also set up as cross level codes.

Steps To Be Taken For New Company

Complete your Company Profile up to Screen 2 and exit the company profile. The following is a guide to the necessary steps then to be taken:

1. Select the General Ledger Chart Of Accounts option to maintain Ledgers. Set up the codes you intend to use for the balance sheet and profit and loss ledgers.
2. Having set up both ledgers, take the GL Chart Of Accounts option to maintain Account Level Codes. Set up account level codes for each ledger, corresponding to that ledger's structural requirements.
3. Select Maintain Report Level Codes. Enter the report level codes onto the account codes at creation time. You will save time and effort revising your chart of accounts later.
4. The accounts required for company maintenance should themselves be created by combining level codes to form the accounts.
5. If Cash Management is installed, the GL posting code to be used as the default bank account must be defined as a bank account in Cash Management. You may only do this after the Cash Management company profile has been created; you can select available bank accounts when creating the Cash Management company profile.
The bank name and address record must be created first. Once the account has been designated as a bank account it is post inhibited to journals.
6. You can now return to the General Ledger option (/ASCO) to enter your accounts on Screen 3.

Maintain General Ledger Company Profile Screen (Global Levels)



To display the second company profile screen
press **Enter** at the first company profile screen.

GL180	USER LOAN	21/11/96 15:50:01
Maintain General Ledger Company Profile		
Company : Z2 US Demonstration Company		
Use as global levels?	Length	Description
Level 5		
Level 6		
Level 7		
Level 8		
Level 9		
Ad hoc creation of level codes? <u>1</u> (0/1)		
F3=Exit		
F12=Previous		
14-34	SA	MA KS IM II EDN400A PET16SS2

Fields:

Length

Enter the length of the reserve level code. (This is also known as a global level code). As with any extension level code, the length can be from 1 to 15 characters.

Description

Enter a description for the reserve level (global level) of up to 15 characters in length.

You can overwrite the description for specific ledgers which make use of this level code.

Ad Hoc Creation Of Level Codes?

0 - To prohibit the ad hoc creation of level codes. They can only be specified via account codes maintenance.

1 - To allow the ad hoc creation of level codes. You will be able to create level codes for accounts when posting transactions, as well as when you maintain accounts through the normal procedures.



Note: The entry of several key accounts is required by company maintenance. If you have not created your account codes see the section entitled Steps To Be Taken For New Company.



Warning: If you are setting up a new company, you must now exit the company maintenance option.



Press **F8=Update** to accept the details entered.
If you are maintaining an existing company, you can now go on to Screen 3.

Maintain General Ledger Company Profile Screen 3

If you are setting up a new company, you must ensure you have already set up your high-level ledgers and accounts in your chart of accounts before attempting to complete this screen.



Note: The first time the company profile is set up, the fields on the third screen may be left blank until the GL accounts are created. Thereafter, the GL account fields must be completed before leaving the screen.



To display the third company profile screen press **Enter** at the second company profile screen.

GL180	USER GBJBA1MS	28/08/97 14:27:19
Maintain General Ledger Company Profile		
Company : Z1 GB Demonstration Company		
Accounts		
Default payments ?	312100	
Net profit ?	100000	Inter-co accounting . ? 1 (0/1)
Rounding errors ?	899010	VAT periods per year . . 04
Rounding errors (memo) . . . ?		C&E exchange rate code ? CUBC
Future suspense ?	106000	
Prior suspense ?	129000	
Contras suspense ?	899020	Statutory a/c length . . _
Profit account ?	890000	Separate DR & CR . . . 1 (0/1)
Unassigned cash ?	UNASS	Autogenerate match ref . 1 (0/1)
Error limit percentage 25.00		
Error limit absolute value . . 1000.00		
F3=Exit F4=Prompt F10=Consolidation companies		
F12=Previous F15=Names and addresses		
7-34	SR	MW KS CL IM DM II EDN400A KB PKH312S1

Fields:

Default Payments (Bank Account)

Enter an account code of up to 12 characters in length. It must be a valid balance sheet account set up on the chart of accounts, and should be defined as a bank account via Cash Management.

If so specified for this account, you must enter extension codes in the standard window.

Net Profit (Account)

Enter an account code of up to 12 characters in length. This must be a valid profit and loss memorandum account which exists on the chart of accounts. It is mandatory to enter this account, which will be used at period end to hold the net profit for the period and year to date.

The procedure will set the post-inhibit flag to Y.

If specified for this account, you must enter extension codes in the standard window.

Inter-Company Accounting

0 - You do not want to post transactions from this company to another company.

1 - You do want to be able to post transactions to other companies.

Rounding Errors (Fiscal Account)

Enter an account code of up to 12 characters in length. This must be a valid balance sheet account set up on the chart of accounts.

If specified for this account, you must enter extension codes in the standard window.

In the case of an imbalanced journal arising (for example from an external system) the system will balance the journal to this account automatically, allowing the posting to be corrected by way of a general journal posting.

VAT Periods Per Year

Enter the number of VAT accounting periods in a year. You can enter from 1 to 12.

Rounding Errors Account (Memo)

Enter an account code of up to 12 characters in length. It must be a valid balance sheet account set up on the chart of accounts.

If specified for this account, you must enter extension codes in the standard window.

In the case of an imbalanced journal arising - for example from an external system - the system will balance the journal to this account automatically, allowing the posting to be corrected by way of a general journal posting.

C&E Exch Rate Code?

Enter a suitable code to apply to a Customs and Excise exchange rate codes table with regard to acquisition VAT.

US Tax Group

If the United States is specified in the country code field of the company profile screen this field appears.

If your company is to be consolidated with others for a 1099 return, enter the tax group which is to link them.



Note: This field is relevant only to US companies preparing 1099 tax returns.

Future Suspense Account

Enter a valid balance sheet account to be the future suspense account.

This account is used by the cross period journals function when posting to one or more future periods; however, an account must be entered, even if you do not plan to use cross period journals.

Prior Suspense Account

Enter a valid balance sheet account to be the prior suspense account.

This is an account used by the cross period journals functions when posting to one or more prior periods. However, an account must be entered, even if you do not plan to use cross period journals.

Contras Suspense Account

Enter an account code of up to 12 characters in length. It must be a valid balance sheet account set up on the chart of accounts.

If specified for this account, you must enter extension codes in the standard window.

This account is used by the contra accounting facility in Accounts Receivable and Accounts Payable for posting between customer control accounts and supplier control accounts.

Statutory Account Length

Enter the statutory length of accounts if this is a requirement to the country concerned.

Profit Account (Opening Balance Account)

Enter an account code of up to 12 characters in length. It must be a valid balance sheet account set up on the chart of accounts.

Enter extension codes in the standard window which displays if you have opted to use extension codes.

This account is mandatory and is used at year end to post this year's profit after clearing down the profit and loss account year-to-date balances.

If year end journals are active, and this is a profit account, it is designed to hold the positive value posted from a nominated summary profit and loss account when a year end journal is posted.

Separate Dr & Cr?

0 - See the debit and credit values displayed together in the transaction matching procedure.

1 - See debit and credit values displayed separately.

If you wish to use year end procedures and you require your debit / credit position within Accounts Payable and Receivable to balance with the General Ledger, then set this field to 1.

Loss Account

Enter an account code of up to 12 characters in length. It must be a valid account set up on the chart of accounts.

If specified for this account, you must enter extension codes in the standard window.

This account will hold the negative value posted from a nominated summary profit and loss account when a year end journal is posted.



Note: This field will be displayed only if year end journals are active.

Unassigned Cash

You must add a GL account to hold unassigned cash. This should be a fiscal balance sheet account. Unassigned cash is only posted via lockbox/EDI at the CS option Process External Data.

Autogenerate Match Ref?

0 - If you do not want to generate references automatically in the transaction matching procedure. You will have to enter them for each procedure.

1 - If you do want to generate references automatically.

Summary Profit & Loss Account

Enter an account code of up to 12 characters in length. It must be a valid account set up on the chart of accounts.

If specified for this account, you must enter extension codes in the standard window.

This account will hold the values of the profit and loss accounts when a year end journal is run.



Note: This field displays only if the year end journals are active.

Summary Closing Balance Sheet Acct

Enter an account code of up to 12 characters in length. It must be a valid account set up on the chart of accounts.

If specified for this account, you must enter extension codes in the standard window.

This account will hold the values of the balance sheet accounts when a year end journal is posted.



Note: This field displays only if the year end journals are active.

Summary Opening Balance Sheet Acct

Enter an account code of up to 12 characters in length. It must be a valid account set up on the chart of accounts.

If specified for this account, you must enter extension codes in the standard window.

This account will post all values of balance sheet accounts closed down by a year end journal back into the balance sheet accounts at year open.



Note: This field displays only if the year end journals are active.

Error Limit Percentage

Enter a tolerance limit, in percentage terms, covering the allowable difference between input and system-calculated VAT. This field is optional.

Error Limit Absolute Value

Enter a tolerance limit, in value terms, covering the allowable difference between input and system-calculated VAT. The decimal point is implicit.

If neither error limit is entered, the exact amount of VAT must be entered for posting to the General Ledger. To suppress validation, enter limits as all 9s. For example: 999999999999.99.



Note: If the option to have Year End Journals has been chosen, several more fields for key accounts appear on the screen.

Functions:

F10

Consolidation Companies. Set up or maintain consolidation companies.

F15

Names and Addresses. Enter the name and address of the company by which you wish it to be known externally.



Press **Enter**, then **F8=Update** to accept the details on the screen.

Maintain Consolidation Company Screen (F10)

The accounts of one company may be consolidated into the accounts of one or more other companies.

If the base currencies of all companies involved is the same, then the base currency values of this company are consolidated into the base currency values of the target company. Where these currencies are different, the values are translated into the target company's base currency.



Press **F10=Consolidation Companies** to see a list of the General Ledger companies which have already been set up as consolidated companies.



Enter the company you wish to consolidate (which must already exist in its own right), or enter 1 against an existing code to amend it. The Maintain Consolidation Company screen displays.

GL180	FS9	21/06/95 11:34:17
Maintain Consolidation Company		
Company code.....	09 FS EDUCATION COMPANY - 09	
Currency.....	USD USD	
Target company code.....	GP Group Consolidation Company	
Target currency.....	GBP GBP	
Target rate code.....?	PERD	
Consolidate memo accounts?.....	0 (0=No, 1=Yes)	
Period lead.....		
Translation level.....	1 (0=All a/cs, 1=Top level a/cs only)	
F3=Exit F4=Prompt F12=Previous 13-42 SF MW KS IM II EDN400A PCET02S3		

Fields:

Target Rate Code

If the base currencies of the two ledgers are different, enter the rate code in this company to translate into the target currency.

Consolidate Memo Accounts?

0 - Do not consolidate memorandum accounts.

1 - Memorandum accounts should be included in the consolidation.

Period Lead

This field is used to define the equivalent period in the target company.

For example,

2 - 2 months lead time. Example: If the source period is 10, and the target period is 12, this is a lead of 2 periods (enter 2).

4 - 4 months lag time. Example: If the target period is 6, this is a lag of 4 periods (enter 4).

Translation Level

0 - Consolidation includes sub-ledger accounts.

1 - Consolidate top level accounts only.



Press **Enter** then **F8=Update** to update the consolidation details.

Maintain Names And Addresses Window (F15)

Enter the name and address and registration details of the company, as you wish it to be known externally.

This is printed on the Company Profile Report. Where it is a statutory requirement, Italian reporting includes this information.



From the Company Profile details screen, press **F15=Names and Addresses** and enter the details.

GL100		USER FFV9	21/06/95
Maintain General Ledger Company Profile			11:37:07
Com	Maintain Names and Addresses		
Def	External company name .	Education Test Company (20)	1 (0/1)
Net	Address line 1	Kensington House	1 (0/1)
Rou	Address line 2	136 Suffolk Street	00
Fut	Address line 3	BIRMINGHAM	
Pri	Address line 4		*DFT
Con	Post code	B1 1NN	
Pro			
Los	Tax registration number		
Sum	Company registration. .		
Sum			
Num			
Err			
Err			
Int			
F12=Previous			
F3=Exit	F4=Prompt	F10=Consolidation companies	
F12=Previous	F15=Names and addresses		
07-32	SA	ML	KS IM II EDN400A PCET02S3

Fields:

External Company Name

Enter the name for the company by which you wish it to be known externally - up to 35 characters.

Address Line

Enter the address of the external company in the lines provided - up to 35 characters per line.

Post Code

Enter the post code of the external company - up to 9 characters.

Tax Registration Number

Enter the tax registration number of the external company - up to 20 characters.

Company Registration

Enter the registration of the external company - up to 25 characters.



Press **Enter** to update and return to the previous screen.

General Ledger Report



11/ASCO

This allows you to print two reports, detailing:

- The current state of a specified company profile.
- The history of any changes made to a specified company profile.



Select the appropriate option from the menu, enter the company you wish to report on, and press **Enter** to see the selection fields:

Fields:

Print Current Status Or History?

- 1 - The report will reflect the company profile as it is at the time of printing.
- 2 - An audit trail of all the amendments to the company profile will be printed. You must specify a start date.

Start Date

Enter a start date to limit the report to changes made since that date, or leave blank to print the entire history of changes to the profile.



Press **Enter** to submit a batch job to generate the report.