

-
-
-
-
-

Chapter 2

Audit Control & Other Maintenance



Archived To Period

Displays the last period for which the accounts have been archived.

Level Codes Required

0 - Level codes are not used.

1 - You are using level codes.

Immediate Account Maintenance Required

0 - Do not update hierarchy control accounts at period end.

1 - Hierarchy control accounts should be updated immediately on completion of a posting period.

System Status

Tell you whether the update system is active or not.



Note: The enquiry also informs you of any journals or hierarchy accounts which are awaiting update.



Press **Enter** to exit and return to the menu.

Prior Period Journals Report



11/GLA



Select the Prior Period Journals Report option to display a confirmation window.

This report lists details of all prior period journals which have been posted since transactions were last archived or purged.



Press **F8=Update** to submit a batch job to produce the report.

Journal Sequential Control Report

1...
2...

12/GLA

If the references for any type of journal are entered sequentially (as, say, 90001234, 90001235 and 90001236) or, if they are generated automatically by the system, this report will identify journals not posted within a given range of references and for a given period.

Missing Journal Report Screen 1



Select the Journal Sequential Control Report option to display the selection screen.

Select the report by transaction source, type, private ledger company and journal reference. Define a format for the search criteria.

```

GL139          Z1 - GB Demonstration Company    USER GBJBA1MS    4/
                                                    15:
MISSING JOURNALS REPORT

Transaction Source . . . . . C
Transaction Type . . . . . UC

Private ledger company . . . . . Z1

Format for journal reference . : NNNNNNNN
                                (Select any combination from:-
                                A=Alphabetic (A-Z),
                                N=Numeric (0-9),
                                X=Alphanumeric (A-Z and 0-9),
                                P=Prompt (e.g. for limited values or ot
                                    symbols such as / & -))

F3=Exit    F12=Previous

10-36      SA      MW      KS      CL      IM      DM      II      STUD140      KB      PKH31
  
```

Fields:

Transaction Source

Enter the transaction source. The prompt option is available - select from a list of all sources linked to this General Ledger.

Transaction Type

Enter a transaction type which may be generated from a particular transaction source.

Format For Journal Reference

System-generated references generally start at 00000001 and increment by one. The format for such references is simply NNNNNNNN.

If references for the journal type are entered manually, as in the case of general journals, you can use any permutation of keyboard characters.

Define your search criteria for the next journal reference to be used. At any position within the reference format you may use one of the following characters:

A - at this position, the reference must have a letter, but not a number or a blank.

N - at this position the reference must have a number, but not a letter or a blank.

X - at this position the reference must have either a letter or a number, but must not be left blank.

P - Prompt for anything not covered by A, N or X. For example, / or -. You can specify only certain letters or numbers, or a blank. If you enter P at any position within the format, you will be prompted for further details.

Examples

For a reference of 00000001 use the format NNNNNNNN.

For a reference of bbbbbbb1 (where b is a blank) use the format PPPPPPN.

For a reference of 123456-D use the format NNNNNNPA.

For a reference of 1234L (four digit number, followed by either A, B or C) use the format NNNNP.

Prompt on Format Position Window

You can complete only one section. The window's heading specifies the position within the format currently being defined.

Any combination of characters entered in the upper section could also be entered in the lower section. On revision the previous definition will be displayed in the lower section.



This window displays when the Format for Journal Reference includes P and **Enter** is pressed.

```

GL139                      Z1 - GB Demonstration Company    USER GBJBA1MS    4/
                                                                16:
MISSING JOURNALS REPORT

Transaction Source . . . . . C
Transaction Type . . . . . UC

Private ledger company . . . . . Z1

Fo Prompt on Format Position 5
   Complete one section only.
   -----
   All of A-Z? . . . : 0 (0/1)
   All of 0-9? . . . : 0 (0/1)
   Blank Allowed? . . : 0 (0/1)
   Other symbols . . : 
   -----
   Restricted values : ABC
   -----
   Including blank? : 0 (0/1)
   F8=Confirm F12=Previous

PI
po
Pr

P
ct any combination from:-
phabetic (A-Z),
meric (0-9),
phanumeric (A-Z and 0-9),
ompt (e.g. for limited values or ot
symbols such as / & -))

the usage of the P(s) specified at

F3=Exit F12=Previous F17=Revise all P(s) in format

17-30 SA MW KS CL IM DM II STUD140 KB PKH31
  
```

If you have opted to be prompted on more than one position, the prompts appear sequentially.

Fields:

All Of A - Z

0 - A letter is not allowable.

1 - Any letter from A to Z is allowable.

All Of 0 - 9

0 - A digit is not allowable at this position in the format.

1 - Any digit from 0 to 9 is allowable at this position in the format.

Blanks Allowed

0 - This position cannot be left blank.

1 - This position may be left blank.



Note: If it must be left blank, you do not need to define it as P - you could just leave it blank on

the format definition.

Other Symbols

If characters other than letters, numbers or blanks are permissible, enter them here. Depending on your keyboard, these might include symbols such as /, \$ or %.

If you want to enter more than four such characters, use the lower section of this window.

Restricted Values

If only some characters are allowed at this position and the combination is not covered by the upper section of the window, enter them here.

Including Blank

1 - In addition to characters specified in the preceding field, this position may be left blank.



Having prompted for a position, pressed **F8=Update** and **Enter**, the final screen will appear in which you can enter additional criteria.

Missing Journals Report Screen 2



Press **F8=Confirm** on the Prompt On Format Position Window to display the second Missing Journal Report screen.

Select a range of journal references for a specific period or for all periods.

GL139	Z1 - GB Demonstration Company	USER GBJBA1MS	5/12/97 8:25:00
MISSING JOURNALS REPORT			
Transaction Source		C	
Transaction Type		UC	
Private ledger company		Z1	
Format for journal reference		NNNNP (Select any combination from:- A=Alphabetic (A-Z), N=Numeric (0-9), X=Alphanumeric (A-Z and 0-9), P=Prompt (e.g. for limited values or other symbols such as / & -))	
Lowest Journal Reference		0010A	
Highest Journal Reference		0110B	
Period		9511 (Leave blank for all)	
F3=Exit F8=Confirm F12=Previous (revise format)			
21-42 SA MW KS CL IM DM II STUD140 KB PKH312S1			



*Note: You may press **F12=Previous** to revise the format.*

Fields:

Lowest Journal Reference

Enter the journal reference at which you wish to start to look for missing journals. The reference entered must conform to the specified format

If you leave this blank, the upper limit must be entered to restrict the possible volume of data.

Highest Journal Reference

Enter the latest reference in the range to be selected for checking.

Leave blank to report from the first reference entered.

Period

Enter the period to check for missing journals. Leave blank for the report to cover all periods.

The period entered must be within the number defined in the company profile.



A message is displayed giving the potential number of journals to be listed. Press **F8=Update** to accept the range and print the report. A batch job is submitted to generate the

report.

Suspended Journals Report



13/GLA

This report provides a list of all journals which have been suspended during transaction posting sessions.

The Suspended Journal Report will print all non updated journals.

The report would normally be run immediately before period end, since period end cannot be run if there are suspended journals.



Note: The security object GPST (set up at the utility option Maintain Security Object) may be set up to allow users to post journals but not update them. The update could then be approved and updated by an authorised user.



Select Suspended Journals Report to display a confirmation window. Press **F8=Update** to submit a batch job to produce the report.

Audit Reports



Select the one of the four available GL audit report options.

An audit trail of amendments is printed for selected ledgers and accounts within selected dates. Data may be retained or cleared once printed. A report is produced giving full details of the changes, including change date, terminal and user signon.

- Chart of Accounts.
- Account Level Codes.
- Report Control Codes.
- Ledger Descriptions.

Chart of Accounts Audit Report



21/GLA



Select the GL audit report option Chart of Accounts.

Prints an audit trail of amendments to General Ledger accounts within selected dates. Data may be retained or cleared once printed. A batch job is submitted and a report is produced.

GL259	Version 3 Demonstration Company	USER GBJBANB1	26/11/97
			11:25:10
Print Audit Report on Chart of Accounts			
Ledger ?		BNK	(Leave blank for all)
From Date		010197	(Leave blank for earliest)
To Date			(Leave blank for latest)
Clear Data After Printing? . .		0	(0=No, 1=Yes)
F3=Exit F4=Prompt			
10-34	▪	KS CL IM DM II	MARVIN KB PKH312S1

Fields:

Ledger

Select a ledger or sub-ledger for the audit report.

Leave blank to print a history of changes for all your ledgers.

From Date

Enter a From date for the first day items are to be included on the report.

Leave blank for earliest date.

To Date

Enter a To date for the last day to include items on the report.

Leave blank for latest date.

Clear Data After Printing

0 - Retain data for later re-selection.

1 - Delete selected data once it is printed.



Press **Enter** to validate your entries and to display the **F8=Confirm** function.



Press **F8=Confirm** to submit a batch job to produce the report.

Account Level Codes Audit Report



22/GLA



Select the GL audit report option Chart of Accounts.

Prints an audit trail of amendments to General Ledger account levels within selected dates. Data may be retained or cleared once printed. A batch job is submitted and a report is produced.

GL259	Z1 - GB Demonstration Company	USER GBJBA1MS	26/11/97
			14:58:12
Print Audit Report on Account Level Codes			
Global Levels?	: 0	(0=No, 1=Yes)	
Cross-ledger levels?	: 1	(0=No, 1=Yes)	
Ledger ?	: ____	(Leave blank for all)	
From Date	: ____	(Leave blank for earliest)	
To Date	: ____	(Leave blank for latest)	
Clear Data After Printing? . .	: 0	(0=No, 1=Yes)	
F3=Exit F4=Prompt			
5-34 SA MW KS CL IM DM II STUD140 KB PKH312S1			

Fields:

Global Levels?

0 - Omit global levels from the audit report.

1 - Include global extension levels in the audit report.

Cross-Ledger Levels?

0 - Omit cross ledger levels from the audit report.

1 - Include the cross ledger level codes (over 2 or more ledgers).

Ledger

Select a ledger or sub-ledger for the audit report.

Leave blank to print a history of changes for all your ledgers.

From Date

Enter a From date for the first day items are to be included on the report.

Leave blank for earliest date.

To Date

Enter a To date for the last day to include items on the report.

Leave blank for latest date.

Clear Data After Printing

0 - Retain data for later re-selection.

1 - Delete selected data once it is printed.



Press **Enter** to validate your entries and to display the **F8=Confirm** function.



Press **F8=Confirm** to submit a batch job to produce the report.

Report Control Codes Audit Report



23/GLA



Select the GL audit report option Report Control Codes.

Prints an audit trail of amendments to General Ledger report level codes within selected dates. Data may be retained or cleared once printed. A batch job is submitted and a report is produced.

GL259	MB - MB Industries	USER GBJBANB1	27/11/97
			11:20:00
Print Audit Report on Report Level Codes			
Ledger	? <u>E/L</u>	(Leave blank for all)	
From Date	<u>010197</u>	(Leave blank for earliest)	
To Date	<u> </u>	(Leave blank for latest)	
Clear Data After Printing? . .	<u>0</u>	(0=No, 1=Yes)	
F3=Exit F4=Prompt			
12-34	▪	KS CL IM DM II	MARVIN KB PKH312S1

Fields:

Ledger

Select a ledger or sub-ledger for the audit report.

Leave blank to print a history of changes for all your ledgers.

From Date

Enter a From date for the first day items are to be included on the report.

Leave blank for earliest date.

To Date

Enter a To date for the last day to include items on the report.

Leave blank for latest date.

Clear Data After Printing

0 - Retain data for later re-selection.

1 - Delete selected data once it is printed.



Press **Enter** to validate your entries and to display the **F8=Confirm** function.



Press **F8=Confirm** to submit a batch job to produce the report.

Ledger Descriptions Audit Report



24/GLA



Select the GL audit report option Chart of Accounts.

Prints an audit trail of amendments to GL ledger and sub-ledger descriptions within selected dates. Data may be retained or cleared once printed. A batch job is submitted and a report is produced including Action, When, and By Whom details.

GL259	MB - MB Industries	USER GBJBANB1	27/11/97
			11:35:03
Print Audit Report on Ledger Descriptions			
From Date	: 01/01/97	(Leave blank for earliest)	
To Date	: 30/06/97	(Leave blank for latest)	
Clear Data After Printing? . . .	: 1	(0=No, 1=Yes)	
F3=Exit			
9-34	▪	KS CL IM DM II	MARVIN KB PKH312S1

Fields:

From Date

Enter a From date for the first day items are to be included on the report.

Leave blank for earliest date.

To Date

Enter a To date for the last day to include items on the report.

Leave blank for latest date.

Clear Data After Printing

0 - Retain data for later re-selection.

1 - Delete selected data once it is printed.



Press **Enter** to validate your entries and to display the **F8=Confirm** function.



Press **F8=Confirm** to submit a batch job to produce the report.

Calendar Maintenance



31/GLA

Calendar maintenance is used to specify the end date for each period. If the accounting date function is active, these dates are used to determine the period that should be posted to.

In addition, information relating to working days and holidays can be specified. In Accounts Receivable and Accounts Payable modules, calculated due dates can, optionally, be made to exclude weekend and holidays.



Note: See GL Country-Specific Parameters 023 and 024 which explain AR / AP Due Date Exclude Weekends/ Holidays options.

The specified holidays are fed into the year's calendar and an update of the number of working days within the year is automatically made.

The calendar can be used to validate document dates against periods.



Note: See GL Country-Specific Parameter 010 Check that Date & Period Correspond.

Calendar Maintenance Selection Screen



Select the Calendar Maintenance menu option.

GL016	Y6 - Education Company - Y6			USER FFV6	31/07/95 11:18:27
Calendar Maintenance					
Sel	Year	Days	Working Days	Year Start	
1	94	365	365	1/01/94	
1=Select 4=Delete 6=Print					
Enter Year: __					
F3=Exit					
06-04 Sf MW KS IM II KENB20A PCET02S1					

Fields:

Sel

Enter 1 against a year to select it for maintenance.

Year

The two digit number indicating the year.

Days

The number of days in the year.

Working Days

The number of working days in the year as calculated by the holidays specified.

Year Start

The date specifying when the company's year begins.

Enter Year

Enter a year number to set up a new year.



The Calendar Maintenance Period End Dates Screen displays when the a year is entered at the selection screen.

Calendar Maintenance Entry Screen

Use this screen to set up and maintain period end dates. Periods display as open for posting or closed.



Enter a year on the first Calendar Maintenance Selection Screen to display this screen.

GL016	Z1 - GB Demonstration Company	USER GBJBA1MS	5/12/97
Calendar Maintenance			
Calendar.... 0001	Year.... 98	Start Date....	10198
Enter the Financial Year End Dates as required			
Period	Period end date		
9801	310198		
9802	280298		
9803	310398		
9804	300498		
9805	310598		
9806	300698		
9807	310798		
9808	310898		
9809	300998		
9810	311098		
9811	301198		
9812	311298		
F3=Exit F8=Update F12=Previous F17=Holidays			
5-57	SA	MW	KS CL IM DM II STUD140 KB PKH312S1

Fields:

Start Date

Enter the date from when the year will begin. You can amend this date.

Period End Date

Enter the date when the period will come to a close. You can amend this date.

This date may not be earlier than the end date of a previous period.

Open?

The appearance of this column is dependent on the parameter setting. This field would usually be used to stop posting to future periods.

0 - You may not post to the period.

1 - Transactions may be posted to the period.

Functions:

F8

Update. Allows you to update the calendar.

F17

Holidays. Allows you to enter details of holidays.



Press **F17=Holidays** on the Calendar
Maintenance screen to enter the calendar dates.

Calendar Maintenance Holiday Screen (F17)

Use this screen to set the usual non-working days as N and to set your company's closed for holiday dates. In Accounts Receivable and Accounts Payable modules, calculated due dates can, optionally, be made to exclude weekend and holidays.



Note: See GL Country-Specific Parameters 023 and 024 which explain AR / AP Due Date Exclude Weekends/ Holidays options.

The specified holidays are fed into the year's calendar and an update of the number of working days within the year is automatically made.



This screen displays when **F17=Holidays** is selected from the first Calendar Maintenance Screen.

```

GL016                Y6 - Education Company - Y6          USER FFY6        31/07/95
                                                    11:18:27

Calendar Maintenance

Year 94              Standard Week: M T W T F S S
Holidays             _ _ _ _ _ N N
From                 To
█ _____      _____
_____            _____
_____            _____
_____            _____
_____            _____
_____            _____
_____            _____
_____            _____
_____            _____
_____            _____
_____            _____

```

```
F8=Update   F12=Previous
    08-03   SF           MW         KS           IM           II   KENB20A PCET02S1

```

Fields:

Standard Week M To S

Enter an N in the field if the day in the standard week is to be taken as a holiday. Otherwise leave it blank if the day is to be taken as a normal working day.

Holidays From

Enter a date to indicate the start of a block of days to be allocated as holiday.

Holiday To

Enter a date to indicate the end of a block of days to be allocated as holiday.



Press **F8=Update** in order to update the calendar.

Parameters Maintenance



32/GLA

Parameters are fields (major types) which hold codes (sub-types) for further organisation of your general ledger.

The system creates some parameter codes with its sub-types. For example, TTYP which holds the identifying transaction type codes, such as IN for an invoice.

You may maintain and add to other parameters. For example, CRSP which holds codes to identify your credit controllers.

Some of these parameters relate to the Accounts Payable and Accounts Receivable applications, such as customer groups or supplier groups. These parameters are only relevant if you are using these applications.

Maintain Parameters Screen



Select the maintenance option Parameters option.

A list of existing major type parameters displays.

GL108		Y6 - Education Company - Y6			User: FFY6		31/07/95	
							11:20:12	
Maintain Parameters								
Sel	Srcce.	Type	Description	Value 1 Reqd.	Value 2 Reqd.	Code Length		
-	Sys.	CCOD	Country Code			03		
-	User	CGP1	Customer Group 1			03		
-	Sys.	CGP2	Customer Group 2			03		
-	Sys.	CGP3	Customer Group 3			03		
-	Sys.	CGP4	Customer Group 4			03		
-	User	CRLC	Credit Agency Code			03		
-	User	CRSP	Credit Responsibility Code			06		
-	Sys.	GENV	General Validation			06		
-	Sys.	GOVS	Tax Supplier	1		08		
-	Sys.	JCOD	Journal Code			02		
-	Sys.	JTYP	Journal Type			02		
-	Sys.	NTCD	National Code			08		
-	User	PFMC	Performance Codes			01	+	
Enter Type.. █								
2=Maintain 4=Delete 5=Sub-codes								
F3=Exit								
21-15		SF	MW	KS	IM	II	KENB20A	PCET02S1

Fields:

Sel

2 - Maintain an existing major type parameter.

4 - Delete a major type parameter.

5 - Maintain, review or add sub-types for this major type.

Srcce

Sys - the parameter is system-defined.

User - the parameter is user-defined.

Type

The name of this parameter.

Description

A description of the parameter. Up to 30 characters in length.

Values 1 & 2 Required

1 - A value must be entered whenever one or both of these parameters are applied to a transaction.

Code Length

Identifies the length of the sub-type code, which can be up to 10 characters.



Enter 5 to display the sub-codes of a major type parameter. A list of existing sub-types display.

Parameters Sub-types Screen (Option 5)



Enter 5 to display the codes of a major type parameter, A list of any existing sub-types displays.

At this screen, add new sub-codes or maintain or delete existing sub-codes. System defined sub-codes may not be deleted.

GL108	Y6 - Education Company - Y6	User: FFV6	31/07/95 11:21:07
Maintain Parameters			
Parameter . . : SGP1		Code Length . : 03	
Description . : Supplier Group 1			
Src. Code	Description	Value 1	Value 2
_ User NTH	North UK	.00	.00
_ User STH	South UK	.00	.00
Enter new code..			
2=Maintain 4=Delete F3=Exit F12=Previous			
21-09	SF	MW	KS IM II KENB20A PCET02S1

Fields:

Select

2 - Maintain an existing sub-type.

4 - Delete an existing sub-type.

Enter New Code

Enter the name of a new sub-type of up to three characters in length.

Description

Enter a description for the sub-type of up to 30 characters in length.

Value 1

If required, enter a value for this sub-type parameter. Such a value might indicate tolerance limits. This field is displayed only if the Value 1 Req'd field is 1 on the maintain parameters screen.

Value 2

If required, enter a value for this sub-type parameter. Such a value might indicate tolerance limits. This field is displayed only if the Value 2 Req'd field is 1 on the maintain parameters screen.



Note: The length allocated to the sub-types (as

specified on the Maintain Parameters Screen) is shown at the top of the screen.



Press **Enter** to update.

Parameters List of GL Types

ACSH

Auto cash adjustment tolerance. The system creates this code to be used for write off adjustments in the Accounts Receivable Advanced Post Cash & Allocate option. It will hold the adjustments write-off code AJ with the maximum write-off value. This is the maximum write-off value for automatic write-offs. You may, of course, manually write off any values.

You may amend the adjustment code and the value. The adjustment code must exist as an adjustment type in ARAT. Only one reason code can be used here.

ARAT

AR Adjustment type. These codes are used during Accounts Receivable cash allocation to post adjustments.

ARIT

AR Item type. These codes describe item postings.

BRD1

Brand 1. Reserved for future use.

CCOD

Country code. This parameter is used to identify which country a company, customer or supplier belongs to. In customer/supplier and bank account maintenance it will determine the type of bank window that will be displayed for input.

CGP1 to CGP4

Customer groups. This holds user-defined codes which group customers together for reporting purposes.

CLND

Calendar. This code must be set up to define different calendars. Calendars are assigned codes to be used in GL Calendar Maintenance. Calendar codes may also be selected at customer and supplier Names and Addresses options - so that due dates may be calculated around weekends/holidays.

CRLC

Credit agency code. Credit agency codes can be attached to customers where an agency is being used to collect payment.

CRSP

Credit responsibility code. Credit controllers are set up to be attached later to customers and to be reported at aged debt, overdue items and rolling trends reports/enquiries. Bad debt provision and interest calculations can be calculated by controller.

CSTA

Cost allocation. If you intend to use the Cost Allocation Journal maintenance option then you must set up the accounts you wish to use as default and unallocated accounts.



Note: This is not necessary when using the Advanced Cost Allocation Journal option.

See also CSTA Cost Allocation Sub-codes.

GENV

General validation. No longer used in the system.

GOVS

Tax supplier. This parameter enables you to set up suppliers as Government Suppliers for the purposes of the withholding tax function.

JCOD

Journal code. This parameter holds the system defined journal types (for example: invoice, credit note, journal) used by General Ledger and French statutory reports.

JTYP

Journal type. This parameter holds the system defined transaction analysis types (for example, sales, purchases, bank transactions, GL items) used by French statutory reports.

LENT

Classification of supplier. This parameter is used to identify a supplier as a person or legal entity.

NTCD

National code. This parameter is used to identify the country of a supplier subject to withholding tax.

PFMC

Performance codes. These performance codes are used if you are using Accounts Receivable trend parameters.

PYGP

Payment group. This parameter holds codes which are used to group together suppliers for a payment run.

REGN

Region. You can set up codes to represent regions within Accounts Receivable. Regions can then be assigned against each customer and may be used for reporting.

RPAC

Recurring payment analysis. If you are going to use the recurring payments function in Accounts Payable, you must set up at least one analysis code here.

SGP1 to SGP4

Supplier groups. Used to group suppliers for reporting purposes.

SLMN

User-defined code to group customers together by salesman, for reporting purposes.

SRC1

This parameter is used to hold an extra search field in the Customer Search facility in Accounts Receivable. The search fields to be used are selected at the AR Company Profile Alpha Search Details Screen.

Set up this parameter with the description AR Search Field 1. The system adds the sub-codes from your selection in the AR Company Profile.

SRC2

The second extra search field. Set up this parameter with the description AR Search Field 2. The system adds the sub-codes from your selection in the AR Company Profile.

STCD

State code. A code is defined for each of the states in the USA, plus some codes for other trading areas. This is used when 1099 Payment Analysis Codes are assigned to suppliers.

TSRC

Transaction source. These single character codes tell GL where the postings it receives have come from (which application has sent each posting).

TTYP

Transaction type. These two character codes tell GL the type of posting that it is receiving - for example, IN for an invoice or CR for a credit note.

TXST

Text status. Accounts Receivable enables you to assign a status to the text entered on customers and their items. Used for enquiry purposes.

VREC

VAT reconciliation report. This parameter holds a sub-code VTOL which is the default tolerance value (in base) to be used instead of the company profile VAT tolerance value when running the VAT reconciliation report.

VREG

VAT register. VAT registers are used to satisfy Italian statutory requirements. These registers are used when posting items within Accounts Receivable and Accounts Payable.

WTAX

Withholding tax. Defines the different withholding tax groups on the system. Identifies types of business for suppliers.

CSTA Cost Allocation Sub-codes



Note: This is not necessary when using the Advanced Cost Allocation Journal option.

Select major type CSTA with 5 to see the sub-types. The Maintain Parameters screen displays (with or without entries).

If no accounts have been entered, you must now enter your four GL cost allocation accounts as follows:

Subtype	Entry
DEFAULT1	Enter positions 1-25 of the default account to be used for fiscal journals.
DEFAULT2	Enter positions 26-42 of the default account to be used for fiscal journals.
DEFAULT3	Enter positions 1-25 of the default account to be used for memorandum journals.
DEFAULT4	Enter positions 26-42 of the default account to be used for memorandum journals.
UNALLOC1	Enter positions 1-25 of the unallocated account to be used for fiscal journals.
UNALLOC2	Enter positions 26-42 of the unallocated account to be used for fiscal journals.
UNALLOC3	Enter positions 1-25 of the unallocated account to be used for memorandum journals.
UNALLOC4	Enter positions 26-42 of the unallocated account to be used for memorandum journals



Enter the first account as the DEFAULT1 sub-type. If the account including extension codes is longer than 25 figures, you will have to enter the end ones as DEFAULT2. If the account is 25 figures or fewer, you will not need to use DEFAULT2 at all.

Continue for the other three accounts. When you have finished, you are ready to start setting up your journal.

Rebuild Account Descriptions



33/GLA

Within chart of accounts you have the option to change the description generated by the system. If you do so, then change your mind, this procedure enables you to rebuild the descriptions.

This facility could also be used if the description of a level code changes and you wish to reflect the changed level code description across your chart of accounts.



Select Rebuild Account Descriptions to see the following fields.

Fields:

Ledger

Enter a valid ledger code of up to three characters in length, or leave the field blank to rebuild account descriptions across all ledgers.

Include Only Changed

0 - All accounts are to be printed, whether or not they have been modified.

1 - Only those accounts which have been modified are to be printed on the audit report.



Press **Enter** to accept the details entered. An audit report is printed.

Total Descriptions Options

Two options enable you to maintain and report on the description of totals in the balance sheet and profit and loss reports.

- Total Descriptions Maintenance.
- Total Descriptions (Reports).

Total Descriptions Maintenance



34/GLA



Select the GL audit control and other maintenance option Total Descriptions.

This procedure enables you to define sub-totals in the balance sheet and profit and loss reports.

Maintain Total Descriptions Screen



Select either the balance sheet or the profit and loss option to display the Total Descriptions screen.

Select an existing total description to amend, or add new report sub-totals. For each report line an account sequence number must be given. Lines will be included in the assigned total. For example, all 1s will be sub-totalled together, all 2s and so on.

See Total Example for more information.

GL137		Y9 - Education Company - Y9		USER FFV9	28/07/95
Maintain Total Descriptions					
Ref.	Acct Seq.	Description	Total		
1	100	TOTAL FIXED ASSETS	5		
2	150	TOTAL STOCKS	2		
3	180	TOTAL DEBTORS	2		
4	250	TOTAL BANK/ST Invest	2		
5	300	TOTAL CURRENT ASSETS	3		
6	350	TOTAL CREDITORS	2		
7	370	TOTAL CURR.LIABILITS	3		
8	380	NET CURRENT ASSETS	5		
9	400	NET ASSETS	10		
10	450	TOTAL CAPITAL & RESV	1		
Reference... (Change only)					
Acct Seq....					
Total No.... (01-20)					
F3=Exit 19-17 SF MW KS IM II EDN400A PE0079S1					

Fields:

Reference

When new total descriptions are being entered, this reference is generated sequentially by the application. Where details are being amended or deleted, the code is identified by entering this reference number.

Acct Seq

If you require a sub-total to appear on your report, enter the account sequence number as defined in report level code E.

Total

Defines the level of sub-total for this particular code. The range of codes is 0 to 20. The total code operates as follows:

Given any single total code, the application will accumulate all values of a lower level code since the last occurrence of the same level. The bigger the total code, the more major the sub-total.

See Total Example for more information.



Press **Enter** to accept your entries.

Total Example:

Ref	Code	Description	Total Code	Posted Value
1	010	Sales		-5,000.00
2	020	Cost of Sales		3,000.00
3	050	Gross Profit	03	-2,000.00
4	100	Heating		213.00
5	110	Lighting		209.00
6	120	Vehicle Expenses		184.00
7	190	Total Expenses	01	606.00
8	200	Repairs		88.00
9	210	Carriage		92.00
11	300	Insurance		100.00
12	310	Depreciation		200.00
13	320	Rates		300.00
14	390	Total Fixed Costs	01	600.00
15	400	Total Costs	03	1,386.00
16	500	Net Profit	04	-614.00
10	290	Total Variable Costs	02	786.00

Each sub-total adds up all the preceding individual accounts (excluding sub-totals) until it finds a total number greater than or equal to itself. For example:

Heading	Accumulates
Gross Profit	Sales and Cost of Sales
Total Expenses	Heating, Lighting and Vehicle expenses
Total Variable Costs	Total expenses , plus Repairs, Carriage
Total Fixed Costs	Insurance, Depreciation, Rates
Total Costs	Total Variable costs , plus Total Fixed Costs
Net Profit	Gross Profit , plus Total Costs

Using these codes and the account sequences, the following report would be produced:

Gross Profit	-2,000.00
Total Expenses	606.00
Total Variable Costs	180.00
Total Fixed Costs	600.00
Total Costs	1386.00
Net Profit	-614.00

Total Descriptions (Report)



42/GLA



Select the GL audit control option Total Descriptions (Reports) to display the maintenance window.

A window will display asking you to press **F8=Update** and set a batch job running. A report of all total descriptions for this company will be produced.

Inter-Company Accounts Maintenance



35/GLA



Select the audit control maintenance option Inter Company Accounts to display the selection screen.

Within this procedure you can specify the names of accounts you wish to use to process transactions between companies.


When a value is to be credited in one company's account and debited in a second company's account, all you will enter is the credit on one side and the debit in the other. However, the accounts within a company must balance, so for the credit in the first company, there must also exist an account within that company to hold the debit. Likewise, within the second company, for the debit there must also be a separate account holding the credit.

The accounts which hold these values are Inter-Company Accounts, which are set up solely for this purpose.

Balancing postings are automatically made to these accounts when required.

This diagram illustrates the use of such accounts:

Posting \$100 from Company X to Company Y



Select the GL audit and other maintenance option Inter-Company Accounts Maintenance and a list of company relationships and account details which have been set up on the system displays.

Source Company

The company from which transactions are to be posted.

Target Company

The company to which transactions are to be posted.

Debtor Account

The account to which balancing debits should be posted in the source company.

Description

The description of the debtor account.

Creditor Account

The account to which balancing credits should be posted in the source company.

Description

The description of the creditor account.



Note: The relationship must be defined in both directions. For example, company AA must be defined to company BB, and company BB to AA.



The Account Details Window displays when you enter 1 to amend or by pressing **F10=Add**.

Change Inter-Company Account Details Window (F10)



This window displays when you enter 1 to amend or by pressing **F10=Add** at the first selection screen.

At this window enter your GL debtor and credit accounts for the inter-company accounting. Select a currency rate code and year-end period lead difference where required.

Src		Tgt		Debtor Acct		Description		Creditor		Acc. Description	
Opt	Co	Co	Co	Co	Co	Description	Description	Co	Co	Description	Description
	Y0	Y9		411500		Trade Debtors-Int/Co		401500		Trade Creditors-Int/Co	
1	Y9	Y0		411500		Trade Debtors-Int/Co		401500		Trade Creditors-Int/Co	

Change Inter-company Account Details					
Src	Tgt	Debtor (?)	Creditor (?)	Rate Code (?)	Period Lead
Y9	Y0	11500	401500	PERD	

F4=Prompt F12=Previous
1=Select 4=Delete
F3=Exit F10=Add

20-19 SA MK KS IM II EDN400A PCET02S3

Fields:

Src Co

Enter the company from which transactions are to be posted.

Tgt Co

Enter the company to which transactions are to be posted.

Debtor

Enter the account to which balancing debits should be posted in the source company.

This must be a valid account set up in the source company's chart of accounts.

Creditor

Enter the account to which balancing credits should be posted in the source company.

This must be a valid account within the source company's chart of accounts.

Rate Code

Enter a rate code if the base currencies of the two companies differ.

Period Lead

The year ends of the two companies may not be the same. If, for example, period 12 in one company is December, while in the other it is April, then the period lead (difference) needs to be specified. This will ensure that the same real period will be updated in the target company.

Enter the period lead as a negative number.



Note: If the Memo Values To Balance field is set to 1 in the company profile for the source company, you must also maintain the memo debtor and creditor accounts. Another window asks you to enter these.



Press **Enter** to accept the details.

You are returned to the first screen which will include any new or amended inter-company account(s) details.



Press **F3=Exit** to return to the menu.

Group Company



36/GLA



Select the GL audit control option Group Company to display the Group Company maintenance screen.

This option enables you to define a single company as a template company, with other companies defined to it.

When you wish to maintain these companies you can simply maintain the template company, and all the maintenance details will automatically be passed on to the others.

Fields:

Application

Enter the application to which the company group maintenance facility is to apply.

Group Company

Enter the code of the company which is to be the template company. This is the company which you maintain, and which then passes on the maintenance details to the other companies defined to it.



Enter the two codes required. If the company you enter has already been set up as a group company within this application, press **Enter** to be taken to the list of companies defined to it.

If the company you enter has not yet been set up as a group company within the application specified, then you will be asked to define what type of group company you are setting up.

Group Type

The group company can maintain companies defined to it in several ways. Enter the appropriate code:

- 1 - Mass maintenance and creation.
- 2 - Mass creation.
- 3 - Mass maintenance.
- 4 - Division.
- 5 - Tax.
- 6 - Legal.

To maintain an existing company select from the displayed list of all the companies defined to it.



Enter the type and press **Enter** to display the All Companies screen.

Parameters Report



41/GLA



Select the Parameters Report menu option.

A report of all application parameters for this company will be produced.



A window displays asking you to press
F8=Submit and set a batch job running.