

-
-
-
-
-

Chapter 1

Maintenance



Advanced Shipping Maintenance Procedures

This section defines the Advanced Shipping file maintenance procedures. It covers all the options that allow you to maintain the system parameters.


Defaults are held at company, customer/delivery sequence, and contract levels. When new customer defaults are created they are defaulted from the company level. When new contract defaults are created they are defaulted from the customer/delivery sequence level.

Customer/Delivery Point Defaults

1... 1/ADM **2...**

Customer defaults are held at customer/delivery sequence level. In general, whenever customer defaults are created the corresponding company parameters are used as default values. Company default parameters **MUST** exist in the company profile before any customer parameters can be maintained.

Advanced Shipping customer defaults are entered via the Customer Defaults screen. There are four possible input screens, which are linked together as follows:



Customer Defaults Screen



Selecting the Customer/Delivery Point Defaults option from the menu to display the Customer Defaults screen.

AS015	Z1 - GB Demonstration Company	User GBJBANB1	9/03/98 17:00:37
Customer Defaults			
Customer	<u>AUTOCUS1</u> <u>000</u>		
F3=Exit F4=Prompt			

Fields:

Customer

Enter the required customer code.



Press **Enter** to display the Customer Contract Defaults screen.

Customer Contract Defaults Screen



Press **Enter** from the Customer Defaults screen to display the Customer Contract Defaults screen.

```

AS025                Z1 - GB Demonstration Company    User GBJBANB1    9/03/98
                                                           17:03:04
Advanced Shipping Customer Contract Defaults
Customer.... AUTOCUS1      000      Automotive customer eg ROVER

Sales administrator code.?. SALE1 Premier salesperson
Country of origin.....?.  
Self billing..... 0 (0/1)
Pack rounding..... 0 (0/1)   Pack rounding %..... 0
Transmit ASNs..... 1 (0/1)   Create pack details..... 1 (0/1)
Detailed Packaging/Print Shipping Labels ..... 1 (0/1/2)
Ship lead time in days....     Ship only on working days.. 1 (0/1)
Calendar code.....?. CA
Despatch profile.....?.  
  OR Stockroom.....?. 01
Generate invoice no. as consignment ref.. 0 (0/1)
Invoice consolidation method.....
Invoice no. policy.....?. 01   One Invoice per Consignment
Send cumulative totals...?. 01   Cums. inclusive of this ASN
Consignment stockroom....?.  
Customers supplier code....  

F3=Exit F4=Prompt F8=Update F12=Previous
  
```

Fields:

Customer

The customer details are displayed.

Sales Administrator Code

Enter a code to enable contacts to be grouped together for review purposes. This field is optional.

Country Of Origin

Enter the code for the country of origin of the goods. This is used in Advanced Shipment Notification processing. This value will default onto the contract header record. This field is optional.

Self Billing

This is the Self Billing processing indicator.

0 - Self billing is not required. This is the default.

1 - Self billing is required and a regular invoice will not be generated.

Pack Rounding

This is the pack rounding indicator.

0 - Pack rounding is not required.

1 - Pack rounding is required.

Pack Rounding %

This is the pack rounding percentage used in pack rounding calculations. Enter the required percentage from 0 - '99'. The pack rounding percentage can only be set if the pack rounding flag is 1.

Transmit ASNs

This indicator identifies if Advanced Shipment Notifications will be created for transmission via EDI.

0 - ASNs will not be created.

1 - ASNs will be created.

Create Pack Details

This flag indicates whether pack details should be created by the Advanced Shipping process.

0 - The pack details should not be created.

1 - The pack details should be created.

Detailed Packaging/Print Shipping Labels

Although the choice of simple or detailed mode for Advanced Shipping is made in the Inventory descriptions, and is therefore at company level, you can override this for individual customers by making an entry here.

0 - Simple packaging. This gives you a single level of packaging, and no labelling.



Note: This value is ignored if you subsequently set any labelling options on for the customer/item/pack. The customer will automatically be treated as a detailed mode customer.

1 - Detailed packaging mode, and shipping labels.

2 - Detailed packaging mode, but without shipping labels. This option gives you the dual level packaging, but hides all the fields and functions relating to shipping labels.

Ship Lead Time In Days

Enter the number of days that it normally takes to deliver goods to the customer site. The system will accept blank (none) or a positive value.

Ship Only On Working Days

This indicator controls whether despatches can take place only on a defined working day in the calendar or on any day. Enter one of the following:

0 - Despatch on any day.

1 - Despatch only on a working day.

Calendar Code

Enter the default calendar for the customer's requirement dates. This field is mandatory.

Despatch Profile

Enter a valid despatch profile.

Or Enter A

Stockroom

Enter a valid stockroom from which goods will be sourced/allocated during consignment build.

Invoice No Policy

Enter one of the following invoice number policies:

'01' - One invoice per Consignment (this is the default).

'02' - One invoice per Contract/Consignment.

'03' - One invoice per RAN/Contract/Consignment.

'04' - OE Invoice Consolidation level.

Send Cumulative Totals

This field indicates how cumulative totals are dealt with. This field is optional.

'00' - None sent.

'01' - Cumulative inclusive of this Advanced Shipment Notification.

'02' - Cumulative exclusive of the Advanced Shipment Notification.

Consignment Stockroom

Enter a stockroom code when the customer receives consignment stock. Only one consignment stockroom code can be assigned to each Customer/ Delivery sequence against each contract.

Customer's Supplier Code

Enter the code/reference the Customer uses to identify the supplying company. This field is optional.



Press **Enter** to re-validate the screen. When Create Pack Details or Transmit ASNs is set to 1, the Customer and Defaults ASN and Pack Details screen is displayed.

Functions:

F8

This saves any changes made up to this point. You **MUST** set up the data in all associated customer default screens when you first set up a customer.

A successful **F8=Update** will return to the Customer Selection screen.

Customer Defaults ASN and Pack Details Screen



Press **Enter** from the Customer Contract Defaults screen. This screen is only displayed when Create Pack Details or Transmit ASNs is set to 1 on the Customer Contract Defaults screen.

AS030	Z1 - GB Demonstration Company	User GBJBANB1	9/03/98 17:03:43
Advanced Shipping Customer Defaults - ASN & Pack Details			
Customer ... AUTOCUS1 000 Automotive customer eg ROVER			
Consignee ..?. <u>JBA AUTOMOTIVE</u>		Carrier code.....?. _____	
Final Deliv.?. _____		Freight forwarder.?. _____	
Add.Dest....?. _____		Vehicle capacity.... _____	
Consignee country.....?. _____			
Mode of transport.....?. <u>3</u>		Road	
Volume UOM?. <u>M3</u>		Cubic metre	
Print cums code (0/1/2)... <u>0</u>		Do not print cums	
Default pack type.....?. <u>BOX</u>		Small Box	
Default pallet type.....?. <u>PAL</u>		Euro Pallet #1	
Pack label format.....?. <u>C01</u>		Pack:Standard (Odette	
Pallet label format.....?. <u>P01</u>		Pallet:Single Item (Odette	
No. of labels per pack.... <u>1</u>		No. of labels per pallet..... <u>2</u>	
Complete layers..... <u>0</u> (0/1)		Safety critical flag..... <u>0</u> (0/1)	
Odd packs <u>0</u> (0/1)		Containers on invoice..... <u>0</u> (0/1)	
Transmit ANSI X12 856s..... <u>0</u> (0/1)			
Default ASN map sequence & 856 hierarchical levels..?. _____			
F3=Exit F4=Prompt F8=Update F12=Previous F14=ASN Map Seqs & Hierarchies			
F21=Additional address codes F22=Additional ASN Defaults			

Fields:

Consignee

Enter the customer's internal reference for the final delivery point. This field is mandatory only if Transmit ASNs is set to 1.

Carrier Code

Enter the carrier code.

Final Delivery

Enter the final delivery point code, gate number or dock number.

Freight Forwarder

Enter the freight forwarder code.

Add Dest

Enter an additional destination number, or assembly line number as required.

Vehicle Capacity

Enter the vehicle capacity in Volume Unit Of Measurement.

Consignee Country

Enter the consignee country code.

Mode Of Transport

Enter the mode of transport. This field is mandatory.

Volume UOM

Enter the cube unit of measure to be used for calculating volume.

Print Cums Code

Enter the print cumulative code:

- 0 - Do not print cumulative.
- 1 - Print cumulative including this shipment.
- 2 - Print cumulative excluding this shipment.

Default Pack Type

Enter the default pack type.

If you do not enter values in the Pack Label Format field and No Of Labels Per Pack field, and you are using shipping labels, then the system will find defaults for these values.

Default Pallet Type

Enter the default pallet type.

If you do not enter values in the Pallet Label Format field and No Of Labels Per Pallet field, and you are using shipping labels, then the system will find defaults for these values.

Pack Label Format

Enter the pack label format which you want to use as a default.

You can only use this field for detailed packaging if you have the Document Processing module attached and active for this company, and this format must be set up in that module.

If you enter a pack label format you must also enter a value in the No Of Labels Per Pack field.

Pallet Label Format

Enter the pallet label format which you want to use as a default.

You can only use this field for detailed packaging if you have the Document Processing module attached and active for this company, and this format must be set up in that module.

If you enter a pallet label format you must also enter a value in the No Of Labels Per Pallet field.

No Of Labels Per Pack

Enter a value between 1 and 999 for the quantity of labels per pack to be printed.

No Of Labels Per Pallet

Enter a value between 1 and 999 for the quantity of labels per pallet to be printed.

Complete Layers

This field indicates whether the pallet layers have to be complete or not. Dummy packs will be created if required.

0 - Pallet Layers do not have to be complete. This is the default.

1 - Pallet Layers must be complete.

Safety Critical Flag

0 - The item is not safety critical.

1 - The item is safety critical.

Odd Packs

This is the odd packs indicator. This indicator determines if individual packs can be shipped.

0 - All packs must be shipped on a pallet. This may result with the generation of dummy packs in order to satisfy the complete or minimum layer flags. This is the default.

1 - Odd packs can be shipped.

Containers On Invoice

This determines whether retainable containers appear on the invoice as line items.

0 - They should not appear.

1 - They should appear.

Transmit ANS1X12 856s

This field indicates whether 856 ASNs are transmitted. The following options are available:

0 - No. The system will continue to send European ASNs.

1 - Yes. The system will send 856 ASNs.

Default ASN Map Sequence & 856 Hierarchical Levels

Enter a sequence number. The system displays the default set up on the Company ASN and Pack Details Defaults screen in the Company Profile Maintenance section. The default can be overridden.



Press **Enter** to validate the screen.

Functions:

F8

This saves any changes made up to this point and returns to the customer selection screen.

F14

This displays the ASN Map and Sequences Hierarchies window which allows you to add and amend hierarchical options.

F21

This displays the Additional Address Codes window which allows additional address codes to be associated with the customer.

F22

This displays the Additional ASN Defaults window which allows you to maintain ASN default fields.

ASN Map And Sequences Hierarchies Window (F14)

This screen allows you to add and amend hierarchical options. The default sequence of '00' must be created on the Company ASN & Pack Details Defaults screen in the Company Profile Maintenance option in order for the system to send 856 ASNs correctly.



Select **F14=ASN Map Seq & Hierarchies** on the Customer Defaults ASN & Pack Details screen to display the ASN Map Sequences And Hierarchies window.

```
AS030                                Version 3 Demonstration Company   User QAUT01   15/07/97
                                      12:04:00

Advanced Shipping Customer Defaults - ASN & Pack Details
Customer ... CG01      000      Automotive customer

Consignee ...?. CGEE01      Carrier code.....?. CARR01
Final
Add.De      ASN Map Sequences and Hierarchies
Consign
Mode o      Sel Seq? ASN Map Sequence Description      Hierarchy?
Volume
Print       -   00      default                          S I O I P
Default     -   01      alternative                      S I O P I
Default     -   -
Pack l      -   -
Pallet
No. of      1=Select  4=Delete
Comple      F4=Prompt F6=Add  F12=Previous      .. 0 (0/1)
Odd pa      .. 0 (0/1)
Transmit ANSIX12 856s..... 1 (0/1)
Default ASN map sequence & 856 hierarchical levels...?. _ S T O I P

F3=Exit  F4=Prompt  F8=Update  F12=Previous  F14=ASN Map Seqs & Hierarchies
F21=Additional address codes
14-12      S2      MK      KS      IM      II  KENB20A  PE9106S2
```

Fields:

Sel

Select. The following options are available:

- 1 - Select. Selects a hierarchy option.
- 4 - Delete. Deletes a hierarchy option.

Seq

Sequence. Enter the sequence number to be associated with the hierarchy option.

ASN Map and Sequence Description

This is a free field, enter the description.

Hierarchy

Enter the hierarchy agreed with the customer. Levels T, O, I, P can be arranged in any order.

Functions:

F6

Add. This displays blank record lines in the window to allow you to add more data.



Press **Enter** to validate the selection and return to the Customer Defaults ASN And Pack Details Screen

This is an additional destination code number displayed from the previous screen.

Type Code

Enter the name and address type code for the specific entry you want to make.

Address Code

Enter the address code for the entry you want to make.



Warning: You cannot have more than one of each type code. If you enter a type code you must also enter an address code.



These values are maintained to allow the relevant details to be captured during the creation of the Advanced Shipment Notification.



Press **F8=Update** to save the details.

Additional ASN Defaults Window (F22)



Select **F22=Additional ASN Defaults** from the ASN & Pack Details screen to display the Additional ASN Defaults window.

```
AS030          Z1 - GB Demonstration Company   User GBJBACHG  16/10/97
                                           11:53:56

Advanced Shipping Customer Defaults - ASN & Pack Details
Customer ... ABC01   000   ABC Holiday Shop Ltd

Consignee ..?. EORDDAV          Carrier code.....?. BL1
Final Deliv.?.              Freight forwarder.?.
Add.Dest....?.              Vehicle capacity...
Consignee country.....?.
Mode of transport.....?.
Volume UOM ..... M3          Cubic metre

Additional ASN Defaults
Transmission No. Last Used... 0
Transport No. Last Used..... 0
Freight Payment (ICMM) term.?.
Means of Transport Detailed.?.

F4=Prompt  F12=Previous
Default ASN map sequence & 856 hierarchical levels..?. 00 S

F3=Exit  F4=Prompt  F8=Update  F12=Previous  F14=ASN Map Seqs & Hierarchies
F21=Additional address codes  F22=Additional ASN Defaults

14-35  SA  AW  KS  CL  IR  DR  II  EDN400A  KB  PET178S1
```

Fields:

Transmission No. Last Used

This displays the last used transmission number.

Transport No. Last Used

This displays the last used transport number.

Freight Payment (ICCM) Term

Enter the freight payment term code which identifies who pays the freight. This field is mandatory.

Means of Transport Detailed

Enter the means of transport code which is used to indicated detailed transport methods, for example Road Freight by Carrier Transport. This field is mandatory.



Press **Enter** to display the Customer Defaults ASN and Pack Details screen.

Contracts Maintenance

1... **2/ADM**

Use this option to create the individual contract requirements for Advanced Shipping.

Any contracts must first exist in Advanced Customer Scheduling.

Before you can add a contract you must set up your customer and delivery point defaults in the Customer/Delivery Point Defaults option. This provides many of the defaults for this option.

Contract Maintenance Screen



There are two ways of entering this option:

Select Contracts Maintenance from the menu to display the Contract Maintenance screen.

Select **F8=Update** on the final screen of the Advanced Customer Scheduling Contract Maintenance option, which will automatically lead into this option.

AS020	Z1 - GB Demonstration Company	User GBJBANB1	29/05/98
			10:59:59
Advanced Shipping Contract Maintenance			
Customer	_____		(*=Wildcard)
Item	_____		(*=Wildcard)
Customer part.....	_____		(*=Wildcard)
Item model year.....	_____		
OR			
Contract number.....	_____		
F3=Exit F4=Prompt F10=Additional Search			
MA	a		05/024

Fields:

Customer

Enter a customer code or ? to display a Customer Scan Window. An incomplete customer name or number can be entered to search for a contract. This window will only present customers that are registered with the Advanced Customer Scheduling/Advanced Customer Shipping products.

Item

Enter an item code or ? to display an Item Scan Window. An incomplete item name or number can be entered to search for a contract. This window will only present items that are registered with the Advanced Customer Scheduling/Advanced Customer Shipping products.

Customer Part

Enter the customer part number as part of your contract search criteria.

Item Model Year

Enter the item model / year as part of your contract search criteria.

OR

Contract Number

If a valid contract number is entered, then the program will jump to the next screen without displaying the Contract Scan Selection Screen..

If the contract number is not known, enter a blank in this field to display a Contract Scan Selection window. Entries made in the Customer, Item, Customer Part and Item Model Year fields can be used to narrow down the list of contracts displayed.

Functions:

F10=Additional Search

Will display the Additional Contract Characteristics Panel.

Contract Search Selector Screen



Enter a blank in the Contract Number Field in the Advanced Shipping Contract Maintenance Screen to display the Contract Search Selector Screen.

AC717	Z1 - GB Demonstration Company	USER GBJBANB1	15/06/98 11:31:50
Contract Scan			
Sel Customer/Del Item	Contract No.	Start Date	End Date Customer Order Number Model Yr
- ABC01	000	BRAKES	
- ABC01	000	BUMPER	-
- ABC01	000	CARBODY	
- ACTEST	001	ACITEM1	
- ACTEST	001	AC001	
- ACTEST	001	AC001	
- ACTEST	001	AC001	
- ACTEST	001	AC001	
- ACTEST	001	AC001	
- ACTEST	001	AC001	
- ACTEST	001	AC001	
- ACTEST	001	AC001	
- ACTEST	001	AC001	
- ACTEST1	001	ACITEM1	
			More...
1=Select 2=Enquiry			
F10=Additional Search F12=Previous F14=Fold/Drop			
a			08/032

Fields:

Selecting a Contract

Enter 1=Select beside the contract selected.

Functions:

F10=Additional Search

Will display the Additional Contract Characteristics Panel.

Additional Contract Characteristics Panel (F10)

 Select **F10 = Additional Search** on the Advanced Shipping Contract Maintenance Screen.

AC717 Z1 - GB Demonstration Company USER GBJBANB1 28/05/98
09:53:14

Additional Contract Characteristics

Customer.....?.

Item.....?.

Customer Part.....

Item Model Year.....

Internal Sales Admin.?.

Customer Order Number..

Contact Name.....

Article Status.....?.

Final Delivery Point.?.

EDI Link Field 1.....

(*=Wildcard)

(*=Wildcard)

(*=Wildcard)

(*=Wildcard)

(*=Wildcard)

(*=Wildcard)

(*=Wildcard)

(*=Wildcard)

F4=Prompt F5=Refresh F12=Previous

MA

a

10/026

Fields:

Selection Criteria Fields

Search criteria selected in the initial Schedule Enquiry Selection Screen will be displayed on this screen. Search criteria fields can be changed on this panel without having to go back to the previous screen.

Functions:

F5=Refresh

Will restore any field that you have changed.

 Press **Enter** to continue.

Contract Defaults Screen

This screen allows you to enter the specific Contract processing parameters. The defaults established at Company and Customer level must be presented but may be overridden as required.



Press **Enter** from the Contract Maintenance screen to display the Contract Defaults screen.

```
AS025          Distribution V3 -> V3 Financials    User GBJBAPH2    16/02/96
                                                    14:33:23

Advanced Shipping Contract Defaults                ** Active **
Customer.... NH001      000      Northern Motor Spares Limited   Contract AR00001
Item..... NHAC1              000 A-POST FNSHR LH (LHD)
Contract quantity UOM..... EA      Single of.....*

Sales administrator code.?. SA1      SALES ADMINISTRATOR 1
Country of origin.....?. UK        the UK

Allow zero price..... 0      (0/1)
Pack rounding..... 0      (0/1)   Pack rounding %..... _

Ship lead time in days..... 2              Ship only on working days.. 1 (0/1)
Consignment stockroom....?. _
Calendar code.....?. CA
Despatch profile.....?. _
OR
Stockroom.....?. 01

-----
F3=Exit  F4=Prompt  F8=Update  F12=Previous

00-30    SA      MW      KS      IM      II  KENB20A  PET087S1
```

Fields:

Customer

This is the customer code and description which is displayed from the previous screen.

Item

This is the item code and description which is displayed from the previous screen.

Contract Quantity UOM

This is the contract quantity and unit of measure taken from the database files by the system.

Sales Administrator Code

Enter a code to enable contracts to be grouped together for review purposes. Use the F4 prompt to select an appropriate code from the Descriptions file type SACD.

Country Of Origin

Enter the code for the country of origin of the goods. This is used in Advanced Shipment Notification processing. This value will default onto the contract header record. Use the F4 key to select from the Descriptions file type CTRY.

Allow Zero Pricing

This indicates if a zero price is valid for the Contract. If so a valid zero price line must be established on the price profile.

0 - A zero price cannot be entered. This is the default.

1 - A zero price can be entered.

Pack Rounding

This is the pack rounding indicator.

0 - Pack rounding is not required. This is the default.

1 - Pack rounding is required.

Pack Rounding %

This is the pack rounding percentage used in pack rounding calculations. Enter a suitable percentage from 0 - '99'.



Note: The pack rounding percentage can only be greater than zero if the pack rounding flag is set to 1.

Example: The maximum items per pack = 100, the pack rounding percentage is 40, and the requirement is for 229. Do you send 2 or three packs?

As $29/100 < 40/100$, 2 packs will be allocated. If the pack rounding percentage had been 20, 3 packs would have been allocated, as $29/100 \geq 20/100$.

A pack rounding percentage of 100 implies you should always round down unless already an exact number of packs, a pack rounding percentage of 0 implies that you always round up unless already an exact number of packs.

Ship Lead Time In Days

Enter the number of days that it normally takes to deliver goods to the customer site. The default is zero. The system will only accept a positive figure.

Ship Only On Working Day

This indicator controls whether despatch shipping can take place only on a defined working day on the calendar, or on any day.

0 - Despatch on any day.

1 - Despatch only on a working day.

Consignment Stockroom

Enter a stockroom when the customer receives consignment stock.

Calendar Code

The default calendar for the customer's requirement dates should be entered. This field is mandatory.

Despatch Profile

Enter a despatch profile which will provide a list of stockrooms from where goods can be sourced during consignment build.

Or

Stockroom

Enter the stockroom from which goods will be sourced during consignment build.



Press **F8=Update** to save any changes and return to the Contract Maintenance screen.

Pack Types

1... **2...** **3/ADM**

Products may be supplied in customer specified packaging, which in turn, may be loaded onto pallets. The ability to define the relationships between customer/item/pack/pallet will support the semi-automatic calculation of the requisite packaging and therefore reduce the time and effort involved in operator entry of the details.

Pack and pallet in their generic terms mean the two outermost shipping containers - for example, this may be boxes in a crate. It is possible that a single container may be used as a 'pack' for one item and a 'pallet' for another. In this case it needs to be set up as both as if it were two different containers.

All weights are considered to be in the unit of measure defined on the Advanced Shipping company profile.

All quantities are considered to be in the contract unit of measurement (which is taken from the Item Master issue unit of measure at contract set-up).

Pack Type Maintenance Screen 1



Select Pack Type from the menu to display the first Pack Type Maintenance screen.

AS060	Z1 - GB Demonstration Company	User GBJBANB1	16/02/98 12:15:48
Advanced Shipping Pack Type Maintenance			
Pack type.....?.. <u>PK1</u>			
F3=Exit F4=Prompt			

Fields:

Pack Type

Enter the pack type that you want to maintain.



Press **Enter** to display the second Pack Type Maintenance screen.

Pack Type Maintenance Screen 2

This screen allows you to define, modify, or delete pack type definitions. A pack type defines any kind of container or packaging used for delivery of an item to a customer, and may be used to calculate consignment weights and volumes.



Press **Enter** from the first Pack Type Maintenance Screen to display the second Pack Type Maintenance Screen.

AS060		Z1 - GB Demonstration Company		User GBJBANB1		16/02/98 12:15:57	
Advanced Shipping Pack Type Maintenance							
Pack type.....		PK1 <u>PACK TYPE #1</u>					
Tare weight.....		<u>10.000</u>					
Capacity weight.....		<u>100.000</u>					
Volume.....		<u>5.000</u>		Volume UoM.....		M3 Cubic metre	
Length.....		<u>2.000</u>		Length UoM.....?		<u>MT</u> Metre	
Depth.....		<u>1.000</u>					
Width.....		<u>1.000</u>					
Number of Labels....		___		Default Label Format?..		___	
Pack cost.....		<u>10.00000</u>					
Deposit value.....		<u>10.00000</u>		Returnable.....		<u>0</u> (0/1)	
Pack supplier....?		___		Item.....?		___	
Comments.....		___					
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F13=856 Container Defaults F23=Language Descriptions							

Fields:

Pack Type

The system will display the pack type code entered on the previous screen. Enter a description for this pack type.

Tare Weight

Enter the tare weight. This is the empty weight of the pack. This field is mandatory.

Capacity Weight

Enter the capacity weight. This is the maximum weight the pack can safely contain.

Volume

Enter the gross volume of the pack. This field is mandatory.

Volume UOM

The volume unit of measurement from the Company defaults is displayed.

Length

Enter the length of the pack. This field is mandatory.

Depth

Enter the depth of the pack. This field is mandatory.

Width

Enter the width of the pack. This field is mandatory.

Length UOM

Enter the Unit of Measurement for the length of the package. This field is mandatory.

Number Of Labels

Enter the number of labels you want to be printed when you decide to print for this pack. If you enter a value in the Default Label Format field, then you must enter a number here.

Default Label Format

Enter the format which you want to use as the default for this pack's labels. If you enter a value in the Number Of Labels field, then you must enter a number here.

Format codes are subdivided into various document types. The document type assigned to shipping labels is 30.

Pack Cost

Optionally enter the cost of the packaging.

Deposit Value

Optionally enter the deposit value if this is a returnable package.

Returnable

This is where you identify whether the pack is returnable.

0 - The pack is non returnable.

1 - The pack is returnable. You must also enter an item number in the item field. The item number must be a valid code from the Inventory Item file.

Pack Supplier

Enter a valid Accounts Payable supplier for the pack supplier. This field is optional.

Item

If the pack is defined in Inventory Management, enter the item reference number. This field is optional, unless the Returnable field is set to 1, in which case it becomes mandatory.

Comments

Enter any free format comments relating to this pack type.



Press **F8=Update** to save this new information to the file.

Functions:

F11

This function key deletes the current pack type definition. You will not be able to delete the pack details if the pack is defined on any customer/item/pack/pallet records.

F13

856 Container Defaults. This brings up the 856 Container Defaults Window.

F23

Language Descriptions. Displays the Multi Lingual Descriptions Maintenance Window.

Multi Lingual Descriptions Maintenance Window (F23)

This window allows you to enter and amend a text in another language.



Select **F23=Language Descriptions** from the second Pack Type Maintenance Screen.

```
A5060      Distribution V3 -> V3 Financials 3F User GBJBA1MS      9/07/96
                                           14:38:19
Advanced Shipping Pack Type Maintenance
Multi-lingual Descriptions Maintenance
Pac Code..... BX1
Description.. ROVER BOX TYPE ROVBX1
Tar
Cap Language (?) Description
Vol      _
Len      _
Dep      _
Wid      _
Pac      _
Dep      _
Pac      _
Com      _
F4=Prompt F8=Update F12=Previous

F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous
F23=Language Descriptions
09-11  SA MW KS IM II KENB20A PET087S1
```

Fields:

Language

Enter the language code you want to maintain.

Description

Enter the descriptive name for the pack type in the entered language.

Pallet Types

1... **2...** 4/ADM

Products may be supplied in customer specified packaging, which in turn may be loaded onto pallets. The ability to define the relationships between customer/item/pack/pallet will support the semi-automatic calculation of the requisite packaging and therefore reduce the time and effort involved in operator entry of the details.

Pack and pallet in their generic terms mean the two outermost shipping containers, for example boxes in a crate. It is possible that a single container may be used as a 'pack' for one item and a 'pallet' for another. In this case it needs to be set up as both, as if it were two different containers.

All weights are considered to be in the unit of measure defined on the Advanced Shipping company profile.

All quantities are considered to be in the contract unit of measurement (which is taken from the Item Master issue unit of measure at contract set-up).

Pallet Type Maintenance Screen 1



Select Pallet Type from the menu to display the Pallet Type Maintenance Screen.

AS065	Z1 - GB Demonstration Company	User GBJBANB1	16/02/98
Advanced Shipping Pallet Type Maintenance			11:30:34
Pallet type.....?.. <u>PL1</u>			
F3=Exit F4=Prompt			

Fields:

Pallet Type

Enter the pallet type that you want to maintain.



Press **Enter** to display the second Pallet Type Maintenance Screen.

Pallet Type Maintenance Screen 2

This screen allows you to define, modify, or delete pallet type definitions. A pallet type defines any kind of container or packaging used for delivery of an item to a customer, and may be used to calculate consignment weights and volumes.



Press **Enter** on the first Pallet Type Maintenance Screen to display the second Pallet Type Maintenance Screen.

AS065	Z1 - GB Demonstration Company	User GBJBANB1	16/02/98 11:30:49
Advanced Shipping Pallet Type Maintenance			
Pallet type PL1 <u>PALLET TYPE #1</u>			
Tare weight.....	<u>5.000</u>		
Capacity weight.....	<u>500.000</u>		
Volume.....	<u>.050</u>	Volume UoM.....	M3 Cubic metre
Length.....	<u>1.000</u>	Length UoM.....?..	<u>MT</u> Metre
Depth.....	<u>.050</u>		
Width.....	<u>5.000</u>		
Number of Labels....	—	Default Label Format?..	—
Pallet cost.....	<u>5.00000</u>	Returnable.....	<u>1</u> (0/1)
Deposit value.....	<u>5.00000</u>	Controlled pallet.....	<u>1</u> (0/1)
Pallet supplier..?..	<u>TDCVEND1</u>	Item.....?..	<u>PL1</u>
Comments.....			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			
F13=856 Container Defaults			

Fields:

Pallet Type

Enter a pallet description of up to 30 characters. This field is mandatory.

Tare Weight

Enter the tare weight. This is the empty weight of the pallet. This field is mandatory.

Capacity Weight

Enter the capacity weight. This is the maximum weight the pallet can safely hold.

Volume

Enter the gross volume of the pallet. This field is mandatory.

Volume UOM

The Volume unit of measurement from the company defaults will be displayed.

Length

Enter the length of the pallet. This field is mandatory.

Depth

Enter the depth of the pallet. This field is mandatory.

Width

Enter the width of the pallet. This field is mandatory.

Length UOM

Enter the unit of measurement for the length of the pallet. This field is mandatory.

Number Of Labels

Enter the number of labels you want to be printed when you decide to print for this pallet. If you enter a value in the Default Label Format field, then you must enter a number here.

Default Label Format

Enter the format which you want to use as the default for this pallet's labels. If you enter a value in the Number Of Labels field, then you must enter a number here.

If you are operating in simple packaging mode, then this field is optional, and the format you enter must exist in the Inventory descriptions.

If you are operating in detailed packaging mode, and the AS Shipping Labels Enabled In Document Processing field on the Company ASN And Pack Details Defaults Screen is set to on, then the format you enter must exist in the Document Processing module.

Pallet Cost

Optionally enter the cost price of the pallet.

Returnable

This is where you identify if the pallet is returnable.

0 - The pallet is non returnable. This is the default.

1 - The pallet is returnable. You must also enter an item number in the item field.

Deposit Value

Enter the deposit value of the pallet if this is a returnable item.

Controlled Pallet

This flag determines whether the pallet is controlled.

1 - A controlled pallet.

0 - The pallet is not to be controlled.

Pallet Supplier

Enter a valid Accounts Payable supplier for the pallet supplier. This field is optional.

Item

If the pallet is defined in Inventory Management, enter the item reference number. This field is optional, unless the returnable field is set to 1, in which case it becomes mandatory.

Comments

Enter any free format comments relating to this pallet type.



Press **F8=Update** to update the files with the new information.

Functions:

F11

Delete. This function key deletes the current pallet type definition. You will not be able to delete the pallet details if the pallet is defined on any customer/item/pack/pallet records.

F13

Container Defaults. This brings up the 856 Container Defaults Window.

856 Container Defaults Window (F13)



Select **F13=Container Defaults** on the Pallet Type Maintenance Screen 2 to see the 856 Container Defaults Window.

When you take the ANSI12 856 Maintenance And Send option and maintain additional details from the Additional 856 Details Window, you can go to many different screens. These screens can display defaults you set up here, on the 856 Container Defaults Window.

These defaults record the ways in which different companies refer to a single container. So each container has the reference given to it by its manufacturer, the reference used by shippers, and perhaps another used by carriers. If you enter them here, all the references will be recorded on the 856 message, so all the relevant handlers recognise the container.

AS065	Z1 - GB Demonstration Company	User GBJBANB1	16/02/98 11:30:49																		
Advanced Shipping Pallet Type Maintenance																					
Pallet type PL1 <u>PALLET TYPE #1</u>																					
<table><tr><td>UCC 128 Packaging Type Code.....?</td><td><u>1</u></td><td>Packs</td></tr><tr><td>UCC 128 Manufacturer Code.....</td><td><u>123</u></td><td></td></tr><tr><td>UCC Container Code.....</td><td></td><td></td></tr><tr><td>Shipper's Container Code.....</td><td></td><td></td></tr><tr><td>Carrier's Container Code.....</td><td></td><td></td></tr><tr><td>Pallet Exchange Code.....?</td><td><u>-</u></td><td></td></tr></table>				UCC 128 Packaging Type Code.....?	<u>1</u>	Packs	UCC 128 Manufacturer Code.....	<u>123</u>		UCC Container Code.....			Shipper's Container Code.....			Carrier's Container Code.....			Pallet Exchange Code.....?	<u>-</u>	
UCC 128 Packaging Type Code.....?	<u>1</u>	Packs																			
UCC 128 Manufacturer Code.....	<u>123</u>																				
UCC Container Code.....																					
Shipper's Container Code.....																					
Carrier's Container Code.....																					
Pallet Exchange Code.....?	<u>-</u>																				
F4=Prompt F12=Previous																					
Deposit value.....	<u>5.00000</u>	Controlled pallet.....	<u>1</u> (0/1)																		
Pallet supplier...?	<u>TDVEND1</u>	Item.....?	<u>PL1</u>																		
Comments.....																					
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F13=856 Container Defaults																					

Fields:

UCC 128 Packaging Type Code

Enter the relevant UCC (Universal Container Code) to indicate the range of pack numbers you wish to use.

UCC 128 Manufacturer Code

Enter the code which indicates the manufacturer of the container.

UCC Container Code

Enter the code which indicates the container itself.

Shipper's Container Code

Enter the code which the shipper uses when referring to the container.

Carrier's Container Code

Enter the code which the carrier uses when referring to the container.

Pallet Exchange Code

Enter the code indicating whether the container should be returned for reuse or not. These codes are set up in Inventory descriptions, under the major type PAEC.



When you have completed these fields, press **Enter** to store and return to the previous screen. The information is not saved until you select **F8=Update**.

Customer/Item/Pack/Pallet Maintenance



5/ADM

This option allows you to uniquely define the relationship between an item, and its pack type and pallet type for a specific customer. Only one such customer/item record may exist to enable automatic calculation of packing information during Advanced Shipment Notification processing.



Tip: When a relationship is first defined, as many values as possible are defaulted automatically from the customer ASN/Pack defaults. See Customer/Delivery Point Defaults.

Customer/Item/Pack/Pallet Maintenance Screen 1



Select the Customer/Item/Pack/Pallet Maintenance option from the menu to see the Customer/Item/Pack/Pallet Maintenance Screen 1.

```
AS070          Distribution V3 -> V3 Financials    User GBJBAPH2    16/02/96
                                                    14:38:37

Customer/Item/Pack/Pallet Maintenance

Customer ..... ? █ _____
Item ..... ? _____

F3=Exit  F4=Prompt

05-20    SP    MW    KS    IM    II    KENB20A    PET087S1
```

Fields:

Customer

Enter the customer for whom you want to set up packs and pallets.

Item

Enter the item for which you want to set up packs and pallets.



Press **Enter** to display the second Customer/Item/Pack/Pallet Maintenance Screen.

Maintain Customer/Item/Pack/Pallet Maintenance Screen 2



Press **Enter** on the first Maintain
Customer/Item/Pack/Pallet Maintenance Screen
to display the second Maintain
Customer/Item/Pack/Pallet Maintenance Screen.

AS070	Z1 - GB Demonstration Company	User GBJBACHG	20/10/97 14:30:16
Customer/Item/Pack/Pallet Maintenance			
Customer	TMM2	000	TESSA PRODUCTS
Item	1BT		PM/V3-0706 : ALBACORE
Pack type.....?	BOX	Small Box	
Pallet type.....?	PAL	Euro Pallet #1	
Customer item ref.....			
Customer pack ref.....			
Customer pallet ref....			
Pallet stackability....	10	Pack material item....?	
Pack label format...?		Maximum packs per layer..	1
No. of labels/pack....		Minimum layers.....	1
Pallet label format.?		Maximum layers.....	1
No. of labels/pallet...		Complete layers.....	0 (0/1)
Safety critical flag... 0	(0/1)	Odd packs.....	0 (0/1)
Max. items/pack.....	50	Add pack + pallet volume.	0 (0/1)
Comments.....			
F3=Exit F4=Prompt F8=Update F10=Extend F11=Delete F12=Previous			
7-26 SA NW KS CL IA DA II EDN400A KB PET178S1			

Fields:

Customer

This is the customer selected on the previous screen.

Item

This is the item selected on the previous screen.

Pack Type

Enter the pack type. This field is mandatory. If you do not enter any values in the Pack Label Format field and the No Of Labels/Pack field, then default values will be used.



If you want to use only a single level of packaging for this item, simply enter the same pack type and pallet type.

Pallet Type

Enter the pallet type. This field is mandatory. If you do not enter any values in the Pallet Label Format field and the No Of Labels/Pallet field, then default values will be used.



If you want to use only a single level of packaging for this item, simply enter the same

pack type and pallet type.

Customer Item Ref

Enter the customer's item reference. This field is optional.

Customer Pack Ref

Enter the reference by which the customer identifies a pack. This value is optional.

Customer Pallet Ref

Enter the reference by which the customer identifies a pallet. This value is optional.

Pallet Stackability

Enter the maximum number of pallets which can be stacked one on top of the other. This must be greater than zero. This field is mandatory.

Pack Material Item

Enter an item number of an additional piece of packaging material, for example a divider. This field is optional.

Pack Label Format

Enter the pack label format. This must be set up for the company. If you enter a format here, you must also enter a value in the No Of Labels/Pack field.

This field is optional if you are not printing shipping labels.

You can only use this field for detailed packaging if you have the Document Processing module attached and active for this company, and this format must be set up in that module.

Maximum Packs Per Layer

Enter the maximum number of packs required to complete a layer on the specified pallet.

If you are using only a single level of packaging for this item (that is, the pack type and pallet type are the same), then this field must be set to 1.

No Of Labels/Pack

Enter the quantity of labels to be printed per pack. This can be zero.

This field is optional if you are not printing shipping labels.

Minimum Layers

Enter the minimum number of layers which have to be on a pallet. This number must be between 1 and less than or equal to the maximum number of layers. This field is mandatory.

Pallet Label Format

Enter the pallet label format. This must be set up for the company. If you enter a format here, you must also enter a value in the No Of Labels/Pallet field.

This field is optional if you are not printing shipping labels.

You can only use this field for detailed packaging if you have the Document Processing module attached and active for this company, and this format must be set up in that module.

Maximum Layers

Enter the maximum number of layers allowed on a pallet. The default is 1. This must be greater than or equal to the minimum number of layers. This field is mandatory.

If you are using only a single level of packaging for this item (that is, the pack type and pallet type are the same), then this field must be set to 1.

No Of Labels/Pallet

Enter the quantity of labels to be printed per pallet. This can be zero.

If you are using only a single level of packaging for this item (that is, the pack type and pallet type are the same), then this field must be set to 0.

This field is optional if you are not printing shipping labels.

Complete Layers

0 - Layers on the pallet need not be complete.

1 - All layers on a pallet must be complete.

This field is mandatory.

Safety Critical Flag

0 - The item is not safety critical. This is the default.

1 - The item is safety critical. This can only be set if the pack and/or pallet label format is entered.

Odd Packs

This field determines if individual packs may be shipped. This field is mandatory.

0 - Odd packs must be made up to complete and/or minimum layers by the inclusion of empty packs.

1 - Individual packs may be shipped.

Maximum Items/Pack

Enter the maximum number of this item in this pack. This number must be greater than zero. This field is mandatory.



Note: If pack rounding is switched on for a particular contract, this quantity will be used in the pack rounding calculation.

Add Pack And Pallet Volume

1 - Combine the volumes when calculating consignment volume.

0 - Do not combine the volumes when calculating consignment volume.

Comments

This is a free format field. Enter any comments required for this particular item/pack/pallet relationship.



Press **F8=Update** to update the files. The Additional Cust/Item/Pack Data Window is displayed when you are setting up an customer/item/pack relationship for the first time. The first Customer/Item/Pack Pallet Maintenance Screen is displayed when the customer/item/pack relationship already exists.

Functions:

F10

Extend. Displays the Additional Cust/Item/Pack Data Window which allows you to amend any additional customer/item/pack relationship data. This function key is only displayed when you are maintaining an existing customer/item/pack relationship.

Additional Cust/Item/Pack Data Window (F8/F10)

-  Select **F8=Update** on the second Customer/Item/Pack/Pallet Maintenance Screen when setting up a Customer/Item/Pack relationship for the first time to display the Cust/Item/Pack Data Window.
-  Select **F10=Extend** on the second Customer/Item/Pack/Pallet Maintenance Screen when amending Customer/Item/Pack relationship details to display the Cust/Item/Pack Data Window.

```
AS070      Z1 - GB Demonstration Company   User GBJBACHG   20/10/97
                                         14:33:19

Customer/Item/Pack/Pallet Maintenance

C  Additional Cust/Item/Pack data
I
P  Customs Preference Status .. 0
P  Returnable packing code..... 0 (0=No, 1=Pallet, 2=Pack, 3=Both)
C  Pack type Owner..... 0 (0=customer, 1=Supplier, 2=3rd Party)
C  Pallet type Owner..... 0 (0=customer, 1=Supplier, 2=3rd Party)
C  Enter=Continue F12=Previous
P
P  Pack label format...?.. ___ Maximum packs per layer.. 1
P  No. of labels/pack.... ___ Minimum layers..... 1
C  Pallet label format...?.. ___ Maximum layers..... 1
C  No. of labels/pallet... ___ Complete layers..... 0 (0/1)
C  Safety critical flag... 0 (0/1) Odd packs..... 0 (0/1)
P  Max. items/pack..... 50 Add pack + pallet volume. 0 (0/1)
C  Comments.....

F3=Exit F4=Prompt F8=Update F10=Extend F11=Delete F12=Previous

7-35  S0  HW  KS  CL  IH  DR  II  EDN4000  KB  PET178S1
```

Fields:

Customs Preference Status

Enter the customs preference status code.

Returnable Packaging

This indicates what packaging is returnable. Enter one of the following:

- 0 - No. Packaging is non returnable.
- 1 - Pallet. Only the pallet is returnable.
- 2 - Pack. Only the pack is returnable.
- 3- Both. Pallet and pack are returnable.

Pallet Owner

This indicates who owns the pallet. Enter one of the following:

- 0 - Supplier.

1 - Customer.

2 - 3rd Party.

Pack Owner

This indicates who owns the pack. Enter one of the following:

0 - Supplier.

1 - Customer.

2 - 3rd Party.



Press **Enter** to display the second
Customer/Item/Pack/Pallet Maintenance Screen.

Assigning Calendars to Stockrooms



6/ADM

This option allows you to assign a calendar to a stockroom. Select the Assign Calendars to Stockroom Option from the menu to display a list of stockrooms in stockroom code sequence.

Assign Calendars to Stockrooms Screen 1



Select the Assign Calendars to Stockroom option on the menu to display the first Assign Calendars to Stockrooms Screen.

AS055 Distribution V3 -> V3 Financials User GBJBAPH2 16/02/96
14:23:42

Assign Calendars to Stockrooms

Sel	S/R	Description	Calendar Code
█	W1	Warehousing Stockroom	* NOT ASSIGNED *
-	W2	Warehousing Stockroom 2	* NOT ASSIGNED *
-	XM	Max's other stockroom	* NOT ASSIGNED *
-	XX	Name	* NOT ASSIGNED *
-	YY	YEAR-END STOCKROOM	* NOT ASSIGNED *
-	01	Main stockroom	CA
-	02	Secondary stockroom	CA
-	03	Area Stockroom 01	CA
-	04	Area Stockroom 02	CA
-	05	Regional Stockroom 02	CA
-	06	Area Stockroom 03	CA
-	07	Depot Seven	CA

1=Select
F3=Exit

07-03 **SE** MW **KS** IM II KENB20A PET007S1

Fields:

Select

Enter 1 - to select a stockroom for assignment or amendment.

Calendar Code

Displays the current stockroom/calendar code assignment.



Note: You may assign a valid calendar code to a non assigned stockroom or select an already assigned stockroom for amendment.



Press **Enter** to display the second Assign Calendars to Stockrooms Screen.

Assign Calendars to Stockrooms Screen 2

This screen allows you to assign a valid calendar code to a stockroom.



Press **Enter** from the first Assign Calendars to Stockrooms Screen to display the second Assign Calendars to Stockrooms Screen.

```
AS055          Distribution V3 -> V3 Financials    User GBJBAPH2    16/02/96
                                                    14:23:42

Assign Calendars to Stockrooms

Stockroom..... W2  Warehousing Stockroom 2

Calendar code....?... █

F3=Exit  F4=Prompt  F8=Update                      F12=Previous
07-23    SF        MW        KS        IM        II  KENB20A  PET007S1
```

Fields:

Stockroom

This field displays the stockroom you have chosen for assignment or amendment.

Calendar Code

Enter the Calendar Code to assign a Calendar to a stockroom.



Press **F8=Update** to update the file.

ASN Names and Addresses Maintenance

1... 7/ADM **2...**

The transmission of Advanced Shipment Notification data may demand, depending on customer and/or EDI message standard, the inclusion of additional name and address information, either coded or in full. The system has been defined in a flexible manner to support the current and future requirements in this area. The emphasis within Advanced Shipping has been to ensure all anticipated business data requirements are stored within the application. The transformation of that business data in to the various EDI Interface file formats is done within the EDI Application Interface functions.

ASN Name and Address Screen 1



Select the ASN Names and Addresses option from the menu to display the first ASN Name and Address Maintenance Screen.

AS075	Distribution V3 -> V3 Financials	User GBJBAPH2	16/02/96
Name and Address Maintenance			14:43:02
Type code.....?.. _____			
Address code.....?.. _____			
F3=Exit F4=Prompt			
05-23	SA	MW	KS IM II KENB20A PET007S1

Fields:

Type Code

Enter an address type code.

Address Code

Enter an address code.



Press **Enter** to display the second ASN Name and Address Maintenance Screen.

Name and Address Maintenance Details Screen

The contents of this screen identify alternative addresses for the customer. An internal ID field allows for an additional code which identifies the address type by some alternative code, for example one which has been mutually agreed between the consignee and consignor.



Press **Enter** from the first ASN Name and Address Maintenance Screen to display the second ASN Name and Address Maintenance Screen.

AS075		Distribution V3 -> V3 Financials 3F User GBJBA1MS		9/07/96	
				14:47:12	
Name and Address Maintenance					
Type code.....	CARR	Transport Carrier Company			
Address code.....	CARR01				
Name.....	CARRIER 01				
Address line 1.....	15 High Street				
Address line 2.....	Freemantle Green				
Address line 3.....	Dingle Wood				
Address line 4.....	Oldsbury				
Address line 5.....	West Midlands				
Post code.....	OL4 9IN				
Telephone number...	0121-555-5555	Extension number...	5555		
Fax number.....	0121-444-4444	Internal ID.....	FJDK		
Telex number.....	023934 4940	Teletext number...	394		
Contact name.....	Mr Fred Brown				
Department code.....	G123				
Comments.....					
F3=Exit F8=Update F11=Delete F12=Previous F23=Language Descriptions					
18-27 SA MW KS IM II KENB20A PET087S1					

Fields:

Type Code

This is the address type code entered on the previous screen.

Address Code

This is the address code entered on the previous screen.

Name

Enter the name. This field is mandatory.

Address Line 1

Enter the first line of the required address. This field is mandatory.

Address Line 2

Enter the second line of the required address.

Address Line 3

Enter the third line of the required address.

Address Line 4

Enter the fourth line of the required address.

Post Code

Enter the post code.

Telephone Number

Enter the telephone number required.

Extension Number

Enter the internal extension number required.

Fax Number

Enter the fax number required.

Internal ID

Enter a suitable Internal ID code.

The internal ID field allows for an additional code which identifies the address type by some alternative code, for example one which has been mutually agreed between the consignee and consignor.

Telex Number

Enter the required telex number.

Teletext Number

Enter the required teletext number.

Contact Name

Enter the contact name as required.

Department Code

Enter the department code for the contact as required.

Comments

This is a free format field. Enter any required comments.



Press **F8=Update** to update the file.

Functions:

F23

Language Descriptions. Displays the Multi-Lingual Descriptions Maintenance Window.


```

AS075                               Distribution V3 -> V3 Financials 3F User GBJA1MS    9/07/96
                                         14:47:12

Name and Address Maintenance
Multi-lingual Descriptions Maintenance
Typ  Code..... CARR      CARR01
Add  Description.. CARRIER 01
Nam
Add  Language (?)  Description
Add  _____
Add  _____
Add  _____
Add  _____
Pos  _____
Tel  _____
Fax  _____
Tel  _____
Con  _____
Dep  _____
Com  _____

F4=Prompt  F8=Update  F12=Previous

55
DK
4

F3=Exit  F8=Update  F11=Delete  F12=Previous  F23=Language Descriptions

09-11    SA      MW      KS      IM      II  KENB20A  PET08751

```




1-53

Despatch Profile Maintenance



8/ADM

This option allows you to set up standard despatch profiles which are used during the consignment build process to determine where requirements should be sourced. Multiple stockrooms can be specified in the sequence in which sourcing should be attempted. These profiles may then be defined as defaults on the company/customer/contract master files.



Despatch Profile Maintenance Screen (F6)

This screen is displayed in add mode for new despatch profiles, and in amend mode for existing despatch profiles.



Select **F6=Add** from the first Despatch Profile Maintenance Screen to display the Despatch Profile Maintenance Screen in add mode.

```
AS000      Distribution V3 -> V3 Financials      User GJBAPH2      16/02/96
                                                    14:45:18

Despatch Profile Maintenance

Despatch profile.... GBN  Northern britain
Calendar code....?.. CA

      Sequence  Stockroom(?)  Description
      -----  -
      1         01          Main stockroom
      2         03          Area Stockroom 01
      3         02          Secondary stockroom
      4         #P          Plymouth Depot
      5         #1          Redditch
      6         #2          Paris
      7         AB          Andy's Depot
      8         AW          main depot amw
      9         A1          test warehouse a1
      -----  -
                                     +

F3=Exit  F4=Prompt  F8=Update  F11=Delete  F12=Previous

05-29    SF      MW      KS      IM      II  KENB20A  PET007S1
```

Fields:

Despatch Profile

Enter the despatch profile code. This must be unique. Enter a description for the despatch profile.

Calendar Code

Enter the relevant calendar code to attach to this despatch profile code. This is a mandatory field.

Sequence

Enter the sequence number. This can only be a positive integer, you cannot have equal rankings.

Stockroom

Enter the stockroom you want to attach to this despatch profile sequence.



Press **F8=Update** to save the information to the file.

Functions:

F11

This key will delete the selected despatch profile. You cannot delete a despatch profile which is attached to company/customer/contract defaults.

Items



9/ADM

This option allows you to enter default measurements against items that are included in 856 ASNs.



Select Items on the menu to display the first 856 Item Measurements Screen.

856 Item Measurements Screen 1

 Select Items on the menu to display the first 856 Item Measurements Screen.

AS284 Version 3 Demonstration Company User QAAUT01 8/07/97
Advanced Shipping 856 Item Measurements 9:26:30

Item?.

F3=Exit F4=Prompt

05-16   KS IM II EDN400A PET149S2

Fields:

Item

Enter the item number.

 Press **Enter** to display the second 856 Item Measurements.

856 Item Measurements Screen 2

This screen allows you to enter default measurements against items.



Press **Enter** on the first 856 Item Measurements to display the second screen.

AS284	Version 3 Demonstration Company	User QAUT01	8/07/97 14:47:21	
Advanced Shipping 856 Item Measurements				
Item 50001		A Dummy Item		
Sel Group ?	Type ?	Value	Range Min.	Range Max.
_ AG AGE of Goo DE	Depth			
4 = Delete				
F3=Exit F4=Prompt F6=Add F8=Update F9=Pack Type Summary F12=Previous				
08-03	SA	ML	KS	IM II EDN400A PET149S2

Fields:

Item

This is displayed from the previous screen.

Sel

The following option is available:

4 - Delete. Delete an item measurement record.

Group

Enter group code.

Type

Enter type code.

Value

Enter the value applicable to the group and type.

Range Min

Enter the minimum value applicable to the group and type.

Range Max

Enter the maximum value applicable to the group and type.



Select **F8=Update** to update data you have

entered and redisplay the first 856 Item Measurements Screen.

Function

F6

Add. Displays additional blank record lines on the screen to allow you to add further default measurements against items.

F9

Pack Type Summary. Displays the Company Item Defaults Pack Summary Window which allows you to enter pack summary data.

Company Item Defaults Pack Summary Window (F9)

This window allows you to enter pack summary data.



Select **F9=Pack Type Summary** on the second 856 Item Measurements Screen to display the Company Item Defaults Pack Summary Window.

AS284	Version 3 Demonstration Company	User QA AUT01	11/07/97
			9:06:55
Advanced Shipping 856 Item Measurements			
Company Item Defaults - Pack Summary			
Sel Pack ?	Type	Supplier Units Size	UOM ?
- QAB	QA Box	_____7	CA Cases of
4=Delete			
F4=Prompt F6=Add F12=Previous			
-	-	_____	_____
-	-	_____	_____
-	-	_____	_____
4 = Delete			
F3=Exit F4=Prompt F6=Add F8=Update F9=Pack Type Summary F12=Previous			
08-06 SA MK KS IM II KENB20A PED201S2			

Fields:

Sel

Select. The following option is available:

4 - Delete. Deletes an item measurement record.

Pack

Enter the pack code.

Type

The system displays this once the pack code is entered.

Supplier Units Size

Enter the unit size.

UOM

Enter the unit of measurement.



Press **Enter** to validate the data and display the 856 Item Measurements Window.

Functions:

F6

Add. Displays additional blank record lines on the screen to allow you to add further default measurements against items.

Hazardous Materials Class Codes



10/ADM

This option allows you to add and maintain hazardous materials class codes that may be required on an ASNIX12 856 message.



Select Hazardous Materials Class Codes on the menu to display the 856 Hazardous Materials Class Code Maintenance Screen.

Functions:

F6

Add. This function allows you to enter additional hazardous material class codes. The fields are displayed in the Add New Hazardous Materials Class Code Window.