

-
-
-
-
-

Chapter 4

Utilities



Company Profile Maintenance



1/ADU

Advanced Shipping company profile defaults are entered in this option.

The Company ASN & Pack Details Defaults Screen and the Self Billing Parameters Screen are displayed depending upon the input to the Advanced Shipping Company Screen.

Company Profile Maintenance Screen



Select the Company Profile Maintenance option from the menu to display the Company Profile Maintenance Screen.

AS010	GBJBANB1	11/02/98
Company Profile Maintenance		16:32:58
Enter Company code ? <u>Z1</u>		
F3=Exit F4=Prompt		

Fields:

Enter Company Code

Enter the code of the company that you want to maintain.



Press **Enter** to display the Advanced Shipping Company Screen.

Advanced Shipping Company Screen



Press **Enter** from the Company Profile Maintenance Screen to display the Advanced Shipping Company Screen.



*Note: If you are using Advanced Customer Scheduling, then the final **F8=Update** in that company profile automatically leads in to this Advanced Shipping company profile.*

AS025	Z1 - Z1 Sales Company	User GBJBANB1	11/02/98
Advanced Shipping Company			16:34:44
Last consignment reference..... <u>00000353</u>			
Contract Defaults			
Sales administrator code.?. <u>LANCE</u> Lance Escott			
Country of origin.....?. <u> </u>			
Shipping weight UOM.....?. <u>KG</u>		Kilogrammes	
Shipping volume UOM.....?. <u>M3</u>		Cubic metre	
Self billing..... <u>0</u>		(0/1)	
Pack rounding..... <u>0</u>		(0/1)	
Transmit ASNs..... <u>1</u>		(0/1)	
		Pack rounding %..... <u>0</u>	
		Create pack details..... <u>1</u>	(0/1)
		Display qtys as integers.. <u>1</u>	(0/1)
		Ship only on working days.. <u>1</u>	(0/1)
Ship lead time in days..... <u> </u>			
Calendar code.....?. <u>CA</u>			
Despatch profile.....?. <u> </u>			
OR Stockroom.....?. <u>01</u>			
Invoice no. policy.....?. <u>01</u> One Invoice per Consignment			
Send cumulative totals...?. <u>01</u> Cums. inclusive of this ASN			
Lot allocation policy....?. <u>01</u> Manual - During Consign. maint			
F3=Exit F4=Prompt F8=Update F12=Previous			

Fields:

Last Consignment Reference

The system will display the last consignment number used or will default to 00000000 on the first set-up. This field is mandatory.

Sales Administrator Code

Enter a code to enable contracts to be grouped together for review purposes. This will default onto the Customer defaults. The Description file type is SACD. This field is optional.

Country Of Origin

Enter the country of origin of the goods. This field is optional.

Shipping Weight UOM

This shows the company wide weight unit of measure for all shipping weights. This will default to blank, thus forcing an entry on the first time through for each Company. This field is mandatory.

Shipping Volume UOM

This field contains the default unit of measurement code for the volume of the consignment. Optionally enter a valid UOM code. This field is mandatory.

Self Billing

This is the self billing processing indicator. This field is for future use.

0 - Self billing is not required. This is the default.

1 - Self billing is required.

Pack Rounding

This is the pack rounding indicator.

0 - Pack rounding is not required. This is the default.

1 - Pack rounding is required.

Pack Rounding %

This is the pack rounding percentage used in pack rounding calculations. The default is blank. Enter a suitable percentage from 0 - 99.



Note: The pack rounding percentage can only be non blank if the pack rounding flag is set to 1.

Transmit ASNs

This indicator identifies whether Advanced Shipment Notifications will be transmitted via EDI.

0 - ASNs are not to be sent via EDI. This is the default.

1 - ASNs are to sent via EDI.

This field is reserved for future use.

Create Pack Details

This flag indicates whether pack details should be created during confirmation of despatch

0 - The pack details should not be created. This is the default.

1 - The pack details should be created.

Display Qtys As Integers

This is a system wide parameter and applies to Advanced Customer Scheduling and Advanced Shipping.

0 - Quantities are to be shown as decimal values up to 3 decimal places.

1 - Quantities are to be shown as whole numbers only. This is the default.

Ship Only On Working Days

This flag indicates if shipment should only take place on working days identified in the calendar for this company.

0 - Ship at any time.

1 - Only ship on working days.

Ship Lead Time In Days

This flag indicates forecast requirements to be ship lead time adjusted. The default is 0. This flag can only be set to 1 if Ship Lead Time in Days is greater than zero.

Calendar Code

The default calendar for the customers requirement dates should be entered. This field is mandatory.

Despatch Profile

Enter a default despatch profile for consignment building. Either a Despatch Profile or a Stockroom must be entered but not both.

Stockroom

Enter a default stockroom.

Invoice No Policy

Enter the invoice number policy.

'01' - One invoice per Consignment (this is the default).

'02' - One invoice per Contract/Consignment.

'03' - One invoice per RAN/Contract/Consignment.

'04' - OE invoice Consolidation Level.

Send Cumulative Totals

This field indicates how cumulative totals are calculated in the despatching process.

'00' - None sent (this is the default).

'01' - Cumulative inclusive of this Advanced Shipment Notification.

'02' - Cumulative exclusive of the Advanced Shipment Notification.

Lot Allocation Policy

This flag identifies the policy on allocating lot numbers.

'01' - Allocated by the user during consignment maintenance. This is the default.

'02' - Automatically allocated, by Warehousing if appropriate, or during Consignment maintenance.

'03' - Allocated by the user at Confirm Despatch. This option is not available if Create Pack Details is set to 1.



Press **Enter** to revalidate the screen. If the Create Pack Details or Transmit ASNs fields are set to 1, press **Enter** a second time to display the Company ASN & Pack Details Defaults Screen.

Functions:

F8

Update. This saves any changes made up to this point and returns you to the Company Profile Maintenance Screen. You must add data to all the associated company default screens the first time you set up a company.

Company ASN & Pack Details Defaults Screen

This screen is only displayed if either the Create Pack Details field or the Transmit ASNs field is set to 1 on the Advanced Shipping Company Screen.

This screen allows you to enter the advanced shipment notification and pack detail default values.



Press **Enter** from the Advanced Shipping Company Screen to display the Company ASN & Pack Details Defaults Screen.

AS030	Z1 - Z1 Sales Company	User GBJBANB1	11/02/98 16:34:51
Advanced Shipping Company ASN & Pack Details Defaults			
Default pack type.....?	<u>BOX</u>	Small Box	
Default pallet type.....?	<u>PAL</u>	Euro Pallet #1	
Pack label format.....?	<u> </u>		
Pallet label format.....?	<u> </u>		
No. of labels per pack.....	<u> </u>	No. of labels per pallet.....	<u> </u>
Complete layers.....	<u>0</u> (0/1)	Safety critical flag.....	<u>0</u> (0/1)
Transmit ANSI12 856s.....	<u>1</u> (0/1)	UCC manufacturers code.....	<u> </u>
856 hierarchical levels..?	<u>S</u> <u> </u> <u> </u> <u> </u>		
Default packing type code..?.. <u>3</u>			
AS Shipping Labels Enabled			
in Document Processing..... <u>0</u> (0/1)			
F3=Exit F4=Prompt F8=Update F12=Previous			

Fields:

Default Pack Type

Enter the pack type. This field is optional.

Default Pallet Type

Enter the pallet type. This field is optional.

Pack Label Format

The system will display a description which corresponds to the pack type you have chosen. This field is optional.

If you are using simple packaging mode, then the format you enter must exist in the Inventory descriptions.

If you are using detailed packaging mode, then the format you enter must exist in the Document Processing module.

Pallet Label Format

The system will display a description which corresponds to the pallet type you have chosen.

No Of Labels Per Pack

Enter a number between 1 and 999 for the quantity of labels per pack you want to be printed.

No Of Labels Per Pallet

Enter a value between 1 and 999 for the quantity of labels per pallet you want to be printed.

Complete Layers

This field indicates whether pallets are generated with complete layers, which may require dummy packs to be generated.

0 - They do not need to be complete. This is the default.

1 - The layers on a pallet must be full - empty packs will be generated to complete a part full layer.

Safety Critical Flag

0 - Items are not safety critical. This is the default.

1 - Items are safety critical.

Transmit ASNIX12 856s

This field indicates whether ASNIX12 856 ASNs are transmitted. The following options are available:

0 = No. The system will continue to send ASNs.

1 = Yes. The system will send ASNIX12 856 ASNs.

UCC Manufacturers Code

Enter code when UCC 128 container codes must be sent. This field is optional and is used in 856 ASNs if entered.

856 Hierarchical Levels

Enter up to 5 one character codes to indicate the default of the hierarchical level.

A default structure must be set up on this screen in order for 856 ASNs to be transmitted correctly. The default is associated with each consignment and automatically copied down to the customer details as a suggested default. It can be overridden on the Customer Defaults ASN And Pack Details Screen and the Consignment Header Screen.

This option allows you to set up what consignment details to send and in what sequence. The options available are:

S - Shipping. This option is defaulted and fixed to first position.

T - Tare. Pallet details.

O - Order. Order details.

I - Item. Item details.

P - Packing details.



Note: T, O, I and P can be entered in any order or omitted.

Default Packing Type Code

Enter the packing type you want to use as the default for the company. This is used if a pack or pallet type is found not to have a UCC (Universal Container Code) packing type code.

You set up packing type codes in the Inventory Management option Reference Numbers, under the Inventory reference code PALLETPACK. They are one character alphanumeric fields.

These codes are used as prefixes for ranges of label numbers. You might, for example, have one prefix for a particular customer, and another prefix for all other customers.

AS Shipping Labels Enabled In Document Processing

0 - You do not want to produce or print shipping labels.

1 - You want to produce or print shipping labels. You must have the Document Processing module (DY) installed if you wish to produce or print shipping labels. See the Document Processing product information for more details.



Press **Enter** to validate the screen.



Press **F8=Update** to update the entered details onto the Company parameters database.

Calendar Codes Maintenance

1... **2/ADU**

Advanced Shipping requires multiple calendar/year records to be set up. These specify number of periods per year, period names, number of calendar days in each period, start date of the year, normal start day of the week, working week templates, standard holidays and the option of specifying alternative week templates for given date ranges.

Calendar codes are assigned to the company profile, stockroom/despatch profiles and customers/contracts. Validation and prompts on calendar code scans the calendar/year file and ensures that the selected calendar code has at least one calendar/year record. Once calendar codes are assigned, the onus is on you the user to ensure that current corresponding calendar/year records are always set up.

You can either select a calendar to maintain, or set up a new calendar.

If a specific contract is established for customer scheduling then it would be prudent to create the 'next year' calendar as well as the 'this year' calendar. If a calendar is not set up for 'next year' and a schedule is received with 'next year' requirement dates then this schedule will not be accepted as 'current'.

Calendar/Year Maintenance Screen 1



Select Calendar/Year Maintenance from the menu to display the first Calendar/Year Maintenance Screen.

AS045 Distribution V3 -> V3 Financials User GBJBAPH2 16/02/96
14:19:36

Advanced Shipping Calendar/Year Maintenance

Sel	Code	Year	Description	Work days	Yr Start
█	CA	95	CA - CALENDAR - GENERAL USE	261	2/01/95
-	CA	96	GENERAL USE CALENDAR	262	2/01/96

Enter Calendar code: Year: Based on Calendar Profile:

1=Select 6=Print
F3=Exit

07-04 **SE** MW **KS** IM II KENB20A PET007S1

Fields:

Select

- 1 - Select the calendar you want to maintain.
- 6 - Print the calendar profile.

Enter Calendar Code

This field is used when setting up a new calendar. Enter a two digit alpha/numeric calendar code. This field is mandatory.

Year

This field is used when setting up a new calendar. Enter the last two digits of the year. This field is mandatory.

Based On Calendar Profile

This field is used when setting up a new calendar. Enter the calendar code and last two digits of the year for a calendar you want to use as a base for the new one. This field is optional.



Note: When setting up a new calendar, the combination of calendar code and year must be unique. The based on details must exist.

Calendar/Year Maintenance Screen 2



Press Enter from the first Calendar/Year Maintenance Screen to display the second Calendar/Year Maintenance Screen.

AS045		Distribution V3 -> V3 Financials		User	GBJBAPH2	16/02/96																																				
						14:22:37																																				
Advanced Shipping Calendar/Year Maintenance																																										
Calendar Code/Year.....		CA 95 CA - CALENDAR - GENERAL USE																																								
Number of Periods per Year...		12																																								
Normal Start Day of Week.....		1 (1=Monday 7=Sunday)																																								
Start Date of the Year.....		2/01/95																																								
<table border="1"><thead><tr><th>Period Name</th><th>Days</th><th>Period Name</th><th>Days</th><th>Period Name</th><th>Days</th></tr></thead><tbody><tr><td>1. JAN</td><td>31</td><td>2. FEB</td><td>28</td><td>3. MAR</td><td>31</td></tr><tr><td>4. APR</td><td>30</td><td>5. MAY</td><td>31</td><td>6. JUN</td><td>30</td></tr><tr><td>7. JUL</td><td>31</td><td>8. AUG</td><td>31</td><td>9. SEP</td><td>30</td></tr><tr><td>10. OCT</td><td>31</td><td>11. NOV</td><td>30</td><td>12. DEC</td><td>31</td></tr><tr><td>13. _____</td><td>—</td><td></td><td></td><td></td><td></td></tr></tbody></table>							Period Name	Days	Period Name	Days	Period Name	Days	1. JAN	31	2. FEB	28	3. MAR	31	4. APR	30	5. MAY	31	6. JUN	30	7. JUL	31	8. AUG	31	9. SEP	30	10. OCT	31	11. NOV	30	12. DEC	31	13. _____	—				
Period Name	Days	Period Name	Days	Period Name	Days																																					
1. JAN	31	2. FEB	28	3. MAR	31																																					
4. APR	30	5. MAY	31	6. JUN	30																																					
7. JUL	31	8. AUG	31	9. SEP	30																																					
10. OCT	31	11. NOV	30	12. DEC	31																																					
13. _____	—																																									
Standard Week Template																																										
M T W T F S S																																										
D D D D N N (N for non working day or D for delivery/despatch day)																																										
F3=Exit F11=Delete F12=Previous																																										
04-40 S ² MW KS IM II KENB20A PET087S1																																										

Fields:

Calendar Code/Year

This is the two character identifier for the calendar code which you entered on the previous screen. This cannot be changed.

Description

This field is not named on the screen. Enter/amend the description of the calendar details.

Number Of Periods Per Year

Enter the number of periods you want in this calendar year. Up to 13 periods can be specified.

Normal Start Day Of The Week

Enter the day the week starts on:

1 - Monday, 2 - Tuesday, and so on up to 7 - Sunday.

Start Date Of The Year

Enter the calendar date of the first date in this year.

Where the new calendar is based on the old calendar for the previous year, the system will default to the last date associated with the previous Calendar/Year plus 1 day.



Note: A warning will be issued if the chosen start

date implies either a gap or an overlap with the end date of the Calendar/Year.

Period Name

These names can be entered to match any internal reporting procedures you may have.



Note: You cannot enter more periods, than the number of periods per year field.

Days

Enter the number of calendar days on each defined period.



Note: The total number of days in all the periods added together should be in the range 357 - 371.

Standard Week Template

Enter the default working week template.

Enter D=Working Day.

Enter N=Non Working Day.



Note: If assigned to a stockroom D=despatch day. If assigned to a contract D=deliveries.



Press **Enter** to validate the screen.

Functions:

F11

The delete key is only available if maintaining an existing calendar. The system will display a confirmation window prior to deletion. Deletion can only take place if the calendar is not defined to any stockroom, despatch profile, or Company/Calendar/Contract default records.

Calendar/Year Maintenance Screen 3

This screen allows you to tailor the calendar to your customers holiday periods, and to accommodate any alternative weekly templates you wish to use.



Press **Enter** from the second Calendar/Year Maintenance Screen to display the third Calendar/Year Maintenance Screen.

AS045		Distribution V3 -> V3 Financials		User GBJBAPH2		16/02/96 14:22:54	
Advanced Shipping Calendar/Year Maintenance							
Calendar Code CA 95 CA - CALENDAR - GENERAL USE							
HOLIDAYS							
From	To	From	To				
■							
Enter up to five alternative week templates with effective dates :							
		MTWTFSS	From Date	To Date			
Standard Week Template:							
M T W T F S S							
D O D O D N N							
F3=Exit F8=Update F12=Previous							
08-02		SE	MW	KS	IM	II	KENB20A PET087S1

Fields:

The following details are display only.

Calendar Code/Year

This displays the calendar code and year already entered.

Description

This displays the calendar description already entered.

Standard Week Template

This displays the standard week template already entered.



Enter the following details to parameterise the Calendar

Holidays

Enter individual holiday days in From field only.

Use To and From fields for holidays or for more than one day.

Alternative Week Templates

Enter the alternative working week templates you want to set up.

Enter D=Working Day (see note).

Enter N=Non working day.



Note: If assigned to a stockroom D=despatch day. If assigned to a contract D=deliveries.

You can enter up to 5 alternative week templates where the working week is non-standard.

Date From/To

Enter the period of time for which each alternative template you have entered should be applied.



Press **F8=Update** to update the files.

Start Confirm Despatch Updates



30/ADU

This background job must be running in order to process any despatches through shipping. When confirming despatch quantities against stockroom, the screen will show despatch pending until file updates have been performed through this job.

When all stockrooms have been confirmed, select **F21=Confirm Consignment** to complete the despatch.

Start ASN EDI Send



31/ADU

This is a background process which sends ASNs to the EDI function. This program must be run for all send/resend items identified.

