

-
-
-
-
-

Chapter 4

Quotations



Build Quote



1/JCG

If you are building a quotation for the first time, or the quotation that you are about to build is different in type to any previous quotations, then you may need to add or amend some initial details:

- The quotation header and details screens are similar to the standard job header and job detail screens, and, like the standard job header, a quotation header must have a valid job type and customer. The customer must exist in Accounts Receivable, although quotation transactions will not update any balances.
- Any parameter used for a job can be used for a quotation.
- A valid job type must be entered. Quotations use the same job types as jobs. Remember that without appropriate expense types associated with the job types, you will not be able to build costs against a quotation.



Tip: There are a number of copy facilities available for quotations:

- Copy a closed quotation to a live job.
- Copy a sub-job/task to another sub-job/task within a quotation.
- Copy an existing quotation to a new quotation.
- Copy a job to a quotation.

Quotation Build Screen



Take the Build Quote option to see the Quotation Build Screen, and enter a new or existing quotation and any relevant revision on the selection screen. Press **Enter**.

Fields:

Quote

Enter a new or existing quotation.

Revision

Enter the relevant revision.

Functions:

F10

Copy. If the quotation you entered does not exist, select **F10=Copy** to specify a quotation to use as the basis of the new quotation. You will see the Copy Quotation Window.



Press **Enter**.

If the quotation you entered exists, you will see the Quote Details Maintenance Screen.

If the quotation you entered does not yet exist, you will see the Quote Header Maintenance Screen.

Copy All Details

0 - Copy only the structure, that is, the number and values of sub-jobs and tasks.

1 - Copy all details. This will include expense types and transaction details in the quotation but will not copy across header details if the quotation to which you are copying already exists.



Press **F8=Copy** to activate the copy. You will now be taken to the Quote Header Maintenance Screen; this is the same screen you will see if you are creating a quotation which has not been copied.

Quote Header Maintenance Screen



You will see this screen if you are creating a new quotation. If you are creating your quotation from a copy, then you will see this screen after you select **F8=Copy** on the Copy Quotation Window. Otherwise, you will see it when you press **Enter** on the Quotation Build Window.

This screen is identical in format to the standard job header, and enables you to maintain the data for the high level quotation. This is data that applies to the overall job features. Do not confuse the header with the details screen, which maintains detail data or a quotation at any level, that is, job, sub-job, and task level.

JM253	Z1 - GB Demonstration Company	USER GBJBANB1	29/01/98 16:48:59
Quote Header Maintenance			
Quote/Revision.. AAQ003		Created 4/10/96	
Job type....?.. <u>TKC</u> Turn-Key Contracts			
Description.... <u>Extend Railway to Treacle Mine</u>			
Customer..... TQA001 Bill & Ben Flowerpots Ltd			
Babylon Garden Centre			
31 Park Road			
Moseley			
BIRMINGHAM			
B13 1BB			
Estimated hours control..... 0 (0=Manual, 1=Automatic)			
Customer order..... <u>BBFL-Q96-0002</u>			
Industry code.....?.. <u>PVTL</u> Private Landlords			
Penalty clause.....?.. <u>NPC</u> No Penalty Clause			
Secondary analysis codes.?.. <u>RD</u> _ _ _ _ _			
Major contract..... <u>DRBEEC</u>			
F3=Exit F4=Prompt F12=Previous			

Fields:

Quote/Revision

The quotation number is displayed here.

Job Type

Each quotation must have a job type. The job type is defined at job level. The job type of each sub-job and task defaults to the job type specified here.

Job types are created within Parameters Maintenance. If you wish this field to remain blank, then a blank job type must be set up.

Description

Enter text to describe the quotation. This field cannot be left blank.

Customer

Enter a valid Accounts Receivable customer. If you enter a customer who is part of a hierarchy, it cannot be above level 1 in that hierarchy. A warning will be

displayed if the customer has exceeded their credit limit, but this can be ignored. This field cannot be left blank.

Estimated Hours Control

0 - The estimated hours value held at quotation detail level are to be maintained manually.

1 - The estimated hours value held at quotation detail level are to be automatically maintained by the system, by accumulating the hours recorded for labour transactions.

Customer Order

Enter a customer order number if applicable.

Industry Code

Enter an industry code. Entry is optional.

Industry codes are created within Parameter Maintenance.

Penalty Clause

Enter a penalty clause. Entry is optional.

Penalty clauses are created within Parameter Maintenance.

Secondary Analysis Codes

Enter up to eight secondary analysis codes.

These codes are created within Parameter Maintenance.



Note: These codes can be used to analyse jobs in various ways, such as using IBM's query facility or creating selective reports using JBA's report generator.

Major Contract

This field is for memo purposes only.



Press **Enter** to see the Quote Details Maintenance Screen. If this second screen is not completed here, then no job details for the job level are added.

Quote Details Maintenance Screen



You will see this screen if you either enter an existing quotation on the Build Quotation Screen and press **Enter**, or press **Enter** from the Quote Header Maintenance Screen.

This is similar to its equivalent job details screen, but note the following differences:

- The only function keys available here are **F3=Exit**, **F4=Prompt** and **F12=Previous**.
- The transfer method field is not available. No transfer methods apply to quotations.
- The parts list is available to a quotation, but not on this screen.

The quotation details for lower sub-levels default to that of the header, but you can overwrite them.

JM254		Z1 - GB Demonstration Company		USER GBJBANB1	29/01/98
					16:49:26
Quote Details Maintenance					
Job/sub-job/task...		AAQ003		Q/S	
Job type.....		TKC Turn-Key Contracts		Status? <u>1</u> New	
Customer (Header)....		TQA001 000		Bill & Ben Flowerpots Ltd	
Description.....		<u>QS : Prepare Bill of Materials</u>			
Customer (Detail).?..		<u>TQA001</u> .?.. <u>000</u>		Bill & Ben Flowerpots Ltd	
		Babylon Garden Centre			
		31 Park Road			
		Moseley			
		BIRMINGHAM			
Estimated start date. <u>1/01/97</u>		Estimated end date. <u>1/04/97</u>			
Actual start date.... <u>0/00/00</u>		Actual end date.... <u>0/00/00</u>			
Selling price.....		319.00		Estimated hours.... <u>25.00</u>	
Grant confirmed.....		.00		Grant anticipated.. <u>.00</u>	
Cost/Price lists..?.. <u>B</u> <u>F</u>		Chase date..... <u>0/00/00</u>			
Income currency...?.. <u>GBP</u>		Division..?.. <u>CE</u>		Civil Engineering	
Profit ctr? <u>300001</u>		Location..?.. <u>BM</u>		Birmingham Area	
Price type. <u>2</u> (0/1/2)		Project mgr? <u>JLF</u>		Jim French	
Region..?.. <u>WM</u>		Account mgr? <u>NP</u>		Norman Peddie	
Chg time/mat (0/1/2) <u>1</u> <u>1</u>		Retn type?.. <u>NR</u>		No retention	
Review <u>1</u>					
F3=Exit F4=Prompt F12=Previous					

Fields:

Status

Select a valid status code. When adding a new job/sub-job/task, it will default to status 01 - job open.

Description

Enter up to thirty characters of text to describe the job.

Customer (Detail)

When you are entering a new job detail, and until transactions are recorded against this job detail, you can enter a customer here. This can be different from the customer entered on the job header.

(Untitled)

Delivery address. This allows multiple site addresses to be associated with the main customer held against the job.

Estimated Start Date

Enter the estimated start date of the quoted job. If you indicated on the quotation header screen that you want the system to calculate estimated hours automatically, and this detail or one at a lower level has labour transactions, and you change this start date, then the system will automatically recalculate the estimated hours when you update.

Estimated End Date

Enter the estimated end date of the quoted job (where applicable).

Actual Start Date

This field is not used for quotations by the system, but you can enter a job start date before converting the quotation into a job.

Actual End Date

This field is not used for quotations by the system, but you can enter a job end date before converting the quotation into a job.

Selling Price

The estimated selling price or quotation that you have received for this quoted job.

Estimated Hours

If you indicated on the quotation header screen that you want the system to calculate estimated hours automatically, then you cannot maintain this field.

If you indicated on the quotation header screen that you want to enter estimated hours manually, then enter here the estimated workload, in hours, for this job.

Grant Confirmed

The value of any grants applied for and confirmed.

Grant Anticipated

The value of any grants applied for but as yet unconfirmed.

Cost/Price Lists

The first of these two fields is for a cost list, the second for a price list.

In the cost list field, enter the list you want to use for labour costs.

In the price list field, enter the list you want to use for labour pricing.

Chase Date

You can enter a date to be used as a prompt to contact the customer or as a reminder to the project manager.

Income Currency

A valid currency is required for invoicing this quotation. It defaults to the base currency.

Division Code

Enter the division of the company providing the service.

Profit Centre

Select a valid profit centre.

Location

Enter the location for the company providing the service.

Price Type

Select the price type for this particular job/sub-job/task.

0 - Fixed price.

1 - Non chargeable.

2 - Time & materials.

This field cannot be left blank.

Project Mgr

Select a valid project manager.

Region

Select a valid region code.

Account Mgr

Select a valid account manager.

Chg Time/Mat

0 - Do not charge. In this case you can allocate timesheets or materials against the job level, but you will not invoice that customer for the time or materials allocated.

1 - Charge for time or materials. You cannot use this setting if the price type is fixed or non-chargeable.

2 - You will make the decision whether or not to charge when you are reviewing this transaction in the Chargeable Transaction Review option.

One of these fields must be set to 1 or 2 for this quotation to be accepted as a time and materials job.

Review

0 - The invoices for this job need not be reviewed before printing.

1 - The invoices for this job are to be reviewed before printing.

Retention Code

Enter a valid retention type code. This field is a memo field only.



Press **Enter** to go to the Quotation Build Work
With Details Screen.

Close Quote



2/JCG

This option enables you to close a quotation. Before entering this option you must set up the reason code you will enter as the reason for closing this quotation.



Take the Close Quote option and enter the quotation/revision on the selection screen. Once you enter the quotation to be closed, all sub-jobs and tasks for that header will also be closed. Press **Enter**, and the first Quotation Close Screen is displayed.

Quotation Close Screen 1



When you have entered the quotation/revision on the selection screen, press **Enter**, and the first Quotation Close Screen is displayed.

JM255	Z1 - GB Demonstration Company	USER GBJBATD0	15/10/97 16:46:17
Quotation Close			
Quote/Revision.. MPLT20		Created 11/04/96	
Description..... MNM's parts list test 1			
Reason code..?... LD			
Generate job.... 1 (0/1)			
F3=Exit F4=Prompt F12=Previous			
11-19 SP MW KS CL IM DM II STUD140 KB PKH317S1			

Fields:

Reason Code

Enter the relevant code. This is mandatory, and can not be blank.


Generate Job

0 - You do not wish to create a job from this quotation.

1 - When you press **Enter**, a window will be displayed enabling you to create a live job from the details of this quotation.



If you are creating a job from the quotation, then when you press **Enter** you will see the second Quotation Close Screen.



active.

Default Transfer Method

Nine transfer methods, 0 - 8, are available for a job detail.

The job is generated in the following way:

- The job header is copied.
- The job details are copied.
- Budget records are created at the requested level at the default budget type from the Job Management company profile.
- If a parts list is to be created then the related sales order will be released. If parts lists are not to be created then orders for the quotation are flagged as cancelled.
- Production transactions from the quotation are copied to the job. Production transactions also generate sales order lines on new or existing parts lists if parts list creation is selected.
- Production expenses and budgets are consolidated with Inventory expenses and budgets.

Cost To Complete Code

If you wish to use cost to complete, enter a relevant code here. These codes must be set up as parameters using the Cost To Complete Codes option.

You can process cost to complete using only one cost to complete code, but if you wish to divide the Cost To Complete Initiation batch job into more than one batch, the cost to complete codes enable you to do this.

If you leave this field blank, the job will not be included in cost to complete processing.

If you want the job to be included in cost to complete calculations, then you must also set the three cost to complete methodology fields in this window. If budgeting is not at expense type level then the cost to complete function will not be available at expense type level.

Maintain Labour Budget From Estimated Hours

0 - The labour budget for this job will be maintained manually.

1 - The labour budget for this job will be maintained automatically by the system, using a calculated value of estimated hours.

Labour Cost To Complete Methodology

You should only use this field if you have set the Include In Cost To Complete field to '1'.

Enter a default method here to calculate the cost to complete. Select from the following:

- 1 - Finish budget on time.
- 2 - Continue at same level of efficiency.
- 3 - Complete at standard rate.

- 4 - Input degree of inefficiency to apply to rest of job.
- 5 - Input degree of efficiency to apply to rest of job.
- 6 - Enter hours to complete manually.



Tip: For more details on these methods, refer to the Cost To Complete Maintenance section.

Materials Cost To Complete Methodology

You should only use this field if you have set the Include In Cost To Complete field to '1'.

Enter a default method here to calculate the cost to complete. Select from the following:

- 1 - Based on commitments.
- 2 - Based on original estimates.
- 3 - Enter revised estimate.



Tip: For more details on these methods, refer to the Cost To Complete Maintenance section.

Other Direct Cost To Complete Methodology

You should only use this field if you have set the Include In Cost To Complete field to '1'.

Enter a default method here to use to calculate the cost to complete. Select from the following:

- 1 - Based on commitments.
- 2 - Based on original estimates.
- 3 - Enter revised estimate.



Tip: For more details on these methods, refer to the Cost To Complete Maintenance section.



Press **Enter**.

If the selected quotation has a parts list or Production transactions, and you entered '1' against the Parts List field on the Quotation Close Screen 2, the Generate Job - Override Order Due Dates Screen is displayed.

If not, the quotation is closed and you leave the option.

Generate Job Override Order Due Dates Screen



If the selected quotation has a parts list or Production transactions, and you entered '1' against the Parts List field on the Quotation Close Screen 2, the Generate Job - Override Order Due Dates Screen is displayed.

JM251	Z1 - GB Demonstration Company	USER GBJBABL	12/02/97
			16:42:07

Generate Job - Override Order Due Dates

Job/Sub-Job/Task	Due Date	Description	Order	Number of M/F Item
MPLT2C	0	11/04/96 MNM's parts list test 1	0000843	0000
MPLT2C SBJ1	0	11/04/96 1st sub job	0000844	0000
MPLT2C SBJ1	1	11/04/96 1st atsk	0000845	0000
MPLT2C SBJ1	2	11/04/96 2nd task	0000846	0000

Bottom

F3=Exit F12=Previous

07-20  MW KS IM II KENB20A PET179S8

Fields:

Due Date

The due date of each job, sub-job or task can be amended.

Number of M/F Item

The number of manufactured items corresponds to the number of sales order lines created for these items. These will subsequently become production orders. This field is displayed for your information only, and cannot be amended.



Press **Enter** to create a sales order.

Work With Quotes

1...
2... 3/JCG

If you are maintaining an existing quotation, two options can take you to a details maintenance screen - Build Quote and Work With Quotes.

Work With Quotations Screen



Take the Work With Quotes option to see the Work With Quotations Screen listing existing quotations. A selection field against each one gives the following options:

Fields:

Option

2 - Work with individual quotation details. Not available for quotations which have been closed.

3 - Copy across quotation details to a new or existing quotation.

The Copy Quote option will copy to an existing quotation. Any existing quotation detail data will be left unchanged, but it will add to it any transactions within the 'from' detail.

5 - Display details for an existing quotation, including closed quotations.



Enter 3 against a quotation to bring up the Copy Quotation Window.

Functions:

F6

Add. This takes you to the Build Quote option to enable you to add a new quotation.

F9

All Revisions.

F17

Position. This is a search facility which finds the nearest alphanumeric match on a quotation.

Copy Quotation Window (Option 3)



Enter 3 against a quotation to bring up the Copy Quotation Window.

JM260		Z1 - GB Demonstration Company		USER GBJBABL		12/02/97	
						15:44:00	
Work With Quotations							
Opt	Job	Description					
-	AAJ019	Refurbish "Th					
3	AAQ001	Refurbish 'Th					
-	AAQ002	Treachle Mine					
-	AAQ003	Extend Railwa					
-	AAQ004	Maintenance G					
-	AAQ005	Renovation of					
-	AAQ006	Build Hot-Air					
-	AAQ009	New Tram Depo					
-	AAQ010	Refurbish "Th					
-	AAQ016	Build Helium					
-	AAQ017	Tooleys' Dry-					

Copy Quotation

From quotation..... AAQ001

From revision.....

To quotation..... _____

To revision..... _____

To customer.....?.. _____

Copy all details... @ 0=No
1=Yes

F3=Exit F4=Prompt F8=Copy F12=Previous

More...

2=Change 3=Copy 5=Display
F3=Exit F5=Refresh F6=Add F9=All Revisions F17=Position

11-52 SF MW KS IM II KENB20A PET179S8

Fields:

From Quotation/Revision

The quotation/revision number which you wish to copy from is displayed and cannot be changed.

To Quotation/Revision

Enter the number of the quotation/revision you wish to copy to.

To Customer

The customer associated with the new quotation.

Copy All Details

0 - Copy only the structure, that is, the number and values of sub-jobs and tasks.

1 - Copy all details. This will include expense types and transaction details, but will not copy across header details if the quotation to which you are copying already exists.

Functions

F8

Copy. Performs the copy, and returns you to the selection list screen, where you will see your new quotation listed.



Enter 2 against a quotation to see the Quotation Build Work With Details Screen. If the quotation you select has more than one revision level, a

window will list revisions for you to select one.

Quotation Build Work With Details Screen

Available from both the Build Quote and the Work With Quotes options, this screen provides an indented list of all job details.



If you are in the Work With Quotes option, enter option 2 against a quotation. If you are in Build Quote, you must go through the header and details screens before seeing the Quotation Build Work With Details Screen.

The first row in this list always shows the quotation header. In the description column you can see the header being identified as '** Header'.

```

JM232                Z1 - GB Demonstration Company      USER GBJBABL    12/02/97
                                           15:48:05
Quotation Build - Work With Details                                Autocalc..: *ON

Quote/Revision.. AAQ001                      Created 17/07/96
Description..... Refurbish 'The Blakeney Hotel'
Customer..... TQA002    000 Weoley Castle Brewery plc

Opt Sub-Job/Task Description                      Total Cost          Price      Margin
■
- ARCH          ** Header                        .00                .00        .00
- ARCH          Architects' Tasks                 .00                .00        .00
- ARCH          1 Draw Plans                      .00                .00        .00
- ARCH          2 Gain Local Authority Appr       .00                .00        .00
- M/C           Main Contractors' Tasks           .00                .00        .00
- M/C           1 Network Plan and Resource       .00                .00        .00
- M/C           2 Erect Building                  .00                .00        .00
- M/C           3 Quality Assurance               .00                .00        .00
                                           More...

2=Change 3=Copy 4=Delete 5=Recalc 6=Text 7=Expenses 8=Price override
9=Parts list
F3=Exit F5=Refresh F6=Add F7=Autocalc Off F9=Cost recalc F10=Header
F12=Previous F17=Position list

10-02  SF  MW  KS  IM  II  KENB20A  PET179S8

```

Fields:

Opt

2 - Change quotation details. The quotation details can be amended for any job, sub-job or task. If you select a job, then related sub-jobs and tasks will first be displayed for selection before you see the Quote Details Maintenance Screen, which is where amendment can take place. See the Build Quote section for details of this screen.

The quotation details for any sub-jobs and tasks added default to the quotation details of the header level. The quotation details can be maintained so that the price type can differ between details of the same quotation.

3 - You can copy sub-job and task details to other sub-jobs/tasks within the same quotation. However, you cannot copy any header information to other sub-job and tasks. Sub-jobs can only be copied to other sub-jobs but tasks can be copied to other task numbers and sub-job details. See the Copy Quotation Window (Option 3) section.

4 - You can delete any sub-job and associated tasks for a quotation. If you delete a sub-job, that sub-job and any associated tasks will be deleted. If, however, you specify a task to be deleted, then only that task is deleted. This option is not available for the quotation header line.

5 - Option 5 enables you to recalculate a line if you have set the autocalculation function key to 'off' (**F7=Autocalc Off**).

6 - You can enter free-format text against each quotation detail. This text can be amended subsequently. Text is not copied across to sub-job/task details when copying across sub-jobs and tasks.

7 - Maintain any expenses for a job/sub-job/task. The option takes you directly to the Work With Expenses Screen, from which you can go on to work with transactions.

8 - For any quotation/sub-job/task, the rolled up price or margin can be overridden.

9 - This option is only allowed if SOP (Sales Order Processing) is active on the company profile and the quotation job type includes the Inventory expense type (e.g. 'INV'). The interface to Advanced Order Entry is also permitted where a sales order can be maintained against the job/sub-job/task. For the quotations facility, a sales order is held as suspended.

It is suggested that you consult appropriate sections of Inventory Management, SOP and Advanced Order Entry documentation for the purpose of building the parts list.

The aim is to use a parts lists to capture the cost of Inventory items for a job detail. Each job or quotation detail can only have one sales order associated with it, although each sales order can subsequently be amended.

Functions:

F6

Add. Adds sub-jobs and tasks to the quotation header

Press **F6=Add** to see a window to enter the number of the new sub-job/task.

Press **Enter** to go to the Quote Details Maintenance Screen, newly set up for that sub-job/task. See the Build Quote section for more details of that screen.

Press **Enter** to validate the details and return to the Add Sub-job/Task Window.

Press **F12** to complete the addition of the sub-job/task. You will see the new sub-job/task added to the indented list.

F7

Autocalc Off/On. This function key turns the interactive cost update on or off. The current status of auto-calculation can be seen in the top right of the screen. This key is also available on the work with expenses and the work with transactions screen.



Note: While autocalc is off, any values that would be different if autocalc were on are displayed in reverse image.

F9

Cost Recalc. Recalculates the total costs for the entire quotation by rolling the values up from lowest task level.

F10

Header. This function enables the quotation header to be maintained.

F17

Position list. This function key positions the indented list to the closest match of the data entered.

Copy Quotation Window (Option 3)



This window is displayed when you enter 3 against a quotation detail on the Work With Details Screen.

If 3 is entered against a task you can copy to another task. Copying a sub-job or task will copy to an existing quotation detail. Any existing detail data will be left unchanged, but it will add to it any transactions within the 'from' detail. External text is not copied, as it only holds job detail details for printing on pick notes.



Note: Copying will reprice any parts list according to the details of the new customer.

JM232		Z1 - GB Demonstration Company		USER GBJBABL		18/06/97	
						17:03:20	
Quotation Build - Work With Details				Autocalc...: *ON			
Quote/Revision..		AAQ001					
Description.....		Refurbish					
Customer.....		TQA002					
Opt	Sub-Job/Task	Description				Price	Margin
3	ARCH	Architect				68.72	39.79
-	ARCH	1 Draw Plan				.00	.00
-	ARCH	2 Gain Loca				.00	.00
-	M/C	Main Cont				.00	.00
-	M/C	1 Network P				.00	.00
-	M/C	2 Erect Bui				.00	.00
-	M/C	3 Quality A				.00	.00
				More...			

Copy Quotation

From sub-job/task.. ARCH c

To sub-job/task....

Customer.....?

Copy transactions.. 0 0=No 1=Yes

Copy tasks..... 0 0=No 1=Yes

F3=Exit F8=Copy F12=Previous

2=Change 3=Copy 4=Delete 5=Recalc 6=Text 7=Expenses 8=Price override
9=Parts list

F3=Exit F5=Refresh F6=Add F7=Autocalc Off F9=Cost recalc F10=Header
F12=Previous F17=Position list

09-52 SP MW KS IM II EDN400A PE9106S2

Fields:

From Sub-Job/Task

Enter the source sub-job or task.

To Sub-Job/Task

Enter the target sub-job or task.

Customer

The customer entered here will be set up on the new quotation detail, with the default '000' delivery address. You can leave this field blank.



Note the following:

If the customer is changed, and the new customer has a different stockroom from the original, then any linked parts lists will not be copied.

Override addresses entered against the job

details will not be copied.

Parts lists will be copied.

Copy Transactions

1 - All transactions will be copied across - expense types and values for any references behind those expenses.

0 - Only the structure is copied. The cost, price and total columns will be zero values.

Copy Tasks

1 - If you are copying sub-job to sub-job, and the source sub-job has tasks, these tasks will be copied too. If you selected a task for copying, the Copy Tasks field does not appear.



Complete as required, and press **F8** to proceed with the copy. You will return to the Work With Details Screen.

Work With Expenses Screen (Option 7)



This window is displayed when you enter 7 against a quotation detail on the Work With Details Screen.

If you wish to build costs as part of a quotation, then you can do so by assigning a number of expense types to a quotation detail. Each line on the Quotation Build Work With Details Screen can have a number of expense types, though not every line needs to. You may decide to add your expense types, and hence your quoted costs, at the lowest level, leaving the header level solely for the purpose of aggregating the costs and prices.

Each expense type can have a number of transactions against it. These transactions are given a reference number in the quotations facility.

This screen lists a summary by expense code of all transactions entered against a job/sub-job/task. Each row on the list shows a summary of all transactions entered against that expense code. If the expense type is equal to the Inventory expense type defined on the Job Management company profile, then these costs have been calculated from a parts list.

```

JM236                Z1 - GB Demonstration Company    USER GBJBABL  12/02/97
                                           16:04:42
Quotation Build - Work With Expenses                Autocalc.: *ON

Quote/Revision.. AAQ001                Created 17/07/96
Description..... Refurbish 'The Blakeney Hotel'
Customer..... TQA002    000 Weoley Castle Brewery plc
Sub-job/task.... ARCH 000    Architects' Tasks

Opt  Expense                Cost  Mark Up        Price
-    MAN Manufacturing      372.00    1.00        375.72

                                           Bottom

4=Delete  6=Global mark up  7=transactions
F3=Exit  F5=Refresh  F6=Add  F7=Autocalc Off  F9=Cost recalc  F12=Previous
F17=Position list

11-02    Sg    MW    KS    IM    II  KENB20A  PET179S8
  
```

Fields:

Opt

4 - Delete a line, with all references of that expense within a job detail. You only delete the references for the chosen expense of the job detail (to check, take option 7 to view transactions for a breakdown of the transactions which you would delete).

6 - Allows all transactions for a particular expense type to be uplifted. A window enables you to enter the percentage value.

There is a special feature when a global mark-up is applied to the expense associated with Inventory. The system will process all of the lines for the associated parts list, and change the price of each line to a fixed price value which is equal to the Inventory cost plus the mark-up percentage.

7 - Against each expense type, you can enter a number of transactions for a given type. Enter a 7 to view the individual transaction references that make up the expense type for this job detail.

Functions:

F6

Add. Add an expense type. You cannot add the expense type associated with inventory. This must be done using option 9 from the Work With Details Screen.

F7

Autocalc Off/On. Turn the interactive cost update on or off.

The current status of auto-calculation can be seen in the top right of the screen.

F9

Cost Recalc. Recalculate the total costs for the entire quotation by rolling the values up from lowest task level.

F10

The global mark-up change window will allow percentages to be entered. All expense transactions for this job/sub-job/task expense type is updated with the new mark-up and the price recalculated. Any transactions with a fixed price are excluded.

F17

Position List. This positions the indented list to the closest match of the data entered.

Work With Transactions Screen (F6)



If you select **F6=Add** from the Work With Expenses Screen and there are existing transactions, you will see the Work With Transactions Screen, which lists existing transactions for the expense type you selected.

If there are no existing transactions when you select **F6=Add**, the appropriate Add/Amend Transactions Window (Labour, Direct or Production, depending on the expense type selected) is displayed.

```

JM242                Z1 - GB Demonstration Company      USER GJBABL  12/02/97
                                                16:00:53
Quotation Build - Work With Transactions                Autocalc...: *ON

Quote/Revision.. AAQ001                Created 17/07/96
Description..... Refurbish 'The Blakeney Hotel'
Customer..... TQA002    000 Weoley Castle Brewery plc
Sub-job/task.... ARCH 000    Architects' Tasks
Expense type.... MAN            Manufacturing

Opt  Item          Route          Cost      Quantity  Mark Up      Price
-    ALCFG          C              372.00      12.00      1.00      375.72

                                     Total      372.00      12.00      1.00      375.72
                                           Bottom

2=Change 4=Delete
F3=Exit F5=Refresh F6=Add F7=Autocalc Off F10=Chg mark up F12=Previous
F17=Position list F18=Maintain item F19=Copy item F20=Maintain Route

12-02  SP      MW      KS      IM      II  KENB20A  PET179S8

```

Fields:

Opt

Option. Enter one of the following:

2 - Change. Amend the transaction. The appropriate transaction window (labour, direct or Production) is displayed; this depends on the expense type of the job detail.

4 - Delete. Delete the transaction.



Select a transaction to work with (i.e. enter 2 against a line, or press **F6**).

Functions:

F6

Add. Add a transaction. The appropriate transaction window (labour, direct or Production) is displayed; this depends on the expense type of the job detail.

F7

Autocalc On/Off. Turn the interactive cost update on or off.

The current status of auto-calculation can be seen at the top right of the screen.

F10

Chg Mark-up. Change mark-up for all items at this detail level.

F17

Position List.

F18

Maintain Item. The Inventory Management, Linked Item Maintenance Screen is displayed.

F19

Copy Item. The Inventory Management, Copy Item Based On Screen is displayed.

F20

Maintain Route. This takes you through to Production, Routes/Structures.

Add/Amend Labour Transactions Window (F6)

When you enter 7 against an expense type on the Work With Expenses Screen, two screens are possible. If the expense type is 'Inventory' on the company profile, you will be taken to the SOP/AOE order amendment screen. Otherwise you will see the Work With Transactions Screen, which enables you to work with the transactions for any job/sub-job/task/expense type.



If you take **F6=Add** from the Work With Expenses Screen and there are existing transactions, you will see the Work With Transactions Screen, which lists existing transactions for the expense type you selected.

If when you take **F6=Add** there are no existing transactions, the appropriate Add/Amend Transactions Window (Labour, Direct or Production, depending on the company profile expense type) will be displayed.

```

JM242                Z1 - GB Demonstration Company        USER GBJBABL  12/02/97
                                                           16:25:28
Quotation Build - Work With Transactions                    Autocalc...: *ON

Quote/Revision.. AAQ001                                Created  17/07/96
Description..... Refurbish 'The Blakeney Hotel'
Customer..... TQA002    000 Weoley Castle Brewery plc
Sub-job/task.... ARCH 000 Architects' Tasks
Expense type.... LAB      Labour

Opt  Grade/Narrative

Add/Amend Labour Transactions

Transaction ref... 0001
Grade.....?.. _____
Hours..... _____ .00
Narrative..... _____
Mark up..... _____ .00
Fixed price..... 0

F3=Exit  F4=Prompt  F12=Previous  F17=Override

2=Change  4=Delete
F3=Exit  F5=Refresh  F6=Add  F7=Autocalc Off  F10=Chg mark up  F12=Previous
F17=Position list

14-47  SF  MW  KS  IM  II  KENB20A  PET179S8

```

Fields:

Transaction Ref

Grade

Hours

Narrative

Enter free-format text as required.

Mark-up

Enter the percentage mark-up to apply to the labour cost.

Fixed Price

1 - Protect the transaction from any global mark-up at expense type level.



If the expense is not 'Labour' on the company profile, then when you select a transaction to work with you will see the Add/Amend Direct Transactions Window.

Add/Amend Direct Transactions Window (F6)



If you take **F6=Add** from the Work With Expenses Screen and there are existing transactions, you will see the Work With Transactions Screen, which lists existing transactions for the expense type you selected.

If when you take **F6=Add** there are no existing transactions, the appropriate Add/Amend Transactions Window (Labour, Direct or Production, depending on the expense type selected) will be displayed.

```
JM242                Z1 - GB Demonstration Company    USER GBJBABL  12/02/97
                                      16:27:12
Quotation Build - Work With Transactions              Autocalc...: *ON

Quote/Revision.. AAQ001                Created  17/07/96
Description..... Refurbish 'The Blakeney Hotel'
Customer..... TQA002   000 Weoley Castle Brewery plc
Sub-job/task.... ARCH 000   Architects' Tasks
Exp Add/Amend Direct Transactions

Opt Transaction ref. 0001
  External ref.... 
  Narrative..... 
  Quantity..... .00
  Unit cost..... .00   Total cost.... .00
  Unit price..... .00   Total price... .00
  Mark up..... .00
  Fixed price.... 0

F3=Exit F12=Previous
4=Delete
F3=Exit F5=Refresh F6=Add F7=Autocalc Off F10=Chg mark up F12=Previous
F17=Position list

12-26  SF  MW  KS  IM  II  KENB20A  PET179S8
```

Fields:

Transaction Ref

This number is system-generated.

External Ref

Enter a unique free-format reference.

Narrative

Enter free-format text as required.

Quantity

Enter the quantity. This field is normally optional, but you must enter a quantity if you are overriding a labour transaction and you indicated on the header that you want the system to calculate estimated hours automatically.

Unit Cost

Enter a unit cost. This field is optional.

Total Cost

Enter the total cost manually, or allow the system to calculate it as quantity multiplied by unit cost.

Unit Price

Enter a unit price. This field is optional.

Total Price

Enter the total price manually, or allow the system to calculate it as quantity multiplied by unit price.

Mark-up

Enter the percentage mark-up to apply to the cost. This will override any price entered.

Fixed Price

1 - Protect the price from any global mark-up at expense type level.

Add/Amend Production Transactions Window (F6)



If you select **F6=Add** on the Work With Expenses Screen and there are existing transactions, the Work With Transactions Screen is displayed, listing existing transactions for the expense type you selected.

If there are no existing transactions when you select **F6=Add**, the appropriate Add/Amend Transactions Window (Labour, Direct or Production, depending on the expense type selected) is displayed.

JM242	Z1 - GB Demonstration Company	USER GBJBABL	12/02/97
			15:58:24
Quotation Build - Work With Transactions			Autocalc...: *ON
Quote/Revision.. AAQ001 Created 17/07/96			
Description..... Refurbish 'The Blakeney Hotel'			
Customer..... TQA002 000 Weoley Castle Brewery plc			
Sub Add/Amend Production Transactions			
Exp			
Opt	Transaction ref. 0001		
2	Item number...?. ALCFG Config parent		
2	Route..... C Cost set		
Narrative.....			
Quantity..... 12.00			
Unit cost..... .00		Total cost.... .00	
Unit price..... .00		Total price... .00	
Mark up..... 1.00			
Fixed price..... 0			
F3=Exit F4=Prompt F12=Previous F18=Maintain Item F20=Maintain Route			
2=C F21=Cost Simulation F22=Cost Element Enquiry			
F3=Exit F5=Refresh F6=Add F7=Autocalc Off F10=Chg mark up F12=Previous			
F17=Position list F18=Maintain item F19=Copy item F20=Maintain Route			
11-26 SF MW KS IM II KENB20A PET179S8			

Fields:

Item Number

Enter the item number for the transaction.

Route

Enter the item's route.

Cost Set

Enter the relevant cost set.

Narrative

Enter free-format text as required.

Quantity

Enter the quantity. This field is optional.

Unit Price

Enter a unit price. This field is optional.

If you enter a unit price or a total price or a markup, then the system will derive the price from the cost automatically.

Total Price

Enter the total price manually, or allow the system to calculate it as quantity multiplied by unit price.

If you enter a unit price or a total price or a markup, then the system will derive the price from the cost automatically.

Mark-up

Enter the percentage mark-up to apply to the cost.

If you enter a unit price or a total price or a markup, then the system will derive the price from the cost automatically.

Fixed Price

0 - No. Do not protect the price from global mark-up.

1 - Yes. Protect the price from any global mark-up.



Press **Enter** to validate, and again to return to the Work With Transactions Screen.

Functions:

F18

Maintain Item. This takes you through to Inventory Management, Item Maintenance.

F20

Maintain Route. This takes you through to Production, Routes/Structures.

F21

Cost Simulation. This takes you through to Production, Indented Cost Simulation, and is available only if you have advanced Production installed.

F22

Cost Element Enquiry. This takes you through to the Production Cost Element enquiry.

Price Override Window (Option 8)



This window is displayed when you enter 8 against a quotation detail on the Work With Details Screen.

```
JM232                Z1 - GB Demonstration Company    USER GJBABLT    12/02/97
                                      16:18:46
Quotation Build - Work With Details    Autocalc...: *ON

Quote/Revision.. AAQ001                Created 17/07/96
Description..... Refurbish 'The Blakeney Hotel'

Price Override

Quote/rev/sub-job/task.. AAQ001                ARCH    0    ce    Margin
Cost..... 372.00                                72    1.00
Margin/price override... M                                00    .00
Margin..... .00                                00    .00
Selling price..... .00                                00    .00
F3=Exit F8=Update F11=Delete override
F12=Previous                                00    .00
More...

2=Change 3=Copy 4=Delete 5=Recalc 6=Text 7=Expenses 8=Price override
9=Parts list
F3=Exit F5=Refresh F6=Add F7=Autocalc Off F9=Cost recalc F10=Header
F12=Previous F17=Position list

12-30    SP    MW    KS    IM    II    KENB20A    PET179S8
```

Fields:

Cost

This field is input-inhibited. The total cost is displayed as a rolled-up value. The purpose of this figure is that a margin percentage can be adjusted based on this figure.

Margin/Price Override

Enter M or P for appropriate override.



*Note: If you override the existing value, affected values are highlighted. You can undo the override by going back into this window and pressing **F11=Delete Override**.*

When you have entered an override value, then the price or margin is highlighted in order to show that an override exists at this level.

Margin

The percentage margin required over cost. The 'Margin/Price Override' field must be set to M.

Selling Price

The required selling price. The 'Margin/Price Override' field must be set to P.



Press **F8=Update** to update and return to the Work With Transactions Screen.

Close Reason Codes



11/JCG

When you close a quotation you will be asked to enter a reason for closure. This might be a code for 'lost on price', 'won on completion date', etc.



Take the Close Reason Codes option to enter the option.

To set up a code you simply need to enter a two character code with a description.

No blank code can be set up, and the entry of a code when closing a quotation is mandatory.

Quotation Print



21/JCG



Take the Quotation Print option to see the Quotation Print selection window.

Quotation Print Window

JCG		Z1 - GB Demonstration Company		User GBJBABL		14/07/97	
Quotation Print							
Job Ma		From		To			
Proces	Quote.....?..						
1. Bu							
2. Cl	Revision.....?..						
3. Wo							
4. Co	Sub-job.....						
Mainte	Task.....						
11. Cl							
	Print costs..... 0	(0=No/1=Yes)					
	Prices..... 0	(0=No/1=Yes)					
	Mark ups..... 0	(0=No/1=Yes)					
	All levels... 0	(0=No/1=Yes)					
	Text..... 0	(0=No/1=Yes)					
	Transactions. 0	(0=No/1=Summary/2=Transactions)					
F3=Exit F8=Submit F12=Previous							
Option	21						
Search							
05-33 SF MW KS IM II KENB20A PET178S2							

Fields:

Quote

Enter the range of quotations to be printed.

Revision

Enter the range of revisions to be printed.

Sub-Job

Enter the range of sub-jobs to be printed.

Task

Enter the range of tasks to be printed.

Print Costs

0 - Do not print costs.

1 - Print costs.

Prices

0 - Do not print prices.

1 - Print prices.

Mark-ups

0 - Do not print mark-ups.

1 - Print mark-ups.

All Levels

0 - Print top level only.

1 - Print all levels.

Text

0 - Do not print text.

1 - Print text.

Transactions

0 - Do not print transactions.

1 - Print transactions.



When your selection is complete, select
F8=Submit to submit a job to produce the report.

Quotation Enquiry

1...
2...

31/JCG



Take the Quotation Enquiry option to see the selection screen.

JM264	Z1 - GB Demonstration Company	USER GBJBABL	12/02/97
			17:24:57
Quotation Enquiry			
Quote.....?.. <u>AAQ001</u>			
Revision.....?.. _____			
Or			
Customer.....?.. _____			
F3=Exit F4=Prompt			
05-20	SF	MW	KS IM II KENB20A PET179S8

Fields:

Quote/Revision

Select a quotation/revision. If you leave this field blank, you must enter a customer.

Customer

If you enter the customer, a list of quotations will be displayed for selection. If you leave this field blank, you must enter a quotation/revision.



Press **Enter**. If you did not enter a quotation on the first screen you will now see a list of quotation/revisions to select from. Once you have selected one, or if you selected one on the first screen, you will now see the Quotation Enquiry - Details Screen.

Quotation Enquiry Details Screen

This screen lists the jobs you can enquire on.

JM261	Z1 - GB Demonstration Company	USER GBJBABL	12/02/97		
			17:25:27		
Quotation Enquiry - Details		New			
Quote/Revision.. AAQ001		Created 17/07/96			
Description..... Refurbish 'The Blakeney Hotel'					
Customer..... TQA002 000 Weoley Castle Brewery plc					
Opt	Sub-Job/Task	Description	Total Cost	Price	Margin
■		** Header	372.00	375.72	1.00
-	ARCH	Architects' Tasks	372.00	375.72	1.00
-	ARCH	1 Draw Plans	.00	.00	.00
-	ARCH	2 Gain Local Authority Appr	.00	.00	.00
-	M/C	Main Contractors' Tasks	.00	.00	.00
-	M/C	1 Network Plan and Resource	.00	.00	.00
-	M/C	2 Erect Building	.00	.00	.00
-	M/C	3 Quality Assurance	.00	.00	.00
More...					
S=Display 6=Text 7=Expenses 9=Parts					
F3=Exit F5=Refresh F10=Header F12=Previous F17=Position list					
11-02	SP	MW	KS	IM	II KENB20A PET179S0

Fields:

Opt

5 - Display quotation details.

7 - Display any expenses associated with the selected quotation.

9 - Display any parts list associated with the selected quotation.

Functions

F10

Header. Display the quotation header details.



From this screen, you may enquire further to display information regarding the quotation.

Quote Enquiry Details Screen (Option 5)



Enter 5 against a quotation on the Quotation Enquiry Details Screen to see all details for the selected quotation.

JM267	Z1 - GB Demonstration Company	USER GBJBABL	12/02/97
			17:32:29
Quote Enquiry - Details			
Quote/Revision.. AAQ001		Created 17/07/96	
Description..... Refurbish 'The Blakeney Hotel'			
Sub-job/task.... ARCH		Architects' Tasks	
Job status..... 1		New	
Job type..... TKC		Turn-Key Contracts	
Customer..... TQA002		000 Weoley Castle Brewery plc	
Delivery addr... TQA002		008 The Blakeney Hotel	
		The Quay	
		Blakeney	
		Near HOLT	
		Norfolk	
Estimated start date. 1/10/96		Estimated end date. 30/06/97	
Actual start date.... 0/00/00		Actual end date.... 0/00/00	
Selling price..... 375.72		Estimated hours.... .00	
Grant confirmed..... .00		Grant anticipated.. .00	
Income currency..... GBP		Chase date..... 1/08/96	
F3=Exit F12=Previous			
01-02	SE	MW	KS IM II KENB20A PET179S8

Quotation Enquiry Expenses Screen (Option 7)



From the main Quotation Enquiry Details Screen, take option 7 to display any expenses associated with the quotation details.

JM262	Z1 - GB Demonstration Company	USER GBJBABL	12/02/97	
			17:32:55	
Quotation Enquiry - Expenses		New		
Quote/Revision.. AAQ001		Created 17/07/96		
Description..... Refurbish 'The Blakeney Hotel'				
Customer..... TQA002 000 Weoley Castle Brewery plc				
Sub-job/task.... ARCH 000 Architects' Tasks				
Opt	Expense	Cost	Mark Up	Price
-	LAB Labour	.00	.00	.00
-	MAN Manufacturing	372.00	1.00	375.72
-	MAT Materials	.00	.00	.00
				Bottom
7=Transactions				
F3=Exit F5=Refresh F12=Previous F17=Position list				
12-02	SP	MW	KS	IM II KENB20A PET179S0

Quotation Enquiry Transactions Screen (Option 7)



From expenses take option 7 to display transactions.

JM263	Z1 - GB Demonstration Company	USER GBJBABL	12/02/97			
Quotation Enquiry - Transactions			17:33:17			
New						
Quote/Revision.. AAQ001 Created 17/07/96						
Description..... Refurbish 'The Blakeney Hotel'						
Customer..... TQA002 000 Weoley Castle Brewery plc						
Sub-job/task.... ARCH 000 Architects' Tasks						
Expense type.... MAN Manufacturing						
Opt	Item	Route	Cost	Quantity	Mark Up	Price
-	ALCFG	C	372.00	12.00	1.00	375.72
Total			372.00	12.00	1.00	375.72
						Bottom
S=Display						
F3=Exit F5=Refresh F12=Previous F17=Position list						
13-02 SF MW KS IM II KENB20A PET179S8						

Quotation Enquiry Parts List Screen (Option 9)



From the main Quotation Enquiry Details Screen, take option 9 to display any parts lists associated with a quotation detail.

JM268	Z1 - GB Demonstration Company	USER GBJBAAP1	6/02/98
Quotation Enquiry - Parts List			Status 00 = Blanks
Quote/Revision.. AAQ003		Created 4/10/96	
Description..... Extend Railway to Treacle Mine			
Customer..... TQA001 003 Mike Davis (Nurserymen) Ltd			
Sub-job/task.... 000 Extend Railway to Treacle Mine			
Order number.... 0002671			
Part	Description	Quantity	Cost
SN600	Glazed Earthenware Pipes, 18	150.000	1500.00
			Price
			20.00
			Bottom
F3=Exit F5=Refresh F12=Previous F17=Position list F18=Charges			

Quotation Enquiry Parts List Charges Screen (F18)



Select **F18=Charges** from the Quotation Enquiry
Parts List Screen to see the Quotation Enquiry
Parts List Charges Screen.

JM348	Z1 - GB Demonstration Company	USER GBJBAAP1	6/02/98 17:17:23
Quotation Enquiry - Parts List Charges			
Job.....	AAQ003	Extend Railway to Treacle Mine	
Customer.....	TQA001	003	Mike Davis (Nurserymen) Ltd
Sub-job/task....	000	Extend Railway to Treacle Mine	
Order number....	0002671		
Exp Type	Charge Code	Value	
TVL Travelling Expenses	02 Packing Charge	50.00	
F3=Exit F12=Previous			

Quote Header Enquiry Screen (F10)



From the main Quotation Enquiry Details Screen,
press **F10=Header** to display the quotation
header for the quotation.

JM266	Z1 - GB Demonstration Company	USER GBJBABL	12/02/97
			17:40:34
Quote Header Enquiry			
Quote/Revision.. AAQ001		Created 17/07/96	
Job type..... TKC			
Description..... Refurbish 'The Blakeney Hotel'			
Customer..... TQA002		Weoley Castle Brewery plc	
		The Redoubt Brewery	
		210 Bristol Road	
		Weoley Castle	
		BIRMINGHAM	
	B12	2WC	
Customer order.....		WCB-TKC-96/250996001	
Industry code.....		BREWY	
Penalty clause.....		NPC	
Secondary analysis codes..		RR	
Major contract.....		BLAKEH	
F3=Exit F12=Previous			
01-02	SA	MW	KS IM II KENB20A PET179S8