

-
-
-
-
-

Chapter 5

Maintenance



The General Ledger Interface

General Ledger is a prerequisite for the running of Job Management. The interface, however, is optional, and enables Job Management transactions to be posted to financial accounts.

The interface is activated by setting on the General Ledger Active field on the Job Management company profile.

The following options define the structures and control of Job Management postings:

General Ledger Control File

This option specifies:

- the codes you wish to use to compose the GL account.
- the length of each string in the GL account.
- where each string comes in the GL account.

The Masking Options

Each individual code has the string which is to replace it entered against it. Separate options are used for the account code (first 12 characters) and extension codes (last 30 characters) of a GL account.

Job Header



1/JCC

You can set up your job either by converting a quotation into a job, or by setting up a job from scratch.

You can, if you wish, break down a job or project into a hierarchy of sub-jobs and tasks. The top level job, also known as the main job, can have many sub-jobs. Just as a main job can have many sub-jobs, so a sub-job can have many tasks.

If you simply wish to structure jobs as a single time and material entry with a subsequent invoice to a customer, you will have no need for sub-jobs and tasks.

On the system a job is divided into job header and job detail. The purpose of the job header is to hold top level information - for instance, the name of the customer, the analysis codes and the job type.

Job Header Maintenance Screen



Take the Job Header option, and enter a new or existing job number. Press **Enter** to see the Job Header Maintenance Screen.

JM017	Z1 - GB Demonstration Company	USER GBJBAAP1	5/02/98 12:07:10
Job Header Maintenance			
Job number..... COMP21			
Job type....?.. <u>JT1</u> Job Type 1 Rvw/Def			
Description.... <u>CTC test</u>			
Customer..... GC01 Reeves Chemist's 31 Lenton Boulevard Lenton Nottingham England			
NG7 4FW			
Customer order.... _____			
Industry code..?.. _____			
Penalty clause.?.. _____			
Analysis codes.?.. _____ Major contract.. _____			
Cost to complete code.....?.. <u>1</u>			
Maintain labour budget from estimated hours.. <u>0</u> (0/1)			
F3=Exit F4=Prompt F12=Previous			

Fields:

Job Type

Each job must have a job type defined at job level. The job type of each sub-job and task defaults to the job type specified here.

All job types are set up within Parameters Maintenance. If you do not want to have to specify a job type, then set up a blank job type and you can then leave this field blank.

Description

Enter text to describe the job. This field cannot be left blank.

Customer

Enter a valid Accounts Receivable customer. If the customer is part of a hierarchy, it cannot be above level '1' in that hierarchy. The system warns you if the customer has exceeded the credit limit, but you can ignore this. This field cannot be left blank.

Customer Order

Enter a customer order number if applicable. If entered, this becomes the default customer reference on any associated sales order.

Industry Code

Enter an industry code. This field is optional.

Industry codes are created within Parameter Maintenance.

Penalty Clause

Enter a penalty clause. The field is optional.

Penalty clauses are created within Parameter Maintenance.

Secondary Analysis Code

Enter up to eight secondary analysis codes.

These codes are created within Parameter Maintenance.



Note: These codes can be used to analyse jobs in various ways, including running a query or using report generator.

Major Contracts

This field is for memo purposes only.

Cost To Complete Code

If you wish to use cost to complete, enter a relevant code here. These codes must be set up as parameters using the Cost To Complete Codes option.

You can process cost to complete using only one cost to complete code, but if you wish to divide the Cost To Complete Initiation batch job into more than one batch, the cost to complete codes enable you to do this.

If you leave this field blank, the job will not be included in cost to complete processing.

If you want the job to be included in cost to complete calculations, then you must also set the three cost to complete methodology fields in this window. If budgeting is not at expense type level then the cost to complete function will not be available at expense type level.

Maintain Labour Budget From Estimated Hours

0 - Maintain the labour budget for this job from hours entered manually.

1 - Maintain the labour budget for this job from system-calculated estimates.



Press **Enter** to go on to the Job Details Maintenance Screen.

Job Details



2/JCC



Tip: The term job detail refers to a job, sub-job or task. Do not confuse references to job details with references to jobs. Every job is a job detail, but not every job detail is a job - it could be a sub-job or task.

The Job Details option enables you to maintain the details for a job at any level (job/sub-job/task). Remember, the job header holds only the high level job features.

The ability to maintain individual job details means you can store information unique to certain sub-jobs within a project. For instance, start and end dates could vary, and project managers and account managers may differ from task to task within an overall job.

Apart from job detail maintenance, you can attach text to a detail, and a mass update option is provided. You can close and reinstate job details.



Take the Job Details option. The first Job Details Maintenance Screen is displayed.

Job Details Maintenance Screen 1



Take the Job Details option. The first Job Details Maintenance Screen is displayed.

The Job Details option enables you to maintain the details data for a job at any level (job/sub-job/task).

There are therefore three possible entries:

- Job, blank sub-job, blank task
- Job, sub-job, blank task
- Job, sub-job, task.

```
JM055          Z1 - GB Demonstration Company  USER GBJBANB1  29/01/98
                                                    16:51:36

Job Details Maintenance

Job number..?.. AAJM02
Sub-job.....?.. ARCH
Task.....?..  ____

F3=Exit  F4=Prompt
```

Fields:

Job Number

Enter a job number.

Sub-Job

Enter a sub-job code for a job.

When a new sub-job is being created, the job number must already exist.

Task

Enter a three digit task code for a job/sub-job.

When creating a new task, the job number and sub-job for that task must already exist.



Press **Enter** to see the second Job Details Maintenance Screen.

Job Details Maintenance Screen 2



You can get to the second Job Details Maintenance Screen either from the Job Header option (if you are setting up a new job), or from the Job Details option (if you are amending an existing job).

When adding a new sub-job/task to a job, most of the data is already filled in for you from the data recorded at job level. Often these defaults will be correct, but they can be changed if required.

JM055		Z1 - GB Demonstration Company		USER GBJBANB1	29/01/98
Job Details Maintenance 16:51:49					
Job/sub-job/task...		AAJM02 ARCH	Job type... TKC Turn-Key Contracts		
Customer.....		TQA004 000	Old Mutual Properties Limited		
Description.....		Architects' Tasks			
Customer (Detail).?..		TQA004 .?.. 000	Old Mutual Properties Limited		
		Anchor House			
		16 St James's Street			
		LONDON			
Estimated start date		1/09/96	Estimated end date		14/07/98
Actual start date....		0/00/00	Actual end date....		0/00/00
Selling price.....		3322.00	Estimated hours....		.00
Grant confirmed.....		.00	Grant anticipated..		.00
Cost/Price lists..?..		B	Chase date.....		1/08/96
Income currency...?..		GBP	Division..?..		CE Civil Engineering
Profit ctr? 300001		Civil Engineering	Location..?..		SS Scotland: Stranraer
Price type 0 (0/1/2)			Project mgr? IKB		Ian Brown
Region..?.. D86		Dumfries & Galloway	Account mgr? SHY		Sam Younger
Chg time/mat (0/1/2) 0 0		Review 1	Retn type?.. SP		Stage Payments
Status..?.. 40		Order Created	Trnf method 2		(0 - 8)
F3=Exit F4=Prompt F10=Extras F12=Previous F13=Stage payments F14=Budgets					
F15=Parts F16>Returns F17=Override address F18=Activities F24=More keys					

Fields:

Description

Enter up to thirty characters of text to describe the job.

Customer (Detail)

When you are entering a new job detail, and until transactions are recorded against this job detail, you can enter a customer here. This can be different from the customer entered on the job header.

If a parts list exists, you can change the customer in this field until an activity has taken place against the order in Sales Order Processing (for example, stock being allocated).

If a linked customer return exists, then you cannot change this customer.

(Untitled)

This allows multiple site addresses to be associated with the main customer held against the job.

This facility allows each sub-job and or task to have a different site address.

Estimated Start Date

Enter the estimated start date of the job. This is a memo field only.

Estimated End Date

Enter the estimated end date of the job. This is a memo field only.

Actual Start Date

Enter the date the job actually started. This is a memo field only.

Actual End Date

Enter the date the job actually finishes (where applicable). This is a memo field only.

Selling Price

This displays the estimated selling price for this job.

If you change this value, you are taken to the second Variation Entry Screen, to record the change as a variation.

Estimated Hours

The estimated workload for this job is displayed in hours.

If you change this value, you are taken to the second Variation Entry Screen, to record the change as a variation.

Grant Confirmed

The value of any grants applied for and confirmed is displayed.

Grant Anticipated

The value of any grants applied for but as yet unconfirmed is displayed.

Cost/Price Lists

The first of these two fields is for a cost list, the second for a price list.

In the cost list field, enter the list you want to use for labour costs.

In the price list field, enter the list you want to use for labour pricing. T&M job details must have a price list defined. Non T&M job details cannot have a price list defined.

Chase Date

You can enter a date which could be used as a prompt to contact the customer, or as a reminder to the project manager. Further details of the prompt date could be described in the internal text (**F21**).

Income Currency

A valid currency is required for invoicing this job. It defaults to the base currency.

Division

Enter the division of the company providing the service.

Profit Ctr

Enter the profit centre to be used.

Location

Enter the location of the company providing the service.

Price Type

Select the price type for this particular job/sub-job/task.

0 - Fixed price. The **F14=Budgets** button is disabled if you select this price type.

1 - Non chargeable.

2 - Time and materials.

This field cannot be left blank.



Note: Once the job has been entered and validated the price type cannot be changed. You cannot, for example, change over to a time and materials job midway through a fixed price task. You would instead have to create a new task within the sub-job. This is a security feature.

Project Mgr

Enter the project manager. Transactions and/or invoices can be reviewed by project manager.

Region

Enter the region code.

Account Mgr

Enter the account manager.

Chg Time/Mat

0 - Do not charge. In this case you can allocate timesheets or materials against the job level, but you will not invoice that customer for the time or materials allocated.

1 - Charge for time or materials. You cannot use this setting if the price type is fixed or non-chargeable. If, for example, the Chg Time field is set to 0, then you can allocate timesheets against the job level, but you cannot invoice that customer for the time allocated.

2 - You will make the decision whether or not to charge when you are reviewing this transaction in the Chargeable Transaction Review option.

If you enter 2 in the Chg Time field, then the Cost Category/Rate Override Window in the Employee Timesheets option will enable you to enter income.

If you enter 2 in the Chg Mat field, and this defaults through to an Inventory posting, then that posting will automatically appear in the Chargeable Transaction Review.

One of these fields must be set to 1 or 2 for this job to be accepted as a time and materials job.

These settings are used as defaults. Direct transactions will pick up either the time or the materials setting, depending on the expense type. Timesheets will pick up the time setting, and Inventory postings and expenses the materials setting.

Review

- 0 - Do not review invoices.
- 1 - The invoices for this job are to be reviewed before printing.

Retn Type

Enter the retention type. This field is for memo purposes only.

Status

Select a valid status. When adding a new job/sub-job/task, it will default to status 01 (job open).

User-defined status codes are set up as open jobs. Both costs and income can be captured until the job has been closed. When you close the job, the status 99 prevents any further transactions for the job.

Trnf Method

See the matrix below for details on how each individual transfer method works.

Transfer method	Initial posting	Transferred to	Transfer process required	Release process required	Close process required
0	P&L	N/A	N/A	N/A	N/A
1	WIP	P&L	Yes	No	No
2	WIP	P&L	Yes	Yes	No
3	WIP	P&L	Yes	Yes	Yes
4	WIP	FA	Yes	No	No
5	WIP	FA	Yes	Yes	No
6	WIP	FA	Yes	Yes	Yes
7	WIP	N/A	N/A	N/A	N/A
8	WIP	P&L/FA	Yes	N/A	Optional



Note: In the above table:

WIP - Work in progress.

P&L - Profit and loss.

FA - Fixed Assets module.

Initial Posting

This is the place in the General Ledger that costs are posted to when initially posted to the GL.

Transferred To

Shows where costs are transferred to when released from WIP.

Transfer Process Required

This indicates whether the transfer needs to be initiated via a menu option or options.

Release Process Required

Yes - The transfer process will only transfer those costs defined via the Release Job option.

No - The transfer process will process all costs still in WIP.

Close Process Required

Yes - The Release Job procedure will only be allowed for closed jobs.

No - It is not necessary to close jobs before the release process can be used.



Note: To get costs with a transfer method of 7 out of WIP you must change the transfer method.



Press **Enter** to validate any job detail amendments.

Functions:

F10

Extras. This brings up the third Job Details Maintenance Screen, which enables you to enter cost to complete and Fixed Asset details. This function key is not available when you are adding a job detail, or the transfer method is not 4, 5, 6 or 8, or you are not using cost to complete.

F13

Stage Payments. For any job level defined as a fixed price job, stage payments can be set up so that as certain dates arrive, or all listed activities are completed, you can generate invoices automatically (subject to user defined review).

VAT codes entered can be used if the customer's VAT indicator is set to '3'. If it is '2', these codes are ignored in favour of the VAT code set up in the customer master file.

F14

Budgets. If you wish to maintain budgets from here press F14. The application defaults to the budget code and to the job number you are now in. However, any budget is accessible.

F15

Parts. This enables you to create an SOP order within this option. The order header is created automatically, based on the customer details in SOP/AOE, and you are taken into the Amend Order option in SOP/AOE.

When you have entered the parts list, a confirmation window is displayed. This gives the new order number, and gives you a choice of invoicing method. If you select job invoicing, then costs that are invoiced will also be posted within Job Management. If you select SOP invoicing, then costs are not posted within Job Management. The latter option would be rarely used by most people - use it only if you are selling supplies with a machine, and if the Post Customer Issues field on the company profile is set to on.

See the Inventory Costs Via SOP/AOE section.

F16

Returns. This enables you to generate customer returns and receive against them via Job Management. The returns number is used for each return against the parts list sales order.

If the RTN process code is active when a customer return is generated, the status of the job detail changes to that associated with the RTN code.

If the RCV process code is active when a customer receipt is made against the return, the status of the job detail changes to that associated with the RCV code.

F17

Override Address. This displays the delivery and invoice addresses of the customer specified on the job detail, and enables you to change these addresses. If the job detail has a parts list, then Sales Order Processing will also be updated with any new address.

F18

Activities. Stage payments can be made on completed activities (but only when all the listed activities have been completed).

F19

Maintain Costs. Enables you to attach an item to a job detail, detach it from the job detail, or amend the item. A selection list is shown if any already exist. The Production Cost Maintenance - Detail Screen is displayed.

F20

Customer Contracts. Enables you to link to a contract in Advanced Customer Scheduling. The Link Items To Contracts - Selection Screen is displayed.

F21

Internal Text. Text can be maintained for view only by you. Each job detail can have multiple lines of text that is internal to the system. The text can be maintained and altered throughout the life of the job.

F22

External Text. Text to appear on invoices about this job number. External text is text which defaults to all invoice lines with respect to the appropriate job detail.

The text can be amended at a review stage (if review flags are active) prior to printing of invoices.

F23

Service. The contracts selection screen will only include detail if the customer is a service customer and already has installed equipment on a service contract.

F24

More Keys. This key displays any function keys hidden because of lack of space.

Job Details Maintenance Screen 3



Take **F10=Extras** from the second Job Details Maintenance Screen to see the third Job Details Maintenance Screen, or press **Enter** on a job detail that has a transfer method of 4, 5, 6 or 8.



Note: If you are using transfer method 8, then all the Fixed Asset related fields on this screen are optional. Any information you enter will be used as defaults in the Invoice/Asset Generation option, when you come to capitalise or invoice the item.

JM055	Z1 - GB Demonstration Company	USER GBJBATD0	15/10/97 16:51:36
Job Details Maintenance			
Job/sub-job/task...	COMP21	0	CTC test
Customer.....	GC01	000	Reeves Chemist's
Cost to complete methodologies :-			
Labour.....?	1		
Material.....?	1		
Other direct....?	1		
Asset Number.....	_____		
Asset Group.....?	_____		
FA reason.....?	_____		
Depreciation rate..	_____	.00	
Depreciation life..	_____	0	
Multiple assets....	0	(0/1)	
F3=Exit F4=Prompt F12=Previous			
9-22	SA	YW	KS CL IM DM II STUD140 KB PKH317S1

Fields:

Labour

This field is only displayed if the Include In Cost To Complete field on the Job Header Maintenance Screen is set to on.

Enter the default method to be applied for labour in cost to complete. The methods available are as follows:

- 1 - Finish budget on time.
- 2 - Continue at same level of efficiency.
- 3 - Complete at standard rate.
- 4 - Input the degree of inefficiency to apply to rest of job.
- 5 - Input the degree of efficiency.
- 6 - Enter hours to complete.



Tip: For more details on these methods, turn to

the Cost To Complete Maintenance section.

Material

This field is only displayed if the job header is set to use cost to complete.

Enter the default method to be applied for materials in cost to complete. The methods available are as follows:

- 1 - Based on commitments.
- 2 - Based on original estimate.
- 3 - Enter revised estimate.



Tip: For more details on these methods, turn to the Cost To Complete Maintenance section.

Other Direct

This field is only displayed if the job header is set to use cost to complete.

Enter the default method to be applied for other direct costs in cost to complete. The methods available are as follows:

- 1 - Based on commitments.
- 2 - Based on original estimate.
- 3 - Enter revised estimate.



Tip: For more details on these methods, turn to the Cost To Complete Maintenance section.

Asset Number

You must enter an asset number to be created or amended within Fixed Assets when a cost for this job detail is transferred.

Asset Group

Enter an existing asset group.

FA Reason

Enter an existing Fixed Asset reason code to be held against asset when it is created. This is an optional field.

Depreciation Rate

The depreciation rate is recorded against appropriate depreciation methods in the asset group, but if entered here, this rate is used to override the depreciation rate for all depreciation methods not equal to 004 for this particular job detail.

Depreciation Life

The depreciation life is recorded against appropriate depreciation methods in the asset group, but if entered here, this rate is used to override the depreciation rate method 004 for this particular job detail.

Multiple Assets

0 - This will generally mean that all costs for a job detail will be capitalised to one asset.

1 - (For serial controlled Inventory items only). The asset name is automatically truncated to 11 characters (left justified), and the system automatically generates sequential numbering for the last 4 characters. No embedded blanks are allowed.

Example 1

Asset number - ABCDEFGHIJKLMNO (15 characters)

Truncated to - ABCDEFGHIJK

Resulting numbers - ABCDEFGHIJK0001, ABCDEFGHIJK0002

Example 2

Asset number - ABCD

Resulting numbers - ABCD0001, ABCD0002



Note: At the time of capitalisation, any non-serial-controlled Inventory item costs are not capitalised, and are written to the General Ledger write-off account (as specified in the company profile).



Note: If a transfer method is changed from 4, 5 or 6 to a value other than 4, 5 or 6, then the fixed asset data will be cleared for the job detail.

Invoice/Delivery Address Maintenance Screen (F17)



Select **F17=Override Address** on the second
Job Details Maintenance Screen to see the
Invoice/Delivery Address Maintenance Screen.

JM341		Z1 - GB Demonstration Company		USER GBJBABL	18/06/97
					12:21:10
Invoice/delivery address maintenance					
Job/Sub-Job/Task: BJBT&M S001 1					
Description.....: T&M Trasfer method 2					
Customer.....: CS1 000 Customer 1					
Invoice name & address			Delivery name & address		
Customer 1			Customer 1		
1 High St			1 High St		
Redditch			Redditch		
F12=Previous					
12-02	SP	MW	KS	IM	II EDN400A PE9106S2

Fields:

Invoice Name and Address

(Untitled Fields)

Enter the invoice name and address in the fields provided, in the format in which you want them printed. The details will be picked up by Sales Order Processing, where appropriate.

Delivery Name and Address

(Untitled Fields)

Enter the delivery name and address in the fields provided, in the format in which you want them printed. The details will be picked up by Sales Order Processing, where appropriate.

Production Cost Maintenance Detail Screen (F19)



When **F19=Maintain Production Costs** is selected on the second Job Details Maintenance Screen, the Production Cost Maintenance Detail Screen is displayed.

JM333	Z1 - GB Demonstration Company	User GBJBAP1	5/02/98
Production Cost Maintenance - Detail			14:55:36
Job/sub-job/task..... AAJM02 000 'The Marine' Office Block			
Item?... GM1PD0050C1 pd 0050 component 1			
Route... 1	Cost set... _____	Quantity.... 250.00	
Cost Element	Attached Cost	Current Cost	%
1. Relief Costs	12.00000	12.00000	
2. Direct Material	2.00000	2.00000	
3. Packaging	1.00000	1.00000	
4. Resource	1.00000	1.00000	
5. Labour	3.00000	3.00000	
6. Set-up		-	
7. Machine			
8. Subcontract			
9. Overhead 1			
10. Overhead 2 Fixed			
11. overhead 2 Variable			
12. TOOLING			
13. User 2			
14. User 3			
15. User 4			
Total Unit Cost (excludes **)	5.00000	5.00000	
Mark up _____	Total Unit Price 5.00	5.00	
F3=Exit F4=Prompt F5=Refresh with current costs F8=Update F12=Previous			

Fields:

Route

Enter the route as required.

Cost Set

Enter the cost set as required.

Quantity

This is a memo field for a quantity.

Attached Cost

Job Management costs are shown, if they already exist. If you are adding costs for the first time, then when you press **Enter** the system automatically transfers all costs from the current cost set shown to the attached costs.

Mark Up

Any percentage mark-up entered here will be applied to the attached costs to give the total unit price.

Total Unit Price

If you choose to enter the value here, the system will automatically calculate the mark-up.

Function

F5

Refresh With Current Costs. This key moves the current costs to the attached costs.



Select **F8=Update** when you have added the costs you want.

Link Items To Contracts Selection Screen (F20)



When **F20=Customer Contracts** is selected on the second Job Details Maintenance Screen, the Link Items To Contracts Selection Screen is displayed.

This screen lists the items attached to the task.

JM331		Z1 - GB Demonstration Company		User	GBJBABLT	12/02/97
						16:50:37
Link Items to Contracts - Selection						
Job/Sub-Job/Task.... BJBT&M 000						
Description..... T&M Transfer type 4						
Delivery Address.... CS1 000 Customer 1						
Item	Description	Route	Contract			
_ GM1PD0050C1	pd 0050 component 1	1	0000100			
Bottom						
1=Attach 2=Detach						
F3=Exit F12=Previous						
10-03 52 MW KS IM II KENB20A PET179S0						

Fields:

(Untitled)

Select. You can enter the following:

- 1 - Attach. Select an item for linking to a contract.
- 2 - Detach. Detach an item.

Job Detail Activities



3/JCC

Stage payments are triggered when either of the following happens:

- The payment date arrives.
- An activity which has been linked to a stage payment is completed.

Activities and stage payments are set up for fixed price jobs. The two must be linked, and the stage payment is made when you input the activity's completion date.

Activity codes are set up via the Activity Codes option. Once set up, you can use this option to assign start and completion dates to the codes, so that if activity codes are linked to a stage payment, the payment will not be made until all listed activities are complete.



Take the Job Detail Activities option, and enter the job detail you wish to set up or maintain activities for. Press **Enter** to see the Job Detail Activity Maintenance Screen.

Activity Code

Enter an existing activity code. This is optional, as the activity can simply be a start date.

Text

Enter text for the activity. More text is available using option 1.



Press **Enter**, and selection fields will appear beside all lines with activities in them. The entries you have made are now updated on the system.

Stage Payment Linkage Screen (Option 3)



Enter 3 against an activity on the Job Detail Activity Maintenance Screen to see the Stage Payment Linkage Screen.

This screen is where you link stage payments to activities. It lists all activities already linked to payments.

```

JM144                Z1 Amalgamated Amalgamations PLC    User GBJBANB1    8/05/96
                                                           13:02:09

Job Detail Activities - Stage Payment Linkage

Job/sub-job/task.... ACTIVI          Activity Test
Customer..... ANS      000
Activity..... 15/05/96 (Open)
Activity code..... AC1          Activity Code 1
Income currency.... GBP

      Stage      Activity
      Payment no. Code      Amount      Linked to      Other
      -          -          -          -          -          -
      3          AC2      5000.00          0          0
      6          AC1      100.00          0          0
  
```

1=Link 2=Detach 3=Display linked activities 4=Text
 F3=Exit F9=Include processed payments F12=Previous

13-03 **SE** MW KS IM II KENB20A PET149S2

Fields:

(Option)

- 1 - Link this payment to the activity.
- 2 - Sever the link.
- 3 - Display all activities linked to this stage payment.
- 4 - Stage payment text maintenance. You can copy in activity text.

Functions:

F9

Include processed payments in the list - i.e. all completed stage payments.

Budgets



4/JCC

Every job detail can have multiple budgets attributed to it. Each budget can be broken down by period.

This procedure creates a budget or management forecast for any year in the base currency of the Job Management system. Budget/forecasts can be set at any job level. The system automatically 'roll up' budgets from a lower level through the job hierarchy. However, it is possible to record a 'rolled up' budget at a higher level and protect it from being 'overwritten' during the automatic 'roll up' process.

There are thus six budgets that can be created within one budget code:

- Job/blank/blank.
- Job/sub-job/blank.
- Job/sub-job/task.
- Job/blank/blank/expenses.
- Job/sub-job/blank/expenses.
- Job/sub-job/task/expenses.



There are two sources of entry to the first Budget/Forecast Maintenance Screen. You can either take the Budgets option, or press **F14** from the Job Details Screen.

Budget/Forecast Maintenance Screen 1



There are two sources of entry to the first Budget/Forecast Maintenance Screen. You may either take the Budgets option, or press **F14** from the job details screen.

```
JM061          Z1 Amalgamated Amalgamations PLC  USER GBJBANB1  7/05/96
                                                    17:04:27

Budget/Forecast Maintenance

Budget code and type?... BUD 1 (0=Forecast, 1=Budget)

Job.....?.. JNB001
Sub-job.....?.. 
Task.....?.. 
Expense type.....?.. 

Start year..... 96

F3=Exit  F4=Prompt

05-27  82  MW  KS  IM  II  KENB20A  PET149S2
```

Fields:

Budget Code And Type

Select a valid budget code and type.

Budget Type

0 - Forecast.

1 - Budget.



Note: There is no functional difference between the two.

Job

You must select a valid job.

Sub-Job/Task

Depending on the level at which you wish to budget, you can optionally enter a sub-job and task at which to forecast/budget.

Expense Type

If you wish to budget down to expense type level, select a valid expense type.

Start Year

The year from which you wish the display to begin.



Multiple budgets are also catered for in Job Management. These 'budgets' are user defined and can either be classified as a budget or as a forecast. These budgets are added and maintained within the parameter maintenance option.



Remember you must enter a valid year. Press **Enter** to see the second Budget/Forecast Maintenance Screen.

Budget/Forecast Maintenance Screen 2



Press **Enter** on the first Budget/Forecast Maintenance Screen to see the second Budget/Forecast Maintenance Screen.

Entries to maintain budget codes are made here. Values are in the base currency of the Job Management company. Roll down to see more details. You can only roll forward from any starting point.

You do not have to enter a breakdown of the individual period values. If you do not need to break down budgets by period then just enter the total budgets. The breakdown entered does not have to agree with the total value.

JM061		Z1 Amalgamated Amalgamations PLC		USER GBJBANB1	7/05/96 17:05:13
Budget/Forecast Maintenance					
Budget code & type... BUD 1		Default Budget Code			
Job/sub-job/task..... JNB001		Job NB 001			
Expense type.....					
	This Level Budget	Rolled Up Budget	Pr		
Total	.00	.00	0		
Period					
9601	.00	.00			
9602	.00	.00			
9603	.00	.00			
9604	.00	.00			
9605	.00	.00			
9606	.00	.00			
9607	.00	.00			
9608	.00	.00			
9609	.00	.00			
9610	.00	.00			
9611	.00	.00			
9612	.00	.00			
+					
F3=Exit F4=Prompt F8=Update F12=Previous					
08-21 SP MW KS IM II KENB20A PET149S2					

Fields:

This Level Budget

The budget for costs which are relevant to this job level only are entered here.



Note: A budget is for a project, not for a year.

Rolled Up Budget

The budget for costs which include budgets from lower levels of the job. If you wish to budget at all levels and wish the system to automatically roll up through the job hierarchy, then do not enter budgets here.

Rolled up budgeting works in the exact same manner as the roll-up for cost transactions.

Pr

Priority.

1 - Protect your rolled up budgets from being overwritten by the automatic roll-up process.

0 - Allow the automatic roll-up.



Note: If you change a budget, you are now taken automatically to the second Variation Entry Screen, where the variation is recorded.



Select **F8=Update** to validate and update any changes made to budgets.

Close/Reinstate Job

1... **2...** 5/JCC

The primary purpose of closing jobs is two-fold:

- If the job or project (or part of one) has effectively finished, then you can close the job so that no more transactions can be posted to that job number.
- The use of transfer methods 3 or 6 indicates that jobs must be closed before costs can be released from WIP.

Close/Reinstate Jobs Screen



Take the Close/Reinstate Job option to see the Close/Reinstate Jobs Screen.

```
JM200          Z1 Amalgamated Amalgamations PLC  USER GBJBANB1  10/05/96
                                                    11:53:05

Close/Reinstate Jobs

Job/sub-job/task.....?.. ACTIVI  ____  ____
All levels..... 0 (0/1)
Close/reinstate..... 1 (0=Close, 1=Reinstate)

F3=Exit  F4=Prompt  F8=Confirm request

05-29  SP  MK  KS  IM  II  KENB20A  PET149S2
```

Fields:

Job/Sub-Job/Task

Enter a valid job number. If a job/sub-job is entered, you can close the specified level and all levels below it (i.e. all tasks associated with that job or sub-job).

All Levels

0 - Close/reinstate only the job detail entered.

1 - The job detail at the specified level and all lower levels are to be closed/reinstated.

Close/Reinstate

0 - Close the level(s). Jobs cannot be closed if there is a standing cost waiting to be reversed, or if there is an outstanding commitment.

1 - Reinstate the level(s). Reinstated jobs are given a status code of '01' (open).



Note: Jobs cannot be reinstated if the job detail has a transfer method of 3 or 6.



Press **F8=Confirm Request** to submit the job for processing. A report of all jobs reinstated or closed is produced, and any failed jobs are listed with reasons for failure.

Mass Update

1...

2...

6/JCC

This option enables you maintain a job detail at a specified level and have the amendments taken on at all levels below.

 Take the Mass Update option to see the details screen.

JM210

Z1 - GB Demonstration Company

USER GBJBATD0

15/10/97
16:53:22

Job Details - Mass Update

Job/sub-job...?..

Data Field	Reqd? (0/1)	New Value	Chk Val? (0/1)	Existing Value
Customer.....?..	0		0	
Income currency.....?..	0		0	
Profit centre.....?..	0		0	
Region.....?..	0		0	
Division.....?..	0		0	
Location.....?..	0		0	
Project manager.....?..	0		0	
Account manager.....?..	0		0	
Retention type.....?..	0		0	
Transfer method.....?..	0		0	
Status.....?..	0		0	
Cost list.....?..	0		0	
Price list.....?..	0		0	
Methodology-Labour.....?..	0		0	
Methodology-Material...?..	0		0	
Methodology-Other direct.?..	0		0	

F3=Exit

F4=Prompt

F8=Submit

4-20

SR

MW

KS

CL

IM

DM

II

STUD140

KB

PKH317S1

 Roll down to see the remaining fields:

JM210

Z1 - GB Demonstration Company

USER GBJBATD0

15/10/97
16:54:00

Job Details - Mass Update

Job/sub-job...?..

Data Field	Reqd? (0/1)	New Value	Chk Val? (0/1)	Existing Value
Asset number.....?..	0		0	
Asset group.....?..	0		0	
Fixed asset reason code..?	0		0	
Depreciation rate.....	0		0	
Depreciation life (prds)..	0		0	

F3=Exit

F4=Prompt

F8=Submit

4-20

SR

MW

KS

CL

IM

DM

II

STUD140

KB

PKH317S1

Fields:

Job/Sub-Job

If a job is entered, then all the sub-jobs and tasks for that job are affected by the change. If a sub-job is entered, then that sub-job and all its associated tasks are affected.

If this field is left blank, any changes will update all job details for the whole company. Confirmation of this request is required.

Reqd?

0 - No amendment required.

1 - This field is to be amended.



Note: With regard to job details with a status of '99' that is closed with no further transactions or invoices allowed, the following rules apply:

An existing status value of '99' is not allowed.

A new value of '99' is not allowed.

You can not change the value of a status already set to '99'.

New Value

Enter the value to which the job detail is to be updated.

Chk Val?

1 - You wish to check for an existing value.

Existing Value

This field is optional. If an existing value is entered, then a job detail is only altered if its existing value equals this entry.

An audit report is produced for the changed job details.

Cost/Price Lists

7/JCC

Cost and price lists provide you with a very flexible means of identifying the hourly rates applying to costs and income. You can set up an hourly rate according to an employee's grade, and you can also set up a standard rate for each list to act as a default for zero rated grades.



Note: If you are upgrading from an earlier version of System 21 Job Management, then this new method of setting up costs replaces cost/income rate categories A to H.

A list is defined by its list code, the list type (cost or price), its currency and its effective date. This means that you can use the same code for different currencies, and the same code for the cost list and the price list, if you wish.

Cost/Price List Maintenance Selection Screen



Select the Costs/Price Lists option to see the Cost/Price List Maintenance Selection Screen.

JM338	Z1 - GB Demonstration Company	USER GBJBATD0	13/10/97 14:09:28
Cost / Price List Maintenance			
List type..... 1	(1=Costs, 2=Prices)		
List code.....?.. 001			
Currency code...?.. GBP			
Effective date...?.. 13/10/97			
F3=Exit F4=Prompt			
9-21 SA MW KS CL IM DM II STUD140 KB PKH317S1			

Fields:

List Type

Enter one of the following:

- 1 - Cost list.
- 2 - Price list.

List Code

Enter a new or existing cost or price list.

Currency Code

Enter the list currency.

Effective Date

Enter the date on which the list is to become effective. This defaults to the system date.



Press **Enter** to see the Cost/Price List Maintenance Detail Screen.

Cost/Price List Maintenance Detail Screen



Press **Enter** when you have made your selection on the Cost/Price List Maintenance Selection Screen, and you will see the Cost/Price List Maintenance Detail Screen. This screen is the almost identical whether you selected a price list or a cost list - the only difference being the screen description.

JM338	Z1 - GB Demonstration Company	USER GBJBATD0	13/10/97 14:14:25
Cost List Maintenance			
Cost list..... 001 Effective date... 13/10/97			
Currency..... GBP Pounds Sterling			
Description... Costs - Labour rates			
Standard rate.. 14.27			
Grade?	Description	Hourly rate	
- A/M19	A/Manager: Grade 19	25.50	
- CH/HD	Charge-Hand	.00	
		.00	
		.00	
		.00	
		.00	
		.00	
		.00	
		.00	
4=Delete			
F3=Exit F4=Prompt F11=Delete F12=Previous			
7-18 SA MW KS CL IM DM II STUD140 KB PKH317S1			

Fields:

Description

Enter a description for the list.

Standard Rate

You can enter a standard rate for the list, which will apply in all cases except those overridden by a particular grade entry in the list lower down the screen.

This rate is also used in labour commitment valuation.

Untitled

Selection field. Enter '4' against a grade to delete it.

Grade

Enter the labour grades which are allowed within this list. These must be defined to Job Management already, and in the case of cost lists the grade currency must be the same as that of the list itself.

You can if you wish enter a rate different to the standard for any grade specified.

You cannot enter more than 200 separate grades here.

Description

The grade description will be displayed when you press **Enter**.

Hourly Rate

Enter the hourly rate for the grade you have entered. This must not be negative.



Press **Enter** to update.

Variations



8/JCC

The way System 21 Job Management records and handles variations provides a complete audit trail of all changes to selling prices, estimated hours and budgets, so accurate original and variation values can be produced in cost to complete reports.

You can enter variations at either job detail level or expense type level.

Each variation is numbered, with the original being '000', the first variation '001', and so on. Each has a date and a record of which budget was affected by the change, if any.

What is a Variation?



Tip: Not every change to a price, hours or budget is a variation.

Suppose you set up a price, hour or budget at the start of the job with a value of zero, then you change it. This change is not a variation, and the change will simply be recorded on the original '000' record. This is because a starting point of zero is not considered to be a true value.

Any other change is recorded as a variation. The system can tell the difference between an original value of zero (i.e. the '000' record) and a value which has been set to zero during the course of the job (i.e. anything other than '000'), so such variations will not be overlooked.

Variation Entry Selection Screen

 Take the Variations option to see the Variation Entry Selection Screen.

JM357Z1 - GB Demonstration CompanyUSER GBJBATD016/10/9712:04:29

Variation Entry

Job/sub-job/task.....?.. 30MP21 ____

Current budget code...?.. ____

F3=Exit F4=Prompt

5-27SA MW KS CL IM DM II STUD140 KB PKH317S1

Fields:

Job/Sub-job/Task

Enter the job detail to which the variation is to apply.

Current Budget Code

If this variation is to apply to a budget, then enter that budget here.

 Press **Enter** to see the first Variation Entry Screen.

Variation Entry Screen 1



Press **Enter** on the Variation Entry Selection Screen to see the first Variation Entry Screen.

This screen displays the original value, with any existing variations listed in reverse arrival order - that is, with the latest first. This is decided not by the date field but by the variation number.

JM357		Z1 - GB Demonstration Company		USER GBJBATD0	16/10/97 12:26:33
Variation Entry					
Job/sub-job/task.. COMP21		CTC test			
Originals..	Budget	Code	Estimated Hours	Selling Price	
Current....	.00		340.00	.00	
	.00		.00	.00	
Var	Date	Reference	Reason	User ID	
- 4	16/10/97	T55303	UE Under Estimate	GBJBATD0	
		135.00	ALT		.00
- 3	16/10/97		UE Under Estimate	GBJBATD0	.00
		1650.00	ALT		.00
- 2	16/10/97		UE Under Estimate	GBJBATD0	.00
		.00	ALT		.00
- 1	16/10/97		UE Under Estimate	GBJBATD0	.00
		1650.00	ALT		.00
					More...
1=Text					
F3=Exit F6=Add variation F12=Previous					
21-39 SP MW KS CL IM DM II STUD140 KB PKH317S1					

Fields:

Originals

The three original values - budget, estimated hours and selling price - are displayed. These are the '000' variation values.

Current

The current values corresponding to the original values for budget, estimated hours and selling price are displayed. The budget is the job detail budget for the budget entered on the Variation Entry Selection Screen. The estimated hours and selling price are the 'this level' values for the job detail.

Untitled

Selection field. Enter '1' against a variation to display or enter text for it.

Var

The variation number is displayed, with the latest variation first.

Date

Enter a date against the variation.

Reference

The variation reference is displayed.

Reason

This displays the reason code entered against the variation.

User ID

This is the user ID of the person who entered the variation.

Untitled

The word 'Text' is displayed in high intensity letters beside the user ID if there is any text for this variation.

Budget

The new budget value, after the variation, is displayed if this particular variation affects a budget.

Code

The budget code is displayed if this particular variation affects a budget.

Estimated Hours

These are the new estimated hours, after the variation.

Selling Price

This is the new selling price, after the variation.

Functions:**F6**

Add variation. This takes you to the second Variation Entry Screen.

F9

By expense type. This is highlighted if any expense type variations exist, and when you select it you see the third Variation Entry Screen.

Variation Entry Screen 2 (F6)



There are three routes into this screen:

- Select **F6=Add Variation** from the first Variation Entry Screen to see the second Variation Entry Screen.
- If you change a budget at job detail or expense type level within Budget Maintenance, you will be taken to this screen automatically.
- If you change selling prices or estimated hours within Job Detail Maintenance, you will be taken to this screen automatically.

You may have one, two or three columns on your screen, depending on the kind of variation you are entering, and these will be headed 'Budget', 'Estimated Hours' and 'Selling Price'.

JM359		Z1 - GB Demonstration Company		USER GBJBATD0	16/10/97
					12:29:01
Variation Entry					
Job/sub-job/task... COMP21		CTC test			
Budget code....?.. <u>BJD</u>					
		Budget	Estimated Hours	Selling Price	
Current value.....		.00	.00	.00	
New value.....		<u>145</u>	<u>.00</u>	<u>.00</u>	
Percentage change.....		<u>.00</u>	<u>.00</u>	<u>.00</u>	
Update budget code.?.. <u>ALT</u>					
Date..... <u>16/10/97</u>					
Reference..... <u>U7720</u>					
Reason.....?.. <u>UE</u>					
F4=Prompt F12=Previous F16=Maintain period budgets					
7-21 <u>SR</u> <u>MW</u> KS CL IM DM II STUD140 KB PKH317S1					

Fields:

Budget Code

If you arrived at this screen from the first Variation Entry Screen then this holds the budget you entered on the Variation Entry Selection Screen, if any.

If you arrived at this screen from within Budget Maintenance then this holds the budget you were maintaining.

If you arrived at this screen from within Job Detail Maintenance then the budget is blank.

Current Value

The current value is displayed under each heading.

New Value

Enter the new value for the budget, hours and/or price. You cannot enter a percentage change if you enter a new value.

Percentage Change

This is an alternative to entering a value for the budget, hours and price. You can enter a percentage change and the system will calculate the resulting value for you. You cannot enter a percentage change if you enter a new value.

Update Budget Code

Enter here the budget which is to be updated with the variation.

This field only appears if you are entering budget variations, or if you are entering estimated hours variations and your job is set up as maintaining labour budgets from estimated hours.

Date

This is the variation date, and defaults to the system date.

Reference

Enter a variation reference, if you wish.

Reason

You must enter a reason code for every variation.

Functions:**F16**

Maintain period budgets. This is available only if you have changed the budget value, and takes you into Budgets Maintenance, bypassing the selection screen and prefilling the detail fields. Only period values can be maintained this way.

Variation Entry Screen 3 (F9)



Select **F9=By Expense Type** from the first Variation Entry Screen, or select **F6=Add Variation** from the fourth Variation Entry Screen, to see the third Variation Entry Screen.

JM357		Z1 - GB Demonstration Company		USER GBJBATD0	16/10/97 12:12:04
Variation Entry					
Job/sub-job/task.. COMP21		CTC test			
Originals..	Budget	Code	Estimated Hours	Selling Price	
Current....	.00		340.00	.00	
	.00		.00	.00	
Expense Type		Original Budget	Current Budget		
■ CON External Consultants		.00	.00		
- EXP Employee Expenses		.00	.00		
- INV Inventory		.00	.00	Variations	
- LAB Labour		12500.00	12500.00	Variations	
- MAN Productioning		.00	.00		
- MAT Materials		.00	.00		
- P/H Plant Hire		.00	.00		
					Bottom
1=Select					
F9=Exit F12=Previous					
12-2 SP MW KS CL IM DM II STUD140 KB PKH317S1					

Fields:

Originals

The original values for budget, estimated hours and selling price are displayed.

Current

The current values for budget, estimated hours and selling price are displayed.

Untitled

Selection field. Enter '1' against a job/sub-job/type/expense type to see the fourth Variation Entry Screen.

Expense Type

This column lists all the expense types allowed for the job's job type, plus all variations already recorded (bearing in mind that an expense type could have been removed from the job type after a variation had been recorded).

Original Budget

This displays the original budget.

Current Budget

This displays the current budget.

Untitled

Variations. If any variations exist for this expense type, then the word 'Variations' appears alongside the current budget value.

Variation Entry Screen 4

 Select an expense type on the third Variation Entry Screen to see the fourth Variation Entry Screen, which displays all the variations for the selected expense type.

JM357Z1 - GB Demonstration CompanyUSER GBJBATD016/10/9712:30:54

Variation Entry

Job/sub-job/task.. COMP21CTC test

Budget Code

Estimated Hours

Selling Price

Originals..

.00

340.00

.00

Current...

.00

.00

.00

Expense Type

Original Budget

Current Budget

LAB Labour

12500.00

12500.00

Var

Date

Reference

Rsn

Budget

Code

User ID

1

16/10/97

UE

12500.00

BUD

GBJBATD0

-

15/09/97

.00

GBJBAP1

1=Text

Bottom

F3=Exit

F6=Add variation

F12=Previous

14-2

SA

HW

KS

CL

IM

DM

II

STUD140

KB

PKH317S1

Fields:

Untitled

Selection field. Enter '1' against a variation to add or amend text. If the variation already has text, the word 'Text' is highlighted at the end of the row, beside the user ID.

Var

Variation. This is the number of the variation, displayed with the latest variation first.

Date

Enter a date for the variation.

Reference

The variation reference is displayed.

Rsn

This displays the reason code entered against the variation.

Budget

The budget value is displayed, where relevant.

Code

The budget code is displayed, where relevant.

User ID

This is the user ID of the person who entered the variation.

Untitled

The word 'Text' is displayed in high intensity letters beside the user ID if there is any text for this variation.

Functions:**F6**

Add variation. This enables you to add a variation. You will see the third Variation Entry Screen.

Copy Job Or Copy Job To Quote

Copy Job

11/JCC

The Copy Job option enables you to create a new job with an inherent hierarchy based on a hierarchy already existing in another job. All sub-jobs will be copied.

Certain details are copied over from the existing job. This data is copied over from the job header and the job detail maintenance.

All data on the job header is copied over, with the exception of customer code, which is entered directly on this screen. You can also copy budgets, estimated hours and parts lists.



Select Job to display the Copy Job Screen.

Copy Job Screen



Select Job to display the Copy Job Screen.

JM119	Z1 - GB Demonstration Company	USER GBJBATD0	15/10/97 16:56:56
Copy Job			
Copy job number.....?.. █			
To job number.....			
Customer.....?..			
Copy default budgets..... 0 (0/1)			
Copy estimated hours..... 0 (0/1)			
Copy parts lists..... 0 (0/1)			
Copy production costs..... 0 (0/1)			
F3=Exit F4=Prompt F10=Copy sub-job			
5-32	SA	MW	KS CL IM DM II STUD140 KB PKH317S1

Fields:

Copy Job Number

Select the job number to be copied.

To Job Number

This is the name of the new job. You cannot copy to a job that already exists.

Customer

If you do not enter a customer, the new job structure has the same customer code and delivery address sequence as the 'From' job.

If you do enter a customer, the new job will have the new customer code, with a delivery address sequence of '000' at each level.

Copy Default Budgets

If you wish to copy the default budget across to your new job number, enter 1 against this field.

Copy Estimated Hours

0 - No. Do not copy the estimated hours data across to your new job number.

1 - Yes. Copy the estimated hours data across to your new job number.

Copy Parts Lists

0 - No. Do not copy the parts lists across to your new job number.

1 - Yes. Copy the parts lists across to your new job number.

Copy Production Costs

0 - No. Do not copy the Production costs across to your new job number.

1 - Yes. Copy the Production costs across to your new job number.

Functions:

F10

Copy Sub-Job. The Copy Sub-Job Window is displayed.



Press **Enter** to copy over the job to the new job number. All job details for the new job have a status of '01'.



Note: Once you have copied across to your new job, no further 'copy to' access is allowed for that new job. Therefore, if you have set the copy budget flag to 0, you cannot at a later date copy the budget details.

Copy Sub-Job Window (F10)



When **F10=Copy Sub-Job** is selected on the Copy Job Screen, the Copy Sub-Job Window is displayed.



Note: This window only copies a sub-job within a job, it will not copy a sub-job into a new job.



Note: Copying will reprice any parts list according to the details of the new customer.

JM119 Z1 - GB Demonstration Company USER GBJBATD0 15/10/97 16:56:56

Copy Job

Copy job number.....

To job number.....

Customer.....

Copy default budgets.....

Copy estimated hours.....

Copy parts lists.....

Copy production costs.....

From job/sub-job/task....?..

To job/sub-job/task.....

Customer.....?..

Copy tasks..... 0 (1/0)

Copy estimated hours..... 0 (1/0)

Copy default budgets..... 0 (1/0)

Copy parts lists..... 0 (1/0)

Copy production costs..... 0 (1/0)

F3=Exit F4=Prompt F10=Co

7-61 SA MW KS CL IM DM II STUD140 KB PKH317S1

Fields:

From Job/Sub-Job/Task

Select the job/sub-job/task to be copied.

To Job/Sub-Job/Task

Enter the name of the new job/sub-job/task. You cannot copy to a job/sub-job/task that already exists.

Customer

The customer entered here will be set up on the new sub-job, with the default '000' delivery address. You can leave this field blank.

Note the following:

- If the customer is changed, and the new customer has a different stockroom to the original, then any linked parts lists will not be copied.
- Override addresses entered against the job details will not be copied.
- Linked customer returns will not be copied.

Copy Tasks

1 - Copy all tasks from the selected sub-job.

Copy Estimated Hours

1 - Copy the estimated hours data across to your new sub-job.

Copy Default Budgets

1 - Copy the default budget defined on the company profile across to your new sub-job.

Copy Parts Lists

1 - Copy the parts lists across to your new sub-job.

Copy Production Costs

1 - Copy the Production costs across to your new sub-job.

Copy Job To Quote



4/JCG

This option adds a quotation based on an existing job. Order lines are copied to the new quotation as long as they are not cancelled, and were not generated from a Production transaction.

Production transactions are copied to the quotation as long as they originated from a quotation themselves.



Note: Copying will reprice any parts list according to the details of the new customer.

Copy Job To Quote Screen



Select the Copy Job To Quote option to display the Copy Job To Quote Screen.

JM326Z1 - GB Demonstration CompanyUSER GBJBABLTTIME12/02/9717:48:51

Copy Job To Quote

Copy job number.....?..

To quote number.....?..

To revision.....

Customer.....?..

F3=Exit F4=Prompt

05-3282MWKSIMIIKENB20APET179S8

Fields:

Copy Job Number

Enter the job to be copied.

To Quote Number/Revision

Enter the quotation and revision to be added.

Customer

Enter the customer for whom the quotation is to be added. This field is optional - leave it blank to use the job's customer on the quotation.



Press **Enter**. The copy job is run interactively, so you must wait a moment while it completes.

Copy Budget



12/JCC

Use this option to copy a budget from one code into another, within a job.

Copy Budget Screen



Take the Copy Budget option to see the Copy Budget Screen.

JM356Z1 - GB Demonstration CompanyUSER GBJBATD015/10/9716:59:10

Copy Budget

For job number.....?..

From budget code / type...?... (0=Forecast, 1=Budget)

To budget code / type.....?... (0=Forecast, 1=Budget)

F3=Exit F4=Prompt

5-32SA MWKS CL IM DM II STUD140 KB PKH317S1

Fields:

For Job Number

Enter the job number whose budget you want to copy.

From Budget Code/Type

Enter the budget and type of the budget to be copied from. They must already exist.

To Budget Code/Type

Enter the budget and type to be copied to. This budget cannot already exist for the job specified, and must not be the default budget specified on the company profile.



Press **Enter**, and the copy is carried out interactively, while you wait. A message tells you when the copy is complete.

Copy Cost/Price List



13/JCC

Use this option to create new cost or price lists by copying existing ones.

You can apply a percentage change to the values so that the new list rates are, for example, 3.5% higher than those of the original list.

As soon as the copy is done the system displays the results so that you can make any amendments necessary before confirming the copy.

Copy Cost/Price List Screen



Select the Cost/Price List copy option to see the Copy Cost/Price List Screen.

JM350	Z1 - GB Demonstration Company	User GBJBATD0	13/10/97 15:33:10
Copy Cost/Price List			
List type.....	1	(1=Costs, 2=Prices)	
From List code.....?	001		
Currency code..?	GBP		
Effective date.?	13/10/97		
To List code.....?	003		
Effective date....	13/10/97		
Description.....	Labour rates - Admin		
Percentage uplift.....	10-		
F3=Exit F4=Prompt			
5-27	SR	MW	KS CL IM DM II STUD140 KB PKH317S1

Fields:

List Type

Enter the list type to be copied from.

1 - Cost list.

2 - Price list.

From List Code

Enter the existing list to be copied from.

Currency Code

Enter the currency of the list to be copied from.

Effective Date

Enter the effective date of the list to be copied from.

To List Code

Enter a code for the new list.

Effective Date

Enter the effective date of the new list.

Description

Enter a description for the new list. if you leave this blank, then the description from the original list will be used.

Percentage Uplift

To alter all the figures in the old list by a given percentage, enter that percentage here. A positive figure will increase the rates, a negative will decrease them.

To enter a negative, place a negative sign after the value entered.



Press **Enter** to create the new list. A message tells you when the copy is complete. The system then displays the Cost/Price List Maintenance Detail Screen (see the Cost/Price List section for details of this screen), with all the details of the new list displayed, for you to amend and confirm as necessary.



*Note: When you see the details on the Cost/Price List Maintenance Detail Screen, the new list has already been created. You can only delete it at this point by selecting **F11=Delete**.*

General Ledger Control File



21/JCC

Detailed cost and income values are held in Job Management, whilst a financial summary of job values is required in the General Ledger. It is obviously imperative that the two sets of values balance and can be reconciled.

Every transaction should post to a GL account already set up within GL. Obviously, you do not want to enter an account on every transaction, so you can define a posting mask (a kind of template) in order to arrive at a target GL account.

This option enables you to specify the analysis codes, or parts of codes, you want to use to compose the GL account you'll be posting to.



Tip: This concept will be familiar to you if you have used the Advanced Financial Integrator (AFI) application to create GL accounts.

To compose the GL account for each cost transaction (i.e. timesheets, expenses, direct transactions) you can use the following codes:

- Job type.
- Division.
- Profit centre.
- Charge code.
- Expense type.

To compose the GL account for each income transaction you can use the following codes:

- Job type.
- Division.
- Profit centre.
- Price type.

Example

You need to structure P&L posting codes for Job Management costs.

Profit & loss costs	Level (0/1)	Required length	Start position
Job type	1	3	7
Division	0		
Profit centre	1	2	5
Charge code	0		
Expense type	1	4	1

This shows that the GL account you are building will be nine characters long, that the first four characters relate to the expense type, positions five and six relate to the profit centre and positions seven to nine inclusive relate to the job type.



Warning: The length refers to the length of that field within GL, not Job Management, so you can enter a four character code for expense type when posting to GL, when it is only a three character code in Job Management.

The system checks that the elements of the posting code are contiguous and that there is no overlapping of start positions of the various levels.

The relevant posting codes are built up according to the type and status of Job Management data.

The Balance Sheet (Costs)

Any cost posted to a job detail with a transfer method in the range 1-7 is built up and posted according to this structure. If a Job Management sub-ledger has been defined within the company profile then this structure should reflect that of the sub-ledger, otherwise it can be in any part of the balance sheet.

The Balance Sheet (Income)

Any income created through Job Management for a job whose job type is flagged for deferred income is built up and posted according to this structure. If a Job Management sub-ledger has been defined within the company profile then this structure should reflect that of the sub-ledger, otherwise it can be in any part of the balance sheet.

The Profit and Loss (Costs)

When job costs are posted to P&L the costs are built up and posted according to this structure.

The Profit and Loss (Income)

When income is posted to P&L the income is built up and posted according to this structure.



Take the General Ledger Control File option to see the GL Control File Maintenance Screen.

JM005		Z1 Amalgamated Amalgamations PLC		USER GBJBANB1		7/05/96 14:49:35	
GL Control File Maintenance							
	- - - -Balance Sheet- - - -			- - - -Profit & Loss- - - -			
	Level Rqd	Length	Start	Level Rqd	Length	Start	
	(0/1)		Position	(0/1)		Position	
Costs :-							
Job type.....	0	0	0	0	0	0	
Division.....	0	0	0	0	0	0	
Profit centre.....	1	4	1	1	4	1	
Charge code.....	0	0	0	0	0	0	
Expense type.....	1	3	5	1	3	5	
Income :-							
Job type.....	1	3	1	1	3	1	
Division.....	0	0	0	0	0	0	
Profit centre.....	0	0	0	0	0	0	
Price type.....	1	2	4	1	2	4	
F3=Exit							
09-26	SE	MW	KS	IM	II	KENB20A	PET149S2

Fields:

Level Rqd (0/1)

If you wish this level to be used for the appropriate GL structure enter 1.

Length

The length is the length of this field in GL (not Job Management).

Start Position

The maximum length of the GL fiscal account is 12 characters. Specify the starting position of the selected code within the GL account.



Press **Enter**, and you will see a similar screen displayed for the entry of extension codes. This works in exactly the same way as the main account code definition, except that extension codes can be up to 30 characters long. When you have completed these entries, press **Enter** to update.



Warning: The 'General Ledger Active' flag on the Job Management company profile should not be set on until the General Ledger has been installed and a chart of accounts defined for Job Management postings.

The Cost And Income Masks

1... 22/JCC - 31/JCC **2...**

After defining the GL account structure through General Ledger Control File maintenance, these options enable you to specify a General Ledger code for each Job Management code. The entries you have made in the General Ledger Control File option determine the look of your masking screen.



Take the relevant masking option. This will be one of the following:

- Balance Sheet Cost Masks.
- Profit & Loss Cost Masks.
- Profit & Loss Recharge Masks.
- Balance Sheet Income Masks.
- Profit & Loss Income Masks.

The option can be from either the GL Interface Definition (Driver) or the GL Interface Definition (Extensions) section of the menu.



The first screen enables you to enter posting codes.

JM015		Z1 Amalgamated Amalgamations PLC		USER GBJBANB1	7/05/96
					14:50:56
Balance Sheet Costing Codes - Costs					
Profit centres					
Profit Centre	Description	Posting Code			
000001	Computer Expenses	B C D * * * * *			
000002	Central Admin	Z X C V * * * * *			
F3=Exit					
08-47	SF	MW	KS	IM	II KENB20A PET149S2

Fields:

Posting Code

The account code positions not used by this particular code contain asterisks, indicating that you must not use them.

For each code listed on the left hand side of the screen, enter the associated GL code in the blank fields of the posting code (also called the account code).



Warning: The corresponding option from the *Extensions* section of the menu uses the same method to set up posting codes for the extension code, if you are using extension codes.

Example

Using the example below of the posting code structure:

Balance Sheet Costs	Level (0/1)	Required Length	Start Position
Job Type	1	3	7
Division	0		
Profit Centre	1	2	5
Charge Code	0		
Expense Type	1	4	1

This shows that in General Ledger Posting Codes the account (posting) code structure is seven characters long, that the first four characters of the account code is the expense type, positions five and six are the profit centre and position seven is the job type.

You now enter the masking option to enter relevant codes. For example:

- For job type '123', enter 1.
- For division code '56', enter DC.
- For expense type 'MAT', enter 6789.

This would enable a posting to General Ledger code '6789DC1'.