

-
-
-
-
-

Chapter 10

Utilities



Company Profile

1/JCU

You must set up a company profile for each Job Management company. A company profile holds the rules which govern the operation of Job Management for that company.

This procedure enables you to create profile data for a new company, change any existing profile data, and to print it.

A separate option enables you to enquire on a company already set up.



Note: Great care is needed if you change certain application data once the application is in use. System control routines prevent the profile from being maintained when anyone else is using the application.

When you are setting up a new company, you will not be able to enter all of the company profile maintenance screens. This is because the parameters you have to enter do not yet exist. The sequence of events is thus:

- Create the company (use the Company Profile option).
- Create the appropriate parameters.
- Amend the company profile to include these necessary parameters.



Warning: If there is a Copy Company option within Utilities, JBA strongly recommend that you use this option to create a new company. You can use the Copy Company option to copy existing parameters and miscellaneous codes to your new company. You can amend these details using your maintenance and utility options.



Select the Company Profile option, enter the company you want to maintain in the selection screen and press **Enter**. The first Company Profile Update Screen displays.

Company Profile Update Screen 1



Select the Company Profile option, enter the company you want to maintain in the selection screen and press **Enter**. The first Company Profile Update Screen displays.

```

JM002                Z1 - GB Demonstration Company    USER GBJBABL  17/07/97
                                           12:44:12
Company Profile Update                                *Update

Company code..... Z1
Company name..... Job Management (Demos) Ltd
Address..... JBA Software Products Ltd
              Needles House
              Birmingham Road
              STUDLEY
              Warwickshire, UK
Post code..... B80 7AS
General ledger active..... 1 (0/1) Service active..... 1 (0/1)
Accounts payable active..... 1 (0/1) Review service contracts... 0 (0/1)
Accounts receivable active..... 1 (0/1) Customer returns active.... 1 (0/1)
Purchase management active..... 1 (0/1)
Post miscellaneous issues direct.. 0 (0/1)
SOP active..... 1 (0/1) Post cust issues direct.... 0 (0/1)
Fixed assets active..... 1 (0/1) Parent/child relationship.. 0 (0/1)
Use SOP prices..... 1 (0/1) Summarise GL postings..... 0 (0/1)
Last invoice number used..... 3357 Auto process codes..... 1 (0/1)
Last credit note number used..... 33

F3=Exit  F12=Previous  F15=Production functions
          06-20      SC      MK      KS      IM      II  KENB20A  PET178S2
  
```

Fields:

Company Name

Enter company name.

Address

Enter address of company.

Post Code

Enter post code.

General Ledger Active

This field determines whether Job Management posts transactions into General Ledger. It does not control whether GL is installed, as GL is a prerequisite to the running of Job Management (if you are running System 21 on an AS/400, then Job Management libraries must be included in the standard GL library list).

0 - Link not active.

1 - Link active.

Service Active

0 - The link is not active.

1 - The link to Service Management is active. This enables you to go straight into Service Management from job details maintenance. The company code must also exist in Service Management.

Accounts Payable Active

Determines whether Accounts Payable is to post invoices and credit notes automatically into Job Management.

0 - Link not active.

1 - Link active.

If active this company code must also exist in Accounts Payable.

Review Service Contracts

Relevant only if the 'Service Active' field above is set to 1.

0 - The system will not remind you of installation records which need attaching to a contract. This does not mean that no such records exist, only that no reminder is given.

This setting is relevant if all the following are true:

- You despatch a part, via the Confirmation of Despatch option in SOP, that is known to Service Management as belonging to a model.
- The customer is known to Service Management because they have a contract.

Under these circumstances, the Service Management 'SOP Transfer to Service' will create installation records for those parts. If these parts derived from a Job Management parts list, you may or may not wish to be reminded of the attachment required. It is this that the current field controls.

1 - System displays a window to remind you of any installation records that need attaching to a contract. The window displays when you exit from Job Details maintenance.

Accounts Receivable Active

Determines whether Job Management is to post invoices and credit notes automatically into Accounts Receivable.

0 - Link not active.

1 - Link active.

If active this company code must also exist in Accounts Receivable.

Customer Returns Active

0 - Link not active.

1 - Link active. This enables you to create, amend and receive against customer returns from within the Job Details option. The company code must also exist within Customer Returns.

Purchase Management Active

Determines whether Job Management is to accumulate commitments from Purchase Management automatically. If the link is active this company code must also exist in Purchase Management.

0 - Link not active.

1 - Link active.

Post Miscellaneous Issues Direct

This field relates to the miscellaneous physical issue from Inventory.

0 - Does not take Inventory Management costs immediately, but saves costs until you choose to post them.

1 - Posts cost from Inventory Management immediately, at the time of issue.

SOP Active

This field determines whether you can define parts lists for Job Management.

0 - SOP/AOE interface not active.

1 - SOP (Sales Order Processing)/AOE (Advanced Order Entry) interface active. The company code must also exist in SOP.

Post Cust Issues Direct

Post Customer Issues Direct. This field is SOP related.

0 - If an SOP order is created by Job Management, the costs are not posted at the time of despatch, but are saved until you choose to post them.

1 - If an SOP order is created by Job Management, the costs are posted at the time of despatch.

Fixed Assets Active

This field determines whether you can capitalise costs in Fixed Assets from Job Management. The company code must also exist in Fixed Assets.

0 - Fixed Assets interface not active.

1 - Fixed Assets interfaces active.

Parent/Child Relationship

Related to Fixed Assets.

If the 'Parent/Child Relationship' field is set to 1, then the Fixed Asset creation will set the parent of the asset to be the asset of the next level up in the job hierarchy. For example, the parent asset of an asset created at task level would be the asset defined for the sub-job.

Use SOP Prices

0 - Do not update selling prices.

1 - Update selling prices (at job detail level) with SOP prices. The system will not update prices which have been changed or overridden, as it assumes you wish to preserve such changes. This setting can be used only if SOP is active.

Summarise GL Postings

Related to Fixed Assets.

0 - GL postings for Fixed Assets are not to be summarised by asset.

1 - GL postings for Fixed Assets are to be summarised by asset.

Last Used Invoice Number Used

The last invoice number that has been processed displays. This is automatically incremented by the application, but at set up stage the number prior to the first invoice number to be used should be input.

Auto Process Codes

0 - The process codes function is not to be used.

1 - You wish to use the process codes function. This is used to control the status codes of job details automatically. If you wish to use this function now, or plan to use it in the future, then turn the function on.

Last Used Credit Note Number

The last credit note number that has been processed displays. This is automatically incremented by the application, but at set up stage the number prior to the first credit note number to be used should be input.



Note: If the company is being amended, the second Company Profile Update Screen displays next. If the company is being added, you must return to the company selection screen before access is authorised to the third Company Profile Update Screen.

Functions:

F15

Production Functions. Display the Production-related fields for the company profile.

This function is not available from the other company profile screens.



Press **F15** to see the Company Profile Update - Production Options Screen.

Company Profile Update Production Functions Screen (F15)



When **F15=Manufacturing Functions** is selected on the first Company Profile Update Screen, the Company Profile Update - Production Functions Screen displays.

JM002	Z1 - GB Demonstration Company	USER GBJBABL	3/02/97 14:36:32
Company Profile Update - Production Functions			
Company code..... Z1			
Production active..... 1 (0/1)			
Consolidation type..... 0 0=None 1=Job level 2=Company level			
Commitment cost type..... 1 1=Current costs 2=Standard costs			
Cost set..... MAN			
Expense type.....? MAN			
F3=Exit F4=Prompt F12=Previous			
07-31 SP MK KS IM II KENB20A PET179S8			

Fields:

Production Active

0 - No. Production is not linked.

1 - Yes. Production is linked, and Job Management is able to create production orders. Extra fields will be displayed on relevant screens.

Consolidation Type

If you are creating production orders via Job Management, you can consolidate orders for a particular item into one production order. You can consolidate orders from all job details within a job, or all job details within a company:

0 - None.

1 - Job level.

2 - Company level.

If the production order policy of the item is A (discrete), a confirmed production order is created. If the order policy is not discrete, a planned order, without a route, is created and requirements are consolidated.

Commitment Cost Type

1 - Current costs. Use current costs for the committed costs for the Production part.

2 - Standard costs. Use standard costs for the committed costs for the Production part.

Cost Set

If using current costs (Commitment Cost Type is 1), enter a cost set. A blank cost set represents standard costs.

Cost set is a free format code set up by Production to refer to a group of costs.

Expense Type

Enter a Production expense type, as set up in the Expense Types option. This must be different from the expense types entered on the second Company Profile Update Screen for Inventory transaction data, timesheets and expenses.



Press **Enter** to continue to the second Company Profile Update Screen.

Company Profile Update Screen 2



Press **Enter** from the first Company Profile Update Screen if you are amending an existing company, or press **Enter** from the Company Profile Update - Production Functions Screen, to see the second Company Profile Update Screen.



Tip: This screen is only available when a company is being amended. This is because the parameters you have to enter will not yet exist if you are creating a company.

```

JM002                Z1 Amalgamated Amalgamations PLC    USER GBJBANB1    16/04/96
                                                            15:15:43

Company Profile Update

Company code..... Z1
Job management sub-ledger.....?..
Holding account for job management costs.?.. 105000
Holding account for accounts payable costs? 106000
Holding account for inventory costs.....?.. 106000
Fixed asset suspense account.....?.. 106000
Default write off account.....?.. 106000
Cost of sales account (P&L).....?.. 606110
Income account (P&L).....?.. 616100
WIP cost account.....?.. 203000
WIP deferred income account.....?.. 230000
Inventory transaction data - expense type.? INV Tran type? INV Charge code? IN
Expense type for timesheets.....?.. LAB T/S tran type..?.. TMS
Expense type for expenses.....?.. EXP Exp tran type..?.. EEX
Default budget code.....?.. BUD
Supplier no = employee no (0/1)..... 1
Auto generate JM ref nos (0/1)..... 1

F3=Exit F4=Prompt F12=Previous

06-46  SP MW KS IM II KENB20A PED149S1
  
```

Fields:

Job Management Sub-Ledger

An entry of a balance sheet sub-ledger here can force postings of costs to work in progress, and postings of deferred income to be posted to this sub-ledger. If no entry is made, these postings can be anywhere in the balance sheet.

This account must be an existing balance sheet account.

Holding Account For Job Management Costs

This acts as the credit account for postings of costs made via direct transactions or standing costs.

The holding account has to be a balance sheet account. It cannot be post inhibited or a memo account.

Holding Account For Accounts Payable Costs

This acts as a suspense account for any costs posted via Accounts Payable. The interface with Accounts Payable works as follows:

- It debits the holding account for Accounts Payable costs and credits the Accounts Payable control account as normal
- Then, calling in Job Management, it will debit the GL via Job Management and credit the holding account for Accounts Payable costs (rather than the holding account for Job Management costs).

Effectively, the holding account for Accounts Payable costs has balanced itself out in two sessions as below:

Holding a/c for Accounts Payable costs		Accounts Payable control a/c		Job Mgmt (WIP) a/c	
DR	CR	DR	CR	DR	CR
Step 1	Step 2		Step 1	Step 2	

Therefore, through two sessions, one Accounts Payable, the other Job Management, you end up with a debit to WIP and a credit to the Accounts Payable control account.

This account has to be a balance sheet account. It cannot be post inhibited or a memo account.

Holding Account For Inventory Costs

This acts as a credit account for postings of Inventory costs. This account has to be a balance sheet account. It cannot be a post-inhibited or memo account.

It is recommended that you set up this account as a suspense account, and use AFI (Advanced Financial Integrator) to debit this account for Inventory movements created for Job Management related movements. These movements can be identified as follows:

- Miscellaneous Physical Issues
- Movement source - J
- Movement type - 'JM'
- Customer Issues
- Movement reason - 'JM'

Fixed Asset Suspense Account

This acts as a debit account for all work in progress costs that are transferred to Fixed Assets. The account must be a balance sheet account. It must not be a memo account or a post inhibited account.

Costs transferred to Fixed Assets will be debited to this account within the GL, and corresponding Fixed Asset transactions created. The GL structure for cost books in Fixed Assets should be defined so that the credit posting for the GL account type '090' goes to this account.



Note: Reversible or reversing standing costs remain in this account and are not capitalised.

Default Write-Off Account

When you are transferring to Fixed Assets, and you are dealing with multiple assets, and the cost is non-serial-controlled Inventory cost, then the value is held here, and an exception report produced.

Cost Of Sales Account P&L

Enter the default P&L ledger or sub-ledger account to be used for Job Management costs. This account holds any failed posting of cost to P&L. A failed posting will occur if the GL account created by the mask:

- does not exist.
- is post inhibited.
- is a memo account.
- belongs to the incorrect ledger.

Income Account P&L

Enter the default P&L ledger or sub-ledger account to be used for Job Management income. This account holds any failed posting of income to P&L. A failed posting will occur if the GL account created by the mask:

- does not exist.
- is post inhibited.
- is a memo account.
- belongs to the incorrect ledger.

WIP Cost Account

Enter the default WIP balance sheet cost account to be used. This account holds any failed posting of cost to the balance sheet. A failed posting will occur if the GL account created by the mask:

- does not exist.
- is post inhibited.
- is a memo account.
- belongs to the incorrect ledger.

WIP Deferred Income Account

Enter the default WIP deferred income cost account to be used. This account holds any failed posting of income to the balance sheet. A failed posting will occur if the GL account created by the mask:

- does not exist.
- is post inhibited.
- is a memo account.
- belongs to the incorrect ledger.

Inventory Transaction Data - Expense Type

Enter a valid expense type to which all Inventory transactions will be attached. Ensure that the expense type for timesheets is also added to all required job types.

This must be different from the expense types entered for Production, timesheets and expenses.

Tran Type

Enter a valid transaction type to be used for Inventory transactions.

Charge Code

Enter the charge code to be used for Inventory transactions.

Expense Type For Timesheets

Enter a valid expense type to which ALL timesheets will be attached. Ensure that the expense type for timesheets is also added to all required job types.

This must be different from the expense types entered for Inventory transaction data, Production and expenses.

T/S Tran Type

Enter a valid transaction type to be used for timesheet entries.

Expense Type For Expenses

Enter a valid expense type to which all employee expenses will be attached. Ensure that the expense type for employee expenses is added to all required job types.

This must be different from the expense types entered for Inventory transaction data, timesheets and Production.

Exp Tran Type

Enter a valid transaction type to be used for employee expenses.

Default Budget Code

Enter a valid budget code to be used for budgeting jobs. When you enquire on job details, the selected budget code displays as default. Other valid budgets may, of course, be viewed and maintained.

Once used, this code cannot be changed.

Supplier No=Employee No

Relevant where an Accounts Payable interface exists.

Where expenses are to be paid via Accounts Payable, set up your suppliers so that the first 6 characters of the supplier number are numeric and are the same as the employee numbers. This feature saves the re-keying within Accounts Payable.

1 - Suppliers are set up the same as employees.

0 - Suppliers are not set up the same.

Auto Generate JM Ref Nos

This facility enables a unique reference number to be given to each transaction entered through Job Management, and this will be used as the internal reference.

- 1 - The application will generate reference numbers automatically.
- 0 - The reference will be entered manually each time.



Note: The system creates balance sheet accounts to post via masks. If anything exists in the default accounts, then the masking has failed or masking is not required. The Job Management posting validation report highlights any failed postings.



Press **Enter**. A series of GL extension code windows is now displayed, enabling you to specify the extension code for each suspense account you have entered. Press **Enter** to accept the codes shown, or enter new ones.

When you have confirmed extension codes for each account, you will see the third Company Profile Update Screen, where you set up the range of batch numbers for expenses, direct transactions and invoices.

Company Profile Update Screen 3

Job Management uses batch control for expenses, direct transactions and invoices. Each of these uses two ranges of numbers, one for automatically and one for manually generated transactions.

Because of this, each needs two starting points entering.



Warning: Once the ranges are set up, you are strongly advised not to change them. A 7 digit range number is available, so you may choose to use the full range.

```
JM002          Z1 Amalgamated Amalgamations PLC  USER GBJBANB1  16/04/96
                                                    15:17:24

Company Profile Update

Company code..... Z1

Expenses batch control
Automatic batch generation range :-
Start batch.... 1000001  End batch.... 9999999  Last batch used.... 1000003
Manual batch range :-
Start batch.... 1      End batch.... 1000000
Direct transactions batch control
Automatic batch generation range :-
Start batch.... 1000001  End batch.... 9999999  Last batch used.... 1000026
Manual batch range :-
Start batch.... 1      End batch.... 1000000
Invoicing batch control
Automatic batch generation range :-
Start batch.... 1000001  End batch.... 9999999  Last batch used.... 1000016
Manual batch range :-
Start batch.... 1      End batch.... 1000000

F3=Exit  F12=Previous

09-10  SF  MW  KS  IM  II  KENB20A  PED149S1
```

Fields:

Expenses Auto Batch Range

Enter a range of numbers which does not conflict with the manual batch control range for expenses.

Last Batch Used

Output only. Only automatic batch numbers are displayed.

Expenses Manual Batch Range

Enter a range of numbers which does not conflict with the automatic batch control range for expenses.

Direct Trans Auto Batch Range

Enter a range of numbers which does not conflict with the manual batch control range for direct transactions.

Direct Trans Manual Batch Range

Enter a range of numbers which does not conflict with the automatic batch control range for direct transactions.

Invoicing Auto Batch Range

Enter a range of numbers which does not conflict with the manual batch control range for invoicing.

Invoicing Manual Batch Range

Enter a range of numbers which does not conflict with the automatic batch control range for invoicing.



Press **Enter** to update the profile with any changes you have made. You will be returned to the company selection screen.

Start Job Management Subsystem



21/JCU

Balances within Job Management are updated using a background program called a subsystem. If the subsystem is inactive, balances are not updated, but queue up until the subsystem is started. This includes all transactions waiting to be transferred to the General Ledger.

Two options are provided to enable you to start up and end the Job Management subsystem (this can also be done automatically as part of the 'day start' and 'day end' routines).

The options do not require any entries; so you will see no screens or windows. When you take the option the job is done.

End Job Management Subsystem



22/JCU

Balances within Job Management are updated using a background program called a subsystem. If the subsystem is inactive, balances are not updated, but queue up until the subsystem is started. This includes all transactions waiting to be transferred to the General Ledger.

Two options are provided to enable you to start up and end the Job Management subsystem (this can also be done automatically as part of the 'day start' and 'day end' routines).

The options do not require any entries; so you will see no screens or windows. When you take the option the job is done.

Recalculate Rolled Up Values



23/JCU

This option clears all previously rolled up values for:

- job details.
- job details + expense type.
- job details + expense type + GL period.

It completely recalculates all this-level values.

This is a powerful option which should be run only on your software agent's advice.

This option requires sole use of the company, so no other job can be left running in Job Management while it is being used. It is an option which can be heavy on processing power.

Recalculate Quotation Estimated Hours



24/JCU

This option recalculates all the estimated hour values for all levels of a quotation, as long as the quotation is set to have its hours recalculated (i.e. the Estimated Hours Control field is set to '1' on the Quote Header Maintenance Screen). It then recalculates the 'this level' and the 'rolled up' values by accumulating the estimated hours within quotation labour transactions.