

-
-
-
-
-

Chapter 1

Company Parameters Database



Company Profile File Maintenance

1/SSP

Use this option to set up and maintain the fields which control how you want Service Management to work for a specific company. You make key decisions regarding how you wish to operate the system here.

You would normally use this option when you install the system, and infrequently thereafter.



Note: This procedure requires exclusive use of the system.

A company is completely self-contained within the module. You can sub-divide it into branches, but these branches will all operate under the controlling parameters defined for the company.

The company profile is where you decide which other modules (the ledgers, Sales Order Processing, Inventory Management, and so on) you want to integrate with Service Management.

If other modules are to be integrated, then the following functions may be available:

- Inventory can be used to check the engineer's van stock.
- SOP can price parts.
- Technical reporting can automatically send information to update Inventory stock movements, and to generate invoices.

Company Profile Maintenance Selection Screen



Select Company Profile Maintenance.

SS006	JBA Demonstration Company	USER BRERETM	24/06/93 14:53:52
-------	---------------------------	--------------	----------------------

Company Profile Maintenance

1 Company name	Code
<u>1</u> Demonstration Company	ZM

Enter company code to maintain.. __

1=Select company
F3=Exit

Fields:

1

Select. Enter 1 against the company you wish to maintain.

Company Code to Maintain

If you are setting up a new company, enter the two character company code here. You can also enter an existing company, if you do not wish to scroll through the list to select the one you want.



If you selected a company using the selection field, the first Company Profile Maintenance screen is displayed automatically.

If you selected a company by entering the code yourself, you must press **Enter** to see the first Company Profile Maintenance screen.

Company Profile Maintenance Screen 1



To automatically display this screen select the company on the Company Profile Maintenance Selection screen.

Or: Enter a new company code on the Company Profile Maintenance Selection screen and press **Enter**.

SS006	JBA Demonstration Company	USER BRERETM	8/03/94 13:52:45
Company Profile Maintenance			
Company Code	ZM	Company Name	<u>Demonstration Company</u>
Last Job Number			<u>0501221</u>
Last Invoice Number			<u>500676</u>
Last Credit Note Number			<u>900022</u>
Last Contract Number			<u>0000125</u>
New Contract Number at Renewal ?		(1=Yes/0=No)	<u>1</u>
Validate Post Codes ?		(1/0)	<u>0</u>
Use geocode/UK post code rules for team assignment		(1/2)	<u>2</u>
Manual Engineer Allocation across Branch ?		(1/0)	<u>1</u>
Assign by Territory (1) or Alternative (0) Engineer			<u>0</u>
Hard Copy Job Audit Log Required ?		(1/0)	<u>1</u>
Accounting Period			<u>03</u>
Accounting Year			<u>94</u>
F3=Exit F12=Previous			

Fields:

Company Name

For a multi-company environment the name will default from Application Manager, where it is set up via the Maintain Company Parameters option.

For a stand-alone installation, enter up to 30 alphanumeric characters for the company name.

Last Job Number

Enter the number to start off the job numbering. When the system assigns the next job number, this field will be incremented by one, so the field always shows the last job number used. Once you have started using Service Management, do not change this number.

Last Invoice Number

Enter the number to start off the invoice numbering. When the system assigns the next invoice number, this field will be incremented by one, so the field always shows the last invoice number used. Once you have started using Service Management, do not change this number.

Last Credit Note Number

Enter the number to start off the credit note numbering. When the system assigns the next credit note number, this field will be incremented by one, so the field always shows the last credit note number used. Once you have started using Service Management, do not change this number.



Tip: When posting invoices and credits from various System 21 modules into the General Ledger, or elsewhere, the system attaches a prefix which shows where the invoice or credit originated.

The system attaches I to Service Management invoices, and C to Service Management credits. This means that you should avoid using I and C as prefixes in other modules - for example, Sales Order Processing.

Last Contract Number

Enter the number to start off the contract numbering. When the system assigns the next contract number, this field will be incremented by one, so the field always shows the last contract number used. Once you have started using Service Management, do not change this number.

New Contract Number at Renewal

Enter one of the following:

0 - To continue with the existing contract number after the renewal. This is often easier for the customer to remember.

1 - To assign a new contract number when the contract is renewed.

Validate Post Codes

Enter one of the following:

0 - Do not validate any code entered in the post code fields. You can use the post code fields for any geocode you devise.

1 - The system checks that data entered in postcode fields, conforms to the UK postcode format standards. This is particularly useful because the postcode is brought in from the module where it is set up - Accounts Receivable - and if it is not formatted correctly there, it will be highlighted here.

Use Geocode/UK Post Code Rules For Team Assignment

When a call is logged, the system assigns a team to the call by matching the geocode on the customer's additional service details to the corresponding team's territory. The matching depends which of these values you choose:

1 - Geocode. The system first looks for a complete geocode match between customer and team. If no match is found, successive tests will be made, reducing the customer's geocode by one character each time, the final test will try to match on just the first character of the customer's geocode.

2 - UK Postcode. The system first looks for a complete postcode match between customer and team. If no match is found, successive tests will be made, reducing the customer's postcode by one character each time. However, as long as the postcode starts with two alphanumeric characters, the final test will try to match on the first two characters of the customer's postcode. No test is made on the

first character on its own (so BR for Bristol will never be reduced to B for Birmingham, for example).

If there is no match, the job is assigned to a default team *DF which is authorised to service anything. The actual team to work on the job can be assigned during call logging, or in Engineer Work Allocation.

Manual Engineer Allocation Across Branch

Enter one of the following:

0 - To manually assign engineers from the service branch of the piece of equipment to a job.

1 - To manually assign an engineer from any service branch to a job within job maintenance.

Assign By Territory Or Alternative Engineer

Enter one of the following:

0 - Assign another engineer from the engineer's alternative engineers list.

1 - Assign another engineer from the same territory.

This field is used if automatic assignment finds that the selected engineer's absence code is not blank - that is, that engineer is not available.

Hard Copy Job Audit Log Required

Enter one of the following:

0 - You do not require an audit report of all changes to jobs.

1 - You require an audit report which prints every job added, deleted or modified.

Accounting Period

This value is used as the posting period during all invoice generating routines in Service Management. Accounts Receivable postings will be made to the Accounts Receivable open period, if it is later than the period indicated here.

It has to be manually reset at each period end.

Accounting Year

The year value is used as the posting year during all invoice generating routines in Service Management. Accounts Receivable postings will be made to the Accounts Receivable open period/year, if it is later than the year indicated here.

It has to be manually reset at each year end.



Press **Enter** to display the second Company Profile Maintenance screen.

Company Profile Maintenance Screen 2



To display this screen press **Enter** on the first Company Profile Maintenance screen.

Use this screen to define the relationships with the other modules, and to set up General Ledger accounts.

General Ledger accounts are set up on the transactions posted to the General Ledger from the generation of contract and job invoices, unless used with the Advanced Financial Integrator, in which case the accounts are established in AFI.

SS006	Drinks V2 Integr. Test Co.	USER GBJBAJKG	6/03/96 14:42:41
Company Profile Maintenance			
Company Code	D2	Company Name	Z1 - C&T TEST COMPANY
Sales & General Ledgers Active ?	(1=Yes/0=No)	0	
Inventory Active ?	(1/0)	0	
S.O.P. Active ?	(1/0)	0	
Currency Rate Code ?		PERD	
General Ledger Account Codes:			
Sales Ledger Control		411100	
VAT Control		445700	
Service Sales		701100	
Deferred Income		4860130	
Default Labour Rate Price List Code			
Default Scheduled Service Visit Profile			
No. of Service Periods to be Loaded		012	
Minimum No. of Loaded Service Periods		003	
F3=Exit F4=Prompt F12=Previous			
12-65	SP	MW	KS IM II KENB20A PED129S1

Fields:

Sales & General Ledgers Active

Enter one of the following:

- 0 - To use Service Management as a stand-alone module.
- 1 - To integrate Service Management with General Ledger and Accounts Receivable.

Inventory Active

Enter one of the following:

- 0 - To use Service Management as a stand-alone module.
- 1 - To integrate Service Management with Inventory Management.

SOP Active

Enter one of the following:

- 0 - To use Service Management as a stand-alone module.
- 1 - To integrate Service Management with Sales Order Processing.

Currency Rate Code

Enter an existing currency rate. These are set up in the General Ledger.

The currency rate converts contract, or job, invoice values from the customer's prime currency to the customer's base currency. You can overwrite this default value at both customer and sundry invoice/credit note levels.



Note: The field is only displayed if Accounts Receivable is operating as a multi-currency ledger.

When you add a new company, this field defaults to the currency rate on the Accounts Receivable company profile (if set up).

Sales Ledger Control

This field is only used if you are not using AFI.

Enter the GL debtors control account to be used for posting sales revenue.

VAT Control

This field is only used if you are not using AFI.

Enter the GL VAT output account to be used for posting sales revenue.

Service Sales

This field is only used if you are not using AFI.

Enter the GL sales account to be used for posting sales revenue.

Deferred Income

This field is only used if you are not using AFI.

Enter the GL account for posting deferred revenue from service contracts invoiced in advance.

Default Labour Rate Price List Code

Enter a price list.

This default price list is used within the job pricing function when labour charges are being calculated. This company default would only be used if there was no price list found for the model concerned.

Default Scheduled Service Visit Profile

Enter a schedule visit profile.

This default visit profile is used in contract maintenance and contract renewal when a maintenance visit schedule for a piece of equipment on the contract is being generated, and there is no profile defined for the contract, the model or the model group.

A visit profile is used to generate scheduled service visits for each piece of equipment on a contract. The system looks for the relevant profile according to the following hierarchy:

- 1 - Use the SVP on the contract header.
- 2 - If there is none, use the model file SVP.
- 3 - If there is none, use the model group file SVP.

4 - If there is none, use the company profile SVP.

5 - If there is none, no visits will be generated.

Otherwise, generate visits for the equipment line on the contract, using the first SVP code found, when option 8 on the Equipment screen (SS025) is taken.

No Of Service Periods To Be Loaded

This value sets the maximum number of service periods for which scheduled maintenance visits will be generated. The scheduled visit profile (SVP) for a contract lasting for more than a year should include a repeat indicator (*RP), otherwise visits will only be generated for the first year of the contract.

As an example, if monthly service periods are defined and the No Of Service Periods To Be Loaded field is set to 24, using an SVP for four visits a year, plus *RP, will result in eight visits being generated.

The Load PM Jobs option must be run to convert these new visits to actual jobs.

Minimum No Of Loaded Service Periods

This is used at period end, to limit the extension of scheduled service visit generation.

When you run the Period End Routines option, you extend the schedule of planned service visits. You also specify a period in the Start Next Profile Load From field on the Contract Equipment Maintenance Visits screen.

When Period End Routines generates further scheduled visits, these will be for n periods (the minimum number entered here) ahead of the Start Next Profile Load From date.

You must run Load PM Jobs to convert these new visits to actual jobs. Planned maintenance jobs can be limited to one machine only, or can cover all machines on the site due for maintenance in the same period.



Press **Enter**. If there are control accounts in the control account fields, and you use extension codes in your General Ledger chart of accounts, then an extension code window is displayed for each account, so that you can select the correct extension codes.

Press **Enter** on each extension code window, and finally you will see the third Company Profile Maintenance screen.

If no control accounts are entered, then when you press **Enter** you go straight to the third Company Profile Maintenance screen.

Company Profile Maintenance Screen 3



To display this screen press **Enter** on the second Company Profile Maintenance screen.

SS006	JBA Demonstration Company	USER BRERETM	8/03/94 13:53:25
Company Profile Maintenance			
Company Code	ZM	Company Name	Demonstration Company
One Machine per PM Job (1=Yes/0=No) 0			
Apportion Travel Time across Job Categories ? (1/0) 1			
Revenue Analysis Period Based on			
Visit Date (1) or Invoice Date (0) ? 0			
Break Times Entry in Technical Reporting Required (1/0) 0			
Technical Reporting by Times (1) or Hours (0) 0			
Engineers Diary Active (1/0) 0			
Mileage to be Charged By:			
Standard Mileage Value (1/0) 1			
Mileage Zones (1/0) 0			
Actual Miles Driven (1/0) 0			
F3=Exit F12=Previous			

Fields:

One Machine Per PM Job

Enter one of the following:

0 - To list all the items due for service on the site and for the same service period on the one job number.

1 - To generate separate job numbers for each item requiring servicing using the Load Planned Maintenance Jobs option.

See Codes/Parameter File Maintenance (screen 4 of 5) for allowing more than one machine on a breakdown job.

Apportion Travel Time

Enter one of the following:

0 - To accrue travel time to the first job category entered.

1 - To split travel time for a job across the job categories in proportion to the labour time booked for each job category.



Note: This will affect where the travel time cost is allocated.

Revenue Analysis by Visit/Invoice Date

Enter one of the following:

0 - To base the analysis of revenue and cost on the date when the service visit was invoiced.

1 - To base the analysis of revenue and cost on the date of the service visit of the engineer.

Break Times Entry

This is for future development.

Technical Reporting in Hours/Minutes

Enter 0 as technical reporting only supports reporting in hours and minutes.

Reporting by clock time is not supported.

Engineers Diary Active

This field is for future development.

If you enter 1 here then the reserved time buffer fields are shown on the fourth Company Profile Maintenance screen, but these are for future development.

An engineer diary is currently available for non-job activities and job appointments. It is accessed by selecting **F10=Diary** from the Engineer Work Allocation Initial screen.

Mileage To Be Charged By

Standard Mileage Value

Enter one of the following:

0 - Mileage is not to be charged by standard mileage value.

1 - Mileage is to be charged by standard mileage value. The Charge Standard Mileage Value field on a customer's Additional Service Details will initially be set to 1. You enter the charge for making the round trip to the customer site in a separate field.

Only one of the three mileage fields may be set to 1.



Note: If you have set the Zone Code Mandatory field to 1 in System Parameters Maintenance, screen 1 of 5, this field should be 0 - No.

Mileage Charged by Zone

Enter one of the following:

0 - To not charge Mileage by zone.

1 - To charge Mileage by zone. The Charge Mileage Zones field on a customer's Additional Service Details will initially be set to 1. You can enter the zone code, which holds the zone charge, into a separate field.

You can only set one of the three mileage fields to 1.



Note: If you have set the Zone Code Mandatory field to 1 in System Parameters Maintenance, screen 1 of 5, this field should be 1 - Yes.

Mileage Charged by Distance Driven

Enter one of the following:

0 - Mileage is not to be charged by distance driven.

1 - To charge Mileage by distance driven. The Charge Actual Miles field on a customer's Additional Service Details will initially be set to 1. You would enter the actual distance driven at technical reporting.

You can only set one of the three mileage fields to 1.



Note: If you have set the Zone Code Mandatory field to 1 in System Parameters Maintenance, screen 1 of 5, this field should be 0 - No.



Press **Enter** to display the fourth Company Profile Maintenance screen.

Company Profile Maintenance Screen 4



To display this screen press **Enter** on the third Company Profile Maintenance screen.

The service window start and finish times denote the standard working hours per day. They are used both in engineer scheduling and in the calculation of target response dates/times for service jobs. Target dates/times are monitored by the job escalation procedures.

SS006	JBA Demonstration Company	USER BRERETM	8/03/94 13:54:48
Company Profile Maintenance			
Time interval:	0:30	(HH:MM)	
Service window - Start:	8:00 a	(HH:MM a/p/n)	
Service window - Finish:	5:00 p		
F3=Exit F8=Update F12=Previous			

Fields:

Time Interval

This field is for future development.

Service Window - Start

Service operations opening time. Enter a 12 hour clock time and a for a.m., p for p.m., n for noon and blank for midnight.

When you log a call, the response time (and hence the target time) is calculated using the service window.

Service Window - Finish

Service operations closing time. Enter a 12 hour clock time and a for a.m., p for p.m., n for noon and blank for midnight.

When you log a call, the response time (and hence the target time) is calculated using the service window.



Note: Service Window Start and Finish are only effective on the days defined as working days in the Codes/Parameter Maintenance option (major type DAYT); you must set up working days the Daily Calendar File Maintenance option.



Note: If you set the Engineers Diary Active field to 1 on the third Company Profile Maintenance screen, then extra Reserved Time Buffer fields are displayed on this screen. These are for future development.



Select **F8=Update** to save any entries you have made.

Codes/Parameter File Maintenance



2/SSP

Use this option to set up many codes which are used widely throughout the system to assist in data entry, validation and analysis.



Tip: The difference between this option and the Codes/Parameter Maintenance option in Utilities is that system supplied parameters are not included here.

You can change a user code to a system code by adding * to the beginning of the description.

Codes File Maintenance Selection Screen



Select Codes/Parameter File Maintenance.

Any parameter, whether system or user defined, consists of the parameter type, the four-character code itself, and any number of parameter IDs, which are the codes which are defined to that parameter.



Tip: The parameter type corresponds to the major type parameter in other modules, and the parameter ID to the minor type.

SS008	Demonstration Company	USER BRERETM	18/08/93 13:24:49
Codes File Maintenance			
Parameter Type	_____	Enter PTDS to define new type	
Parameter I.D.	_____		
1	Type	Description	
-	ABSC	Engineer absence codes	
-	CCAL	Customer Calendar Codes	
-	CCRC	Contract Cancellation Reason	
-	CHGT	Miscellaneous Charge types	
-	CONF	Configuration code	
-	CORA	Corrective actions	
-	CREA	Reason for call cancellation	
-	DAYT	Day type	
-	DISC	Discount reasons	
-	EGRD	Engineer job grades	+
1=Select			
F3=Exit F4=Code Selection			

Fields:

Parameter Type

Enter PRDS to create or amend a parameter type.

Enter the relevant parameter type to create or amend parameter IDs.

Parameter ID

To amend, delete or enquire on a parameter ID, enter the ID. You must also enter the parameter type.

1

Select. Enter 1 against a parameter type to display a list of existing parameter IDs.



Warning: Do not amend or delete any of the supplied parameter types unless specifically advised to do so by your agent, as unpredictable results may occur.



Select a parameter type, or enter one in the Parameter Type field, and press **Enter** to display the Parameter Type Maintenance screen.

Parameter Type Maintenance Screen



To display this screen select a parameter type and press **Enter** on the Codes File Maintenance Selection screen.

SS008	Demonstration Company	USER BRERETM	18/08/93 13:25:34
Codes File Maintenance			
Parm Type	PTDS		
Parm I.D	DAYT	AMENDMENT	
Description (Maximum) Size....:	30		
I.D. Size....:	1	& Format....:	C (C=Character/N=Numeric)
Description.:	Day type		Max size 30
Value required....:	-	Value Description	
(1=yes)		Value Type Description	
Character 1 req?...:	1	(1=yes/0=no) Description	Deferred rev. a/c day (1/0)?
Character 2 req?...:	1	(1=yes/0=no) Description	Working day (1/0)?
Character 3 req?...:	-	(1=yes/0=no) Description	
F3=Exit F11=Delete F12=Previous			

Fields:

Description (Maximum) Size

Enter a value between one and 30 to define the length of the description of the parameter IDs for this parameter type.

ID Size

Enter a value between one and 4 to define the length of the parameter IDs for this parameter type.

Format

Enter one of the following:

C - For character based parameter IDs.

N - For numerical based parameter IDs.

Description

Enter a parameter type description of up to 30 characters.

As a security measure, any description with the character *, can only be maintained from the Utilities version of this option.

Value Required

Enter one of the following:

Blank - Parameter IDs for this parameter type do not require a value.

1 - To enter a value (either an absolute value or a percentage) when you maintain parameter IDs of this parameter type.

Value Description

If you entered 1 in the Value Required field, then any text entered in this description field will be displayed on the Parameter ID Maintenance screen next to the field where the value has to be entered.

Value Type Description

If you entered 1 in the Value Required field, any text entered in this description field will be displayed on the Parameter ID Maintenance screen next to the 1 character field where P for percentage or V for value can be entered.

Character 1 Req

Enter one of the following:

0 - No field is required.

1 - A single numeric field is required when maintaining parameter IDs of this parameter type.

The entry is held under a system maintained parameter type PMC1

Character 1 Description

If you entered 1 in the Character 1 Req field, this description indicates how the character flag will be used.

The entry is held under a system maintained parameter type PMC1.

Character 2 Req

Enter one of the following:

0 - No field is required.

1 - A single numeric field is required when maintaining parameter IDs of this parameter type.

The entry is held under a system maintained parameter type PMC2.

Character 2 Description

If you entered 1 in the Character 2 Req field, this description indicates how the character flag will be used.

The entry is held under a system maintained parameter type PMC2.

Character 3 Req

Enter one of the following:

0 - No field is required.

1 - A single numeric field is required when maintaining parameter IDs of this parameter type.

The entry is held under a system maintained parameter type PMC3.

Character 3 Description

If you entered 1 in the Character 3 Req field, this description indicates how the character flag will be used.

The entry is held under a system maintained parameter type PMC3.

Allow Blanks

Enter one of the following:

0 - Forces entry of 1 or 0 in the Character 1 or Character 2 fields when the parameter IDs are maintained.

1 - Allows blank entries in the Character 1 or Character 2 fields when the parameter IDs are maintained.



Tip: The rule does not apply to entries or blanks in the (two character) Character 3 field.



Warning: Do not amend or delete any of the supplied parameter type definitions unless specifically advised to do so by your agent, as unpredictable results may occur.



Press **Enter** to display the Existing Parameter IDs screen.

Existing Parameter IDs Screen



To display this screen press **Enter** on the Parameter Type Maintenance screen.

SS608	Demonstration Company	USER BRERETM	18/08/93 13:26:09
Parameter Code Selection			
Parameter Type DAYT Day type			
1	Code	Description	
-	B	Bank holiday	
-	C	Closed	
-	S	Saturday/Sunday	
-	W	Working day	
Enter selection or required code _			
1=Select			
F3=Exit F12=Previous			

Fields:

1

Select. Enter 1 against a parameter code to display the detail screen.



Note: You should not create more than 10 parameter IDs for parameter type DAYT.



Tip: If more than 10 are set up, call logging will ignore the 11th and subsequent codes. As Working Days are often coded W, and could be at the end of the list of codes and ignored, this could lead to unpredictable results.



Select a parameter ID to display the Parameter ID Maintenance screen.

Parameter ID Maintenance Screen



To display this screen select a parameter code from the Existing Parameter IDs screen.

SS008	Demonstration Company	USER BRERETM	18/08/93 13:26:33
Codes File Maintenance			
Parm Type	DAYT	Day type	
Parm I.D	B		AMENDMENT
Description.: <u>Bank holiday</u>		Max size	30
Deferred rev. a/c day (1/0)?			<u>1</u>
Working day (1/0)?			<u>0</u>
F3=Exit F11=Delete F12=Previous			

Fields:

Description

Enter the parameter ID description. The length of this field is defined in the parameter type.

Value or Percentage Code

Enter one of the following:

P - Percentage.

V - Value.

Actual Percentage or Value Figures

Enter the required value, either a percentage or absolute value.

Value Field(s)

These fields are only displayed if extra values and characters have been specified for the parameter type.

Enter the required value(s). These are held under system generated parameter types PMC1, PMC2 or PMC3, depending on whether it is for line 1, 2 or 3.



Note: You should not create more than 10 parameter IDs for parameter type DAYT.



Tip: If more than 10 are set up, call logging will ignore the 11th and subsequent codes. As Working Days are often coded W, and could be

at the end of the list of codes and ignored, this
could lead to unpredictable results.



Press **Enter** to save any entries you have made.

Calendar File Control Maintenance



3/SSP

Use this option to define the number of service periods per year and set the current period and year at system setup time.



Note: This option requires exclusive use of the company.

A service period is a specific number of days, defined by a start and end date.

The system allows anything between one and 99 service periods per calendar year, but typically they are a week, 4 weeks, or a month long.



Note: You must set up the current service period and year when you install Service Management. Thereafter, the running of the Period End Routines option automatically increments the period (and year, when necessary).

Calendar Control Maintenance Screen



Select Calendar File Control Maintenance.

SS003	Demonstration Company CENTRAL BRANCH	USER BRERETM	9/09/93 16:31:32
Calendar Control Maintenance			
Current Year	93		
Current Week	34		
Current Period	34		
No. of Weeks This Year	52		
No. of Weeks Last Year	52		
No. of Periods This Year	52		
F3=Exit F11=Delete			

Fields:

Current Year

Enter the current year as two digits in the range 00 - 99.

Current Week

Enter the week number in the range 01 to 53.



Tip: The week must not be later than the week you enter in the No. Of Weeks This Year field.

Current Period

Enter the current Service Management period number, in the range 01 - 99.



Tip: The period must not be later than the period you enter in the No. Of Periods This Year field.

Once set, this field is updated by the Period End Routines option.

No. Of Weeks This Year

Enter the number of weeks this year. This must be a value of either 52 or 53.

No. Of Weeks Last Year

Enter the number of weeks in last year. The value entered must be 52 or 53.

No. of Periods This Year

Enter the number of periods in this (current) year as two digits in the range 01 - 99.



Tip: Once set up, these fields are system-maintained.



Press **Enter** to update.

Daily Calendar File Maintenance



4/SSP

Use this option to define and maintain a calendar of service and accounting periods.

You use this option when you install Service Management to define the calendar for current, previous and future years.



Note: An extra dummy year, one year previous to the first year actually required in the system, must be created at system set-up time, in order to allow definition of service or accounting years or both which span two calendar years. The Rebuild Period End Dates File option will not create period end date records for the first year defined on the daily calendar file.

After installation the option is used as necessary, to define all future years.



Note: This option requires exclusive use of the company.

Implications

Service periods are used widely in the system to control the scheduling of planned maintenance jobs and to monitor all jobs processed.

Accounting periods are used to control the postings to Accounts Receivable and the General Ledger from job and contract invoicing, particularly in relation to apportioning deferred revenue from contract invoices.

The calendar file data is essential to the system. Without it, contracts cannot be created, jobs cannot be processed, and invoices cannot be raised.

Daily Calendar Maintenance Screen 1



Select Daily Calendar File Maintenance.

SS969	Demonstration Company CENTRAL BRANCH	USER BRERETM	9/09/93 16:31:46
Daily Calendar Maintenance			
Year: <u>93</u>			
F3=Exit			

Fields:

Year

Enter the year to be added or updated.

If you are installing Service Management for the first time, create a dummy year, one year previous to the first calendar year required.

Make sure that the calendar is set up far enough into the future to enable scheduled visits to be generated.



Press **Enter** to display second Daily Calendar Maintenance screen .

Daily Calendar Maintenance Screen 2



To display this screen enter the appropriate year on the first Daily Calendar Maintenance screen and press **Enter**.

For each month, all the days are classified by day type (for example, bank holiday, or Saturday/Sunday, or working day and so on, as defined in the Codes/Parameter File Maintenance option under DAYT). In addition, the relevant dates are marked E, to show the end of service and accounting periods.

For each year, the end date of the first service period and the first accounting period is defined.

```

SS969          Z1 - C&T TEST COMPANY          USER GBJBAJKG    6/03/96
                  BIRMINGHAM BRANCH              14:44:02
Daily Calendar Maintenance

Year: 96
1st Service period - end date: 31/01/96
1st Account period - end date: 31/01/96

          1          2          3
January    1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1
DAY TYPE    W W W W W W W W W W W W W W W W W W W W W W W W W W W W
SERVICE PD  - - - - - - - - - - - - - - - - - - - - - - - - E
ACCOUNT PD   - - - - - - - - - - - - - - - - - - - - - - - - E

F3=Exit  F4=Prompt  F8=Update  F12=Previous
ROLL KEYS=Change month

06-37    SF    MW    KS    IM    II    KENB20A    PED129S1
  
```

Fields:

1st Service Period End Date

Enter the date of the first service period end.

1st Account Period End Date

Enter the date of the first accounting period end.

Day Type

Enter a valid day type code against each day of the month. Day type codes are set up in the codes/parameter file under parameter ID DAYT: the codes define working days and non-working days.

Service Pd

Service Pd and Account Pd fields must be blank or E.

Enter E under the date which represents the last day of a service period. You can enter E into more than one service period in a calendar month.

You must enter E for the date specified as the 1st Service Period End Date.



Note: The service period and the accounting period end dates, for the year being entered, could be in a previous calendar year. The dates must still be identified in the previous year with an E in both the Service Pd and Accounting Pd fields. To allow this, a dummy year must always be entered, one year previous to the first calendar year required.

Account Pd

Service Pd and Account Pd fields must be blank or E.

E is entered under the date which represents the last day of an accounting period. More than one accounting period may be keyed as E in a calendar month.

You must key in E for the dates specified as the first Account Period End Date.



Note: The service period and the accounting period end dates, for the year being entered, could be in a previous calendar year. The dates must still be identified in the previous year with an E in both the Service Pd and Accounting Pd fields. To allow this, a dummy year must always be entered, one year previous to the first calendar year required.

Period end dates will never be generated by the Period End Date Rebuild option for the first calendar year entered on the Daily Calendar file.



Note: After making changes in this option you must run the Rebuild Period End Dates File option. This ensures that the period end dates on the system accurately reflect the daily calendar detail. You are advised to check the period dates after the rebuild, using the Period End Dates Enquiry.



Page up and down to see the different months of the year. When you have entered all months, select **F8=Update** to update.

Branch File Maintenance



5/SSP

Use this option to set up each service branch operating the system within a company. Use this option at system setup time to define all branches, and thereafter as necessary to add new branches.



Note: This option requires exclusive use of the company.

A branch is a sub-division of a company, and is an organisational unit which controls its own service operations, but shares certain data with other branches.

Implications

You must define at least one branch for each company on the system, otherwise no access to the system is possible. (Note that at least one user must be authorised to a branch before the branch can be accessed.)

When you use the system, you are always signed on to a particular branch. You can be authorised to access one or more branches. If you have access to more than one, you can switch between them within the same session. The branch to which you are signed on determines the data you are able to access, and the ownership of the data you create.

Branch Maintenance Selection Screen



Select Branch File Maintenance.

SS010	Demonstration Company	USER BRERETM	9/09/93
	CENTRAL BRANCH		16:32:06
Branch Maintenance			
Branch Code	<u>CT</u>		
F3=Exit F4=Prompt			

Fields:

Branch Code

Select to amend an existing Branch Code.

Or: Enter a new Branch Code using up to a two character alphanumerical code.



Press **Enter** to display the Branch Maintenance
Detail screen.

Branch Maintenance Detail Screen



To display this screen select a branch code on the Branch Maintenance Selection screen and press **Enter**.

SS010	Z1 - UK Demonstration Company	USER GBJBALTW	8/05/98
	CENTRAL BRANCH		10:48:57
Branch Maintenance			
Branch Code.....?	CT		
Branch Name	CENTRAL BRANCH		
Address	CENTRAL HOUSE		
	MAIN STREET		
	NEWTOWN		
Post Code	NT01	1PC	
Telephone			
Time Zone ID ?			
Mileage Travel Rate		.50	
Average Travel Time	00:30		
Calendar Code ?			
Job Audit Log Queue	PRT01		
Error Message Queue			
F3=Exit F4=Prompt F8=Update F12=Previous			

Fields:

Branch Name

Enter the name of the branch, in up to 35 alphanumerics.

Address

Enter the branch address. Five lines are available.

Post Code

Enter the first section of the branch postcode, in the official postcode format.

Untitled

Enter the second section of the branch postcode, in the official postcode format.

Telephone

Enter the branch telephone number, using up to 15 alphanumerics.

Time Zone ID

Optionally enter a time zone for this branch, if it is located in a different zone from the system.

Mileage Travel Rate

This is a memo field only, since the Charge Per Mile/Km field in the customer's additional service details gives the rate.

Average Travel Time

Enter the branch default travel time, for use in call scheduling calculations. The field is five numerics, formatted hhh:mm.

This is a flat, best-guess figure which is used as the amount of travel time to be scheduled between jobs.

Calendar Code

A memo field only, for the current version.

Leave this field blank to use the standard system calendar.

Job Audit Log Queue

This is the name of the output queue to which the job audit log report (audit list of job maintenance activities) should be directed. If left blank, the queue specified for you in Application Manager will be used.

Error Message Queue

This field only appears if remote communications is active (see System Parameters Maintenance screen 4 of 5).

Enter the user or queue identity for receiving the reports on validation and transmission errors arising from remote communications.



Select **F8=Update** to save any changes you have made.

User/Branch Authorities Maintenance

1...
2...

6/SSP

Use this option to maintain the record of the branches to which each user is authorised, and to authorise users to branches.

If you are to be authorised to all branches for a company then enter a special branch code of *A, instead of specifying each branch individually.

Authority Maintenance Selection Screen



Select the User/Branch Authorities Maintenance option to see the Authority Maintenance Initial screen.

SS005	Demonstration Company CENTRAL BRANCH	USER BRERETM	9/04/94 11:33:35
-------	---	--------------	---------------------

Authority Maintenance

User ID..... BRERETM
Branch Code....?.

F3=Exit F4=Prompt

Fields:

User ID

Enter a valid user ID, using up to 10 alphanumeric.

Branch Code

If you want to authorise this user to a particular branch, then enter the branch code and press **Enter**. The Branch Marker field will appear on the screen.

If you want to see a list of all branches to which this user ID is currently authorised, then leave this field blank and press **Enter**. You will see the Branch Selection screen.

If you want to authorise this user to all branches, then enter the code *A and press **Enter**. The Default Branch Code field will appear on the screen.

Branch Marker

You only see this field if you entered both a user ID and a branch code other than *A in the Branch Code field.

Every time a user signs on and starts using Service Management the system has to find out which branch they want to use. Normally this means selecting from a list, but if one branch is selected by putting 1 in its Branch Marker field, then that is the branch the system will automatically assign to that user each time they sign on.

Bear in mind that a user can only have one branch marker.

0 - This is not the branch that this user will be in when they sign on to Service Management.

1 - This is the branch that this user will be in when they sign on to Service Management.

Default Branch Code

This field is only displayed if you entered a user ID and the branch code *A.

Every time a user signs on and starts using Service Management the system has to find out which branch they want to use. Normally this means selecting from a list, but if you enter a branch here, then that is the branch the system will automatically assign to that user each time they sign on.

Enter an existing branch.



Press **Enter**. If you entered a user and a branch, or a user and the *A code, then the new information is updated.

If you entered a user but left the branch blank, you see the Branch Selection screen.

Branch Selection Screen



To display this screen enter a user ID but leave the Branch Code field blank on the Authority Maintenance Selection screen.

This screen displays all the branches to which the user is authorised.

SS005	Demonstration Company CENTRAL BRANCH	USER BRERETM	9/04/94 11:33:44
Branch Selection			
User ID BRERETM			
1	Code Branch Name	Marker	
-	BR BIRMINGHAM BRANCH	0	
-	BT 'BRUM' TRAINING BRANCH	1	
-	CW CHORLEYWOOD BRANCH	0	
Enter a selection or a Branch Code ____			
1=select F3=Exit F12=Previous			

Fields:

1

Select. Enter 1 against a branch to maintain the branch marker. If the user is authorised to *A, that is, all branches, then if you select it with 1 you can maintain the Default Branch Code field.

Branch Marker

This column displays the marker for each branch.

0 - This is not the branch that this user will be in when they sign on to Service Management.

1 - This is the branch that this user will be in when they sign on to Service Management.

A user can only have one branch set to 1. To change the marker, zeroise the existing marker before setting up the new one.

Enter A Selection Or A Branch Code

Enter the branch you wish to maintain, instead of selecting from the list.



Press **Enter** to return to the Authority Maintenance Initial screen, with the Branch Marker or Default Branch Code field showing, as relevant.

Escalation Parameters Maintenance



7/SSP

Job escalation is the method by which the system alerts users to outstanding jobs which are approaching their contracted response time.

The way you set up this option controls the way in which job escalation operates for each Service Management branch. You do not have to use job escalation in Service Management, and if you do decide to use it you can implement it at any time.

You use this option to set the branch response time used at call logging. It can be defined either by division and model group, or as a default for any division/model group combination that has not been set up. The default response time will only be used if there is no match at a higher level in the response time hierarchy.



Note: This option requires exclusive use of the company.



Note: Escalation will take place only if the Start Job Escalation option is taken.

The following fields are defined for each service branch, and optionally each model group being serviced within the branch:

- Escalation Time Fence
 - The number of hours/minutes before its target response time that a job will start to escalate, for example, 4 hours.
- Escalation Step Interval
 - The number of hours/minutes between each escalation level (step) within the time fence, for example, 30 minutes.
- Report PM Jobs
 - Planned (scheduled) maintenance jobs can be excluded from the routine which sends escalation messages to defined users, so users are alerted to breakdown (call-out) jobs only.
- Report Contracted Responses Only
 - Only jobs for pieces of equipment covered by contract will send escalation messages to defined users.
- Default Response Time
 - This field holds the response time to be used as a branch default for jobs.
- Users to Receive Messages
 - You define a list of user IDs who will receive warning messages as jobs reach certain escalation levels.

Implications

Escalation is an optional facility in the system. If it is not required, the escalation parameters need not be defined.

The system assumes a seven day working week. If less than this is actually worked, the system still escalates Monday's jobs on Sunday, not on the preceding Friday.

Escalation Control Maintenance Selection Screen



Select Escalation Parameters Maintenance.

SS850	Demonstration Company	GBJBAMXB	30/06/95
	CENTRAL BRANCH		17:48:35
Escalation Control Maintenance			
Division.....?. ____			
Model Group.....?. ____			
Leave both fields blank to create the Default Branch Response Time.			
F3=Exit F4=Prompt			

Fields:

Division

Enter an existing division.

To set up the branch default response time, leave the division and model group fields blank.

Model Group

Enter an existing model group.

To set up the branch default response time, leave the division and model group fields blank.



Note: You should set up a default response time for each branch. The branch default time on the subsequent details screen will be used to set the call response time for equipment in a division and model group not otherwise specified, if there is no match at a higher level in the response time hierarchy.



Press **Enter** to display the Escalation Control Maintenance Detail screen.

Escalation Control Maintenance Detail Screen



To display this screen enter the appropriate division and model group on the Escalation Control Maintenance Selection screen and press **Enter**.

SS850	Demonstration Company CENTRAL BRANCH	BRERETM	9/04/94 13:43:58
Escalation Control Maintenance			
Division..... 10			
Model Group..... 100			
Report PM Jobs ? <u>0</u> (0=No,1=Yes)			
Report Contracted Responses Only (0/1) <u>0</u>			
Report Escalation Before Response Due (HH:MM) <u>4:00</u>			
Reporting Interval For Escalation (HH:MM) <u>1:00</u>			
Default Branch Response Time (HHH:MM) <u>8:00</u>			
Reports to be sent to :-			
Report Step	User ID	Screen Msg (0/1/2)	where 0=None,1=Notify,2=Break Msg.
<u>00</u>	<u>QSECOFR</u>	<u>2</u>	
<u>01</u>	<u>SUPRVSF</u>	<u>2</u>	
<u>02</u>	<u>OPERATR</u>	<u>1</u>	
<u>00</u>	<u> </u>	<u>-</u>	
<u>00</u>	<u> </u>	<u>-</u>	
<u>00</u>	<u> </u>	<u>-</u>	
			+
F3=Exit F8=Update F11=Delete F12=Previous			

Fields:

Report PM Jobs

Enter one of the following:

0 - Planned maintenance jobs will not have messages sent to the appropriate users when the jobs reach the designated escalation steps.

1 - Planned maintenance jobs will have messages sent to the appropriate users when the jobs reach the designated escalation steps.

Report Contracted Responses Only

Enter one of the following:

0 - All jobs will send messages to the appropriate users.

1 - Only jobs for pieces of equipment covered by contract will send messages when they reach the designated escalation steps.

Report Escalation

Enter a valid number of hours and minutes (hh:mm) between 00:15 and 99:45, with the minutes being a multiple of 15. This is the amount of time before a job's target time that it will start to escalate.

Reporting Interval For Escalation

Must be a valid number of hours and minutes (hh:mm) between 00:15 and 99:45, with the minutes being a multiple of 15. This is the time interval between escalation steps for this model group (within the product division) within the branch.

Default Branch Response Time (hhh:mm)

A job's target date and time are calculated by adding the relevant response hours to the job's date and time when it was first logged (and adjusting to allow for working hours and days).

Relevant hours are found by running through the response time hierarchy, looking for the hours in:

1. Special serial numbers.
2. Contract equipment/line.
3. Contract header.
4. Contract type (incl. *NO).
5. Default branch response time.



The response times defined in a contract can be altered by a percentage in the 3-D matrix.

Report Step

Enter a step in the range 00 to 98. The first record will be for step 00, which is when the job has reached, or passed, its target date and time. The second record is for step 01, and so on, or as determined by the particular escalation pattern set up.

98 is the step when the call is logged. The call will stay at this, until the Report Escalation Before Response Due time is reached. The call's report step is then updated to the highest step value listed on this screen; it decreases, as the escalation steps are reached.

User ID

Enter a valid user ID.

Screen Message

Enter one of the following:

- 0 - No message will be issued when this step is reached.
- 1 - A message will be sent to this user's message queue.
- 2 - A message will be sent to this user in break mode.



Note: If step 00 is reached, and a break message is indicated, the message will be sent on the first occasion. At any subsequent escalation cycle, there will be no message for that job.

The message includes the sender (for example, QPGMR), the message date and time of origin, the job number, the escalation step now reached, the job target date and time, engineer number, site customer's name, the model and serial number, and the time to target (hh:mm).



Select **F8=Update** to save any changes you have made.

Rebuild Of Period End Date File



8/SSP

Use this option to rebuild all service and accounting period end dates for a company, typically after making any changes in the Daily Calendar Maintenance option.

A service period is a specific number of days, defined by a start and end date. The system holds an end date for each service period.

An accounting period is a specific number of days, defined by a start and end date. The system holds an end date for each accounting period.

The option sends a batch job which deletes all existing period end dates for a company. It rebuilds them for both service and accounting periods, using the details from the Daily Calendar Maintenance option (where the period end markers are specified).



Note: This option requires exclusive use of the system.



Tip: You must run this option after making any changes in the Daily Calendar Maintenance option, since the period end dates are used extensively in the system.

You are advised to use the Period End Dates Enquiry option after the rebuild, to check that the period end dates are as expected.

System Parameters File Maintenance

9/SSP

Use this option to maintain the fields which control the system for a specific company.



Tip: This option is in effect an extension to the Company Profile File Maintenance option. It is not a parameter file in the same sense as the Codes/Parameter File Maintenance option in Service Management, or the Descriptions option in Inventory Management.

This option is used at system set up time, but infrequently thereafter.



Note: This option requires exclusive use of the system.

A company can be sub-divided into branches, but these branches will all operate under the controlling system parameters defined for the company.

System Parameters Maintenance Screen 1



Select System Parameters File Maintenance.

SS011		Z1 - C&T TEST COMPANY		USER GBJBAJKG		10/07/96	
						12:23:22	
System Parameters Maintenance						Screen 1 of 5	
Call History Window - How Many Calls to Display.....	<u>5</u>						
Processing by Month or Term (0=Month, 1=Term).....	<u>1</u>						
Zone Code Mandatory (1/0).....	<u>0</u>						
Allow Service Cover on Pending Contracts (1/0).....	<u>1</u>						
No. of Repeat Calls in Sequence = Specialist Call.....	<u>5</u>						
% to Shorten Response on Specialist Call.....	<u>50.00</u>						
Minimum Number of Calls Between Emergency Calls.....	<u>2</u>						
Allow New Job at Technical Reporting (1/0).....	<u>1</u>						
No. of Days Before Contract Expires to Shorten Response....	<u>30</u>						
Shorten Response by Time / Percentage (0=Time, 1=%age)....	<u>0</u>						
Time to Shorten Response (Minutes).....	<u>240</u>						
Percentage to Shorten Response.....	<u>.00</u>						
Range of Percentages - Minimum.....	<u>.00</u>						
- Maximum.....	<u>.00</u>						
F3=Exit							
05-64	SP	MW	KS	IM	II	KENB20A	PET178S2

Fields:

Call History Window - How Many Calls To Display

Not used in current system. The call history window in Call Logging defaults to 5 calls.

Processing By Month Or Term

Enter one of the following:

0 - The prices entered for billing are for a month.

1 - The prices entered for billing are for the term of the contract. You cannot use term pricing for meterage contracts.

This parameter cannot be altered once any contract has been priced/invoiced. It must be correctly set before the system goes live, as it cannot be changed later.

Zone Code Mandatory

Enter one of the following:

0 - The zone code entry in the Customer Additional Service Details option is optional.

1 - The zone code entry in the Customer Additional Service Details option is mandatory.



Note: In the Company Profile File Maintenance option, third screen, you can set up a company default (which may be overwritten at site address level) for Mileage to be Charged by Mileage

Zones.

Allow Service Cover On Pending Contracts

Enter one of the following:

0 - A field on the contract header defaults to prevent calls on a pending contract. If the customer calls with a problem, an engineer will not be sent unless this field is changed.

1 - A field on the contract header defaults to allow calls on a pending contract. If the customer calls with a problem, an engineer can be sent, just as if the contract were active. You may wish to set this on for the sake of customer relations. Remember, it can be altered on the contract header.

No Of Repeat Calls In Sequence = Specialist Call

When the number of repeat calls for the same machine reaches the number defined here, the default job category defined for a specialist call is used on the call logging screen.

% To Shorten Response On Specialist Call

Where a specialist call has been recognised in call logging, the response time retrieved for that call will be reduced by the percentage defined here.

Minimum Number Of Calls Between Emergency Calls

The value entered here prevents the use of the emergency indicator until this number of consecutive non-emergency calls has been logged. This is to prevent customers taking advantage of the emergency service.

This emergency indicator is on the call logging screen. When the job is an emergency, the target date and time is set to the system date and time - that is, now.

Allow New Job At Technical Reporting

Enter one of the following:

0 - You cannot create a new job when technical reporting within the Engineer Work Allocation option.

1 - When you go into technical reporting for a job (by entering 99 against a job in the Engineer Work Allocation option) the New Job Required field is displayed. Enter 1 there to enter a new job for an existing or new machine at the same customer's site.

No Of Days Before Contract Expires To Shorten Response

Not used in current system.

Shorten Response By Time/Percentage

Not used in current system.

Time To Shorten Response

Not used in current system.

Percentage To Shorten Response

Not used in current system.

Range Of Percentages - Minimum

Not used in current system.

Range Of Percentages - Maximum

Not used in current system.



Press **Enter** to display the second System Parameters Maintenance screen.

System Parameters Maintenance Screen 2



To display this screen press **Enter** on the first System Parameters Maintenance screen.

SS011	Demonstration Company	USER BRERETM	9/09/93
			17:04:59
System Parameters Maintenance			Screen 2 of 5
Print Job Documentation (1/0).....			0
Minutes In Between Job Documentation.....			0
Download Call Information to PC (1/0).....			0
Minutes In Between PC Download.....			0
Check Kits Before Assigning Engineer (1/0).....			0
Print Engineers Name on Service Invoice (1/0).....			0
Technical Report Text Mandatory for T&M Calls (1/0).....			0
Engineer Resupply - Send to Home (1/0).....			0
Maximum Calls Displayed on Engineer Work Queue.....			10
Maximum Customer Importance - Customer Invoice Level.....			4
Customer Ref. Mandatory on Call Reporting if VAT free (1/0)			0
Small Invoice Value.....			.00
F3=Exit F12=Previous			

Fields:

Print Job Documentation

Not used in current system.

Minutes In Between Job Documentation

Not used in current system.

Download Call Information To PC

Not used in current system.

Minutes In Between PC Download

Not used in current system.

Check Kits Before Assigning Engineer

Enter one of the following:

0 - No check is made for van stock kit.

1 - When assigning a job to an engineer the system checks to determine if the kit item number set up on the model is present in the engineer's stock room. If it is not present, a reason code for non-allocation is entered on the call logging screen.

Inventory Management must be in use if you want to use this function.

Print Engineer's Name On Service Invoice

Not used in current system.

Technical Report Text Mandatory For T&M Calls

Not used in current system.

Engineer Resupply Send To Home

Not used in current system.

Maximum Calls Displayed On Engineer Work Queue

Not used in current system.

Maximum Customer Importance Customer Invoice Level

A customer's importance is set up in the Customer Additional Service Details option, and is used by the 3-D matrix to help determine response times.

Enter here the setting which is to indicate the most important of your customers. It is best to enter either 1 or 4 here.

Customer Ref Mandatory On Call Reporting If VAT Free

Not used in current system.

Small Invoice Value

Not used in current system.



Press **Enter** on the second System Parameters Maintenance screen to display the third.

System Parameters Maintenance Screen 3



To display this screen press **Enter** on the second System Parameters Maintenance screen.

SS011	Demonstration Company	USER BRERETM	9/09/93
			17:06:17
System Parameters Maintenance		Screen 3 of 5	
Estimates Allowed for Billing (1/0)..... 1			
Maximum Number of Estimates Allowed to Bill..... <u>11</u>			
Estimates Allowed for Reconciliation (1/0)..... 0			
No. of Days Prior to Invoice Date to Trigger Estimate..... 20			
No. of Days Allowed for Return of Meter Card..... <u>10</u>			
Actual Reading Validation Parameters:			
% Within Estimate Reading Allowed..... 20			
Multiple of Minimum Copies Allowed..... <u>2</u>			
Copy Price Conversion Factor (Pence to Pound)..... <u>100</u>			
Item Types to be Invoiced:			
	Type	Description	Abbreviation
1.	<u>1</u>	Major	MAJ
2.	<u>2</u>	Minor	MIN
3.	<u>3</u>	Consume	CON
4.	<u>4</u>	Supplies	SUP
F3=Exit F4=Prompt F12=Previous			

Fields:

Estimates Allowed For Billing

Enter one of the following:

0 - Only actual readings are allowed when pricing meterage contracts.

1 - Estimated readings are allowed when pricing meterage contracts. This value is used in the contract header, but can be changed.

This field defaults to the contract header service parameters window, but can be changed.

Maximum Number Of Estimates Allowed To Bill

Enter the number of default estimates allowed in the contract header, in the range one - 999, (where it may be amended).



Note: This field is only used if the Estimates Allowed For Billing field is set on.

Estimates Allowed For Reconciliation

Enter one of the following:

0 - Only actual meter values are allowed in the reconciliation calculation. This is the recommended setting.

1 - Estimates are allowed in the reconciliation calculation.

Reconciliation is a type of meter billing where there is a review of usage; an invoice may then be raised, for a meter count higher than the minimum agreed in

the contract and not yet billed; or, a credit may be given where the meter count is below that previously estimated and billed, but greater than the minimum.

No Of Days Prior To Invoice Date To Trigger Estimate

This sets the maximum number of days before the invoice date that the system is to generate estimated readings.

For example, if an electricity company sets its invoice date as 31st May, it could enter 20 here to produce estimates on the 11th May, in time for customers to receive their estimates and return their own readings if preferred.

No Of Days Allowed For Return Of Meter Card

This sets the number of days before the invoice date that customers must return their meter cards in order to enter them in time for invoicing.

% Within Estimate Reading Allowed

Sometimes gross errors may be entered for meter readings - a customer might enter a date in the reading box, for example. Any reading which falls outside this percentage of the estimate will be registered as an error.

Multiple Of Minimum Copies Allowed

This value is used to check for errors in meter readings being entered from meter cards or in technical reporting. The parameter used is the minimum value assigned to the machine in the conditions which have been set up for the contract line.

Copy Price Conversion Factor (Pence To Pound)

Copy prices are set up in contract conditions as pence or cents per copy, rather than as decimals of the main currency unit. This factor is used to convert the copy price back to the main currency unit.

For example, if you enter 100 here, then the system moves the decimal point two points to the left, and 0.25 would become 0.0025.

Item Types To Be Invoiced: Type Code

Enter the four item types to be invoiced.

These are setup in Inventory Management. See Descriptions Maintenance under parameter type PTYP for more details.

Item Types To Be Invoiced: Description

Enter the descriptions of the four item types to be invoiced.

These are setup in Inventory Management. See Descriptions Maintenance under parameter type PTYP for more details.

Item Types To Be Invoiced: Abbreviation

Enter an abbreviation for the four item types to be invoiced.

These are setup in Inventory Management. See Descriptions Maintenance under parameter type PTYP for more details.



Note: Once you have set these up they can only be amended by editing the file SSP04.



Press **Enter** to display the fourth System Parameters Maintenance screen.

System Parameters Maintenance Screen 4



To display this screen press **Enter** on the third System Parameters Maintenance screen.

SS011	Z1 - UK Demonstration Company	USER GBJBALTW	8/05/98
			10:56:49
System Parameters Maintenance			Screen 4 of 5
More than one machine allowed on a breakdown call.....: <u>0</u>			
More than one breakdown call allowed at one time.....: <u>1</u>			
Position cursor during call logging.....: <u>1</u>			
Credit control by branch.....: <u>0</u>			
Default expiry days for messages.....: <u>3</u>			
Default invoice start date to first of the month.....: <u>0</u>			
Technical Report generated if receptionist completes call.: <u>1</u>			
Number of days between calls to generate repeat call.....: <u> </u>			
Automatic Call Assignment active (1/0).....: <u>1</u>			
Remote Communications active (1/0).....: <u> </u>			
Default Re-Transmit flag (/1/0).....: <u> </u>			
F3=Exit F12=Previous			
MA	a	05/064	

Fields:

More Than One Machine Allowed On A Breakdown Call

Enter one of the following:

0 - Only one machine can be logged on a job number.

1 - Additional machines for the site can be logged on one job number, after the call for the first machine has been updated.

See the fourth company profile screen for the setting of the One Machine Per PM Job field, to allow more than one machine on a planned maintenance job.

More Than One Breakdown Call Allowed At One Time

Enter one of the following:

0 - Only one incomplete job for a machine can exist. This is not the right setting if you deal with large machines, which might very well have more than one repair logged.

1 - Additional breakdown jobs can be logged for a machine, even if other jobs are open or in progress.

Position Cursor During Call Logging

This value sets the position of the cursor on entry to Call Logging, as follows:

1 - Cursor on Account Number field.

2 - Cursor on Contract Number field.

3 - Cursor on Customer Order Number field.

Credit Control By Branch

0 - All jobs for the company are displayed in Credit Call Maintenance.

1 - The Credit Call Maintenance option, for jobs which have been set to bad credit status, will only display those jobs for the user's branch.

Default Expiry Days For Message

This determines how long engineer messages remain in the system. The value is used as a default when sending a message, at which time the value can be changed.



Note: This value is not used for machine messages, which take a default date of 99/99/99, that is, an indefinite expiry date.

Default Invoice Start Date To First Of The Month

Enter one of the following:

0 - Any new contract being entered into the system will assume an invoice start date the same as the contract start date. This can be amended within Contract Maintenance.

1 - Any new contract being entered into the system will assume an invoice start date of the first of the month following the contract start date. days not invoiced will be included on that invoice. For example, if a contract starts on 8th August, then the first invoice will be sent on 30th September, and will include the charge for 8th - 31st August.



Tip: The invoice start date can be changed within Contract Maintenance.

Technical Report Generated If Receptionist Completes Call

Enter one of the following:

0 - A technical report record is not generated if the call receptionist solves the problem over the telephone.

1 - A technical report record is generated if the call receptionist uses the option to complete a call.

Number Of Days Between Calls To Generate Repeat Call

This field is for future development.

Automatic Call Assignment Active

0 - You do not want to use automatic call assignment. This setting prevents the display of the fifth System Parameters Maintenance screen - any previous settings on that screen are zeroised. **F8=Update** to update is displayed at the foot of this screen.

1 - Automatic call assignment is available for the company. This enables display of the fifth System Parameters Maintenance screen, to set up the company's Automatic Call Assignment parameters.

ACA operation can also be limited by settings on the model, job category and engineer.

Remote Communications Active

Enter one of the following:

0 - Engineers do not use remote communications (for example, hand-held terminals) to transmit job details or messages.

1 - With the Service subsystem active, incoming and outgoing sleeper programs monitor when engineers log on, so that job and message details can be transmitted, or technical report details received.

Default Re-Transmission Flag

If the Remote Communications Active field is set off, then set this field to 9 to condition off the re-transmit field on the call logging screen.

If the Remote Communications Active field is set on, select one of the following:

Blank - You must enter 0 or 1 on the Field Logging screen.

0 - Allows transmission of a job, but not re-transmission of any call logging changes.

1 - Whenever you spot a problem on an incoming transaction, it will be automatically re-transmitted to the engineer.

These defaults can be overwritten on the Call Logging screen.

Functions

F8

Update. This key is only available if you set the Automatic Call Assignment field to 0.



Press **Enter** on the fourth System Parameters Maintenance screen to display the fifth.

System Parameters Maintenance Screen 5



To display this screen press **Enter** on the fourth System Parameters Maintenance screen.



Note: This screen is only displayed if the Automatic Call Assignment Active field on System Parameters Maintenance screen 4 is set to 1.

SS011	Demonstration Company	USER BRERETM	26/10/93 14:03:11
System Parameters Maintenance			Screen 5 of 5
Time within which calls are automatically assigned.....: <u>8</u>			
Assign CM calls only to maintenance-only engineers (0/1)...: <u>1</u>			
Assign repeat calls only to original engineers (0/1).....: <u>1</u>			
Assign calls only to preferred engineer for machine (0/1)..: <u>1</u>			
Assign calls only to engineers carrying kit (0/1).....: <u>0</u>			
Permitted % increase in response time.....: <u>10.00</u>			
Permitted appointed call overlap time (minutes).....: <u>15</u>			
Engineer workload threshold (hours).....: <u>0</u>			
Automatic Call Assignment sleeper wait time (minutes).....: <u>3</u>			
Maximum calls to assign between waits.....: <u>10</u>			
F3=Exit F8=Update F12=Previous			

Fields:

Time Within Which Calls Are Automatically Assigned

Enter the number of hours before call target time when automatic call assignment will pick up an unassigned call and allocate it to a team (or to the preferred engineer, if the fourth field on this screen is set to 1). This prevents the system allocating visits too far in advance.

Assign CM Calls Only To Maintenance-Only Engineers

CM is short for contracted maintenance; it is not a job category, nor a scheduled visit profile code.

Enter one of the following:

0 - Calls will be allocated to any engineer within the team.

1 - System-generated calls (that is, planned visits) will only be assigned to those engineers who have been assigned to contract maintenance.

Assign Repeat Calls Only To Original Engineers

Enter one of the following:

0 - Any call identified as a repeat call is assigned to any engineer within the team.

1 - Any call identified as a repeat call is assigned to the engineer who made the original visit.

Assign Calls Only To Preferred Engineer For Machine

0 - Calls are assigned to any engineer within the team.

1 - Calls are assigned to the engineer defined on the installation, or, if none has been defined, to the team.

Assign Calls Only To Engineers Carrying Kit

Enter one of the following:

0 - The system does not check whether the engineer is carrying the kit item for the equipment to be serviced.

1 - The system checks the engineer's van stock (defined for that engineer), to see if the engineer is carrying the kit item for the equipment to be serviced.

Permitted % Increase In Response Time

Calls which exceed their target time by up to the percentage entered here, will still be scheduled by automatic call assignment.

Above this figure, the call is not allocated and the appropriate reason code (parameter type ETAR) is added to the job.

Permitted Appointed Call Overlap Time

Appointments will be allowed to overlap up to the value in minutes entered in this field.

Engineer Workload Threshold

Not used in the current system.

Automatic Call Assignment Sleeper Wait Time

The automatic call assignment procedure (which runs in the background) will wait for the number of minutes entered here before it runs again.

Maximum Calls To Assign Between Waits

Automatic call assignment will only attempt to schedule this number of calls for an engineer each time it runs, to avoid overloading an engineer.



Select **F8=Update** to update the system.

Working Days Calendar File Maintenance



10/SSP

Use this option to provide alternative calendars to the system's daily calendar. The alternative working calendars would define working days, Saturdays/Sundays, public holidays and shut downs for future use at branch and customer levels.

Calendar codes and descriptions are set up via the Codes/Parameter File Maintenance option, under parameter type CCAL.

Implications

Details of a company's calendar day types are held on the same file as its customers' calendar data.

Company period end dates, set up on a separate file and used in the system for service and accounting period ends, apply to its customers' calendars.

There is no functionality associated with the customer records on the calendar file in the current system. Customer calendars may only be used for memo purposes.

Take the Working Days Calendar File Maintenance option to see the Working Days Calendar Maintenance Selection screen.

Working Days Calendar Maintenance Selection Screen

 Select Working Days Calendar Maintenance.

Fields:

Calendar Code

Enter an existing calendar code.

 Press Enter to see two more input fields appear.

SS082		Z1 - UK Demonstration Company		USER GBJBALTW	8/05/98
		CENTRAL BRANCH			11:00:23
Working Days Calendar Maint.			UPDATE		
Calendar code.....		ED	Education		
Year to maintain.....		00			
Base upon calendar code...?..		00	(Enter based-on code and year to copy existing details if required)		
and year.....		00			
n	Year	n	Year	n	Year
-	93	-		-	
-	98	-		-	
1=Amend, 4=Delete					
F3=Exit F4=Prompt F8=Update F12=Previous					
MA		a		07/029	

Fields:

Base Upon Existing Calendar Code

Enter one of the following:

0 - Do not base the calendar on an existing calendar.

1 - Base the calendar on an existing calendar.

Base Upon Calendar Code

Enter an existing calendar to copy.

n

Enter one of the following:

1 - To amend an existing calendar.

4 - To delete an existing calendar.

 Select a calendar code and year to display the Working Days Calendar Maintenance Detail

screen.

Working Days Calendar Maintenance Detail Screen



To display this screen select a calendar code and year on the Working Days Calendar Maintenance Selection screen.

SS082	Demonstration Company	USER BRERETM	26/10/93
	CENTRAL BRANCH		14:23:14
Working Days Calendar Maint.		ADDITION	
Calendar code.....	C01 Customer Group 999		
Year to maintain.....	93		
	1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1		
January	B S S C C C C C S S W W W W S S W W W W S S W W W W S S		
February	W W W W W S S W W W W W S S W W W W S S W W W W S S		
March	W W W W W S S W W W W W S S W W W W S S W W W W S S W W W		
April	W W S S C C C C B S S B C C C S S W W W W S S W W W W W	+	
F3=Exit F4=Prompt F8=Update F12=Previous			

Fields:

Day Types

This screen requires you to input valid day types (DAYT) for the four months displayed. Page down to display the other months in the year, for entry of their day types.

If a calendar has been copied, just amend the codes that need changing.



Select **F8=Update** to save any changes you have made.

Codes/Parameter File Enquiry



12/SSP

Use this option to enquire on the details of parameter codes.

Codes/Parameter File Enquiry Screen 1



Select Codes/Parameter File Enquiry.

SS500	Z1 - C&T TEST COMPANY BIRMINGHAM BRANCH	USER GBJBAJKG	26/04/96 13:20:18
Codes/Parameter File Enquiry			
Parameter Type		_____	
Parameter I.D.		_____	
Type	Description		
DAYS	* Day Descriptions		
DAYT	Day type		
DISC	Discount reasons		
EGRD	Engineer job grades		
EQST	Equipment Status		
ERRC	* Remote Comms Error Codes		
ETAR	* ACA Errors & Job Sub-Status		
FLTC	Faults		
GLPR	Global Price Increase Code		
GLTX	* G/L Deferred Rev.-Trans.Text	+	
F3=Exit F4=Code Selection			
06-20	SP	MW	KS IM II KENB20A PED129S1

Fields:

Parameter Type

Enter an existing parameter type. To see a list of all the parameter IDs set up under this type, press **F4=Code Selection**.

To see the details of one particular parameter ID, enter that ID in the field below and press **Enter**.

Parameter Type descriptions starting with * are system required codes; access to these codes for maintenance is restricted.

Parameter ID

Enter the parameter ID whose details you wish to see.

If you enter a parameter ID then you must also enter the relevant parameter type.



Enter a parameter type and select **F4=Code Selection**.

Parameter Code Selection Screen



To display this screen select a valid parameter type from the first Codes/Parameter File Enquiry screen and press **F4=Code Selection**.

SS608	Demonstration Company	USER BRERETM	14/12/93
	CENTRAL BRANCH		11:38:44
Parameter Code Selection			
Parameter	Type	DAYT	Day Type
1	Code	Description	
-	B	Bank holiday	
-	C	Closed	
-	S	Saturday/Sunday	
<u>1</u>	W	Working day	
1=Select			
F3=Exit F12=Previous			

Fields:

1

Enter 1 against the parameter ID whose details you want to display.



Select a parameter ID and press **Enter** to display the second Codes/Parameter File Enquiry screen.

Codes/Parameter File Enquiry Screen 2



To display this screen select a parameter code from the Parameter Code Selection screen.

This screen displays the setup details for this parameter ID.

SS508	Demonstration Company	USER BRERETM	14/12/93
	CENTRAL BRANCH		11:38:59
Codes/Parameter File Enquiry			
Parm Type	DAYT	Day Type	
Parm I.D	W		
Description.:	Working day	Max size	30
Deferred Rev. Acct. day (1/0)?	1		
Working day (1/0)?	1		
F3=Exit F12=Previous			



Select **F3=Exit** to return to the menu.

Daily Calendar File Enquiry



14/SSP

Use this option to enquire on the definition of working and non-working days and on service and accounting period end dates.

Daily Calendar File Enquiry Selection Screen



Select Daily Calendar File Enquiry.

SS969	Demonstration Company CENTRAL BRANCH	USER BRERETM	14/12/93 11:39:16
Daily Calendar File Enquiry			
Year: <u>93</u>			
F3=Exit			

Fields:

Year

Enter the year you want to enquire on.



Select a year and press **Enter** to see the first Daily Calendar File Enquiry screen.

Daily Calendar File Enquiry Screen 1



To display this screen select the year on the
Daily Calendar File Enquiry Selection screen.

This screen displays all the details of the calendar year selected. The calendar months in the year are displayed in turn. For each month, the day type code for each day is shown (bank holiday, Saturday/Sunday, working day, and so on) and the date(s) on which the service period(s) and accounting period(s) end.

SS969	Demonstration Company	USER BRERETM	14/12/93
	CENTRAL BRANCH		11:39:24
Daily Calendar File Enquiry			
Year: 93			
1st Service period - end date: 15/01/93			
1st Account period - end date: 29/01/93			
1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1			
April			
DAY TYPE	W W S S W W W B S S B W W W S S W W W W S S W W W W		
SERVICE PD	E E E E E		
ACCOUNT PD	E		
F3=Exit F12=Previous			
ROLL KEYS=Change month			



Select **F3=Exit** to return to the menu.

Branch File Enquiry



15/SSP

Use this option to enquire on the details of any service branch within a company.

Branch File Enquiry Detail Screen



To display this screen take the Branch File Enquiry option and select the appropriate branch.

SS510	Z1 - UK Demonstration Company	USER GBJBALTW	8/05/98
	CENTRAL BRANCH		11:10:14
Branch Maintenance			
Branch Code....?. <u>CT</u>			
Branch Name	CENTRAL BRANCH		
Address	CENTRAL HOUSE MAIN STREET NEWTOWN		
Post Code	NT01	1PC	
Telephone			
Time Zone ID			
Mileage Travel Rate		.50	
Average Travel Time	30		
Calendar Code			
Job Audit Log Queue PRT01			
Error Message Queue			
F3=Exit F12=Previous			
MA	a		01/001

Fields:

Branch Name

The branch name is displayed.

Branch Address

The branch address is displayed.

Postcode

The postcode is displayed.

Telephone Number

The branch telephone number is displayed.

Time Zone ID

If the branch is in a different time zone to the system, then that zone is displayed here.

Mileage Travel Rate

The branch cost rate per mile is displayed.

Average Travel Time

This displays the branch default travel time, for use in call scheduling calculations. The field is formatted hhh:mm.

Calendar Code

This is a memo field.

Job Audit Log Queue

This is the name of the output queue to which the job audit log report (audit list of job maintenance activities) will be directed. If left blank, the queue specified for you in Application Manager will be used.

Error Message Queue

This is the user ID to which any remote communications error messages should be sent.



Select **F3=Exit** to return to the menu.

Period End Dates Enquiry



18/SSP

Use this option to enquire on the service period end dates for a specific year.

Period End Dates Enquiry Initial Screen



Select Period End Dates Enquiry.

SS504	Demonstration Company	USER BRERETM	17/01/94
	CENTRAL BRANCH		11:21:31
Period End Dates Enquiry			
	Year	<u>93</u>	
F3=Exit			

Fields:

Year

Enter the year you want to enquire on.



Press **Enter** to display the Period End Dates Enquiry Detail screen.

Period End Dates Enquiry Detail Screen



To display this screen select the appropriate year on the Period End Dates Enquiry Initial screen and press **Enter**.

All service period numbers and end dates are displayed.

SS504	Demonstration Company	USER BRERETM	17/01/94
	CENTRAL BRANCH		11:21:31
Period End Dates Enquiry			
	Year	93	
Period	End date	Period	End date
01	0/00/00	15	0/00/00
02	0/00/00	16	0/00/00
03	0/00/00	17	0/00/00
04	0/00/00	18	0/00/00
05	0/00/00	19	0/00/00
06	0/00/00	20	0/00/00
07	0/00/00	21	0/00/00
08	0/00/00	22	0/00/00
09	0/00/00	23	0/00/00
10	0/00/00	24	0/00/00
11	0/00/00	25	0/00/00
12	0/00/00	26	0/00/00
13	0/00/00	27	0/00/00
14	0/00/00	28	0/00/00
		29	0/00/00
		30	0/00/00
		31	0/00/00
		32	0/00/00
		33	0/00/00
		34	0/00/00
		35	0/00/00
		36	0/00/00
		37	0/00/00
		38	0/00/00
		39	0/00/00
		40	0/00/00
		41	0/00/00
		42	0/00/00
		43	0/00/00
		44	0/00/00
		45	0/00/00
		46	0/00/00
		47	0/00/00
		48	0/00/00
		49	0/00/00
		50	0/00/00
		51	0/00/00
		52	0/00/00
F3=Exit F12=Previous			



Select **F3=Exit** to return to the menu.

Working Days Calendar File Enquiry

1... 20/SSP **2...**

This option is for future use within the system.

The enquiry displays the day types for all twelve months in the year, for a selected calendar code and year.

Working Days Calendar File Enquiry Selection Screen



Select Working Days Calendar File Enquiry.

Use this screen to select the calendar you want to enquire upon.

SS582		Z1 - UK Demonstration Company		USER GBJBALTW		8/05/98	
		CENTRAL BRANCH				11:11:58	
Working Days Calendar Enquiry							
Calendar code.....		ED		Education			
n	Year	n	Year	n	Year	n	Year
-	93						
-	98						
1=Details							
F3=Exit F12=Previous							
MA		a				08/002	

Fields:

n

Enter 1 to view details of the calendar.



Select the calendar and press Enter to display the Working Days Calendar File Enquiry Details screen.

Working Days Calendar File Enquiry Details Screen



To display this screen select the calendar and press Enter on the Working Days Calendar File Enquiry Selection screen.

SS582	Demonstration Company		USER BRERETM	17/01/94																								
	CENTRAL BRANCH			11:21:16																								
Working Days Calendar Enquiry																												
Calendar code.....	C01	Cust Grp 999																										
Year	93																											
	1234567890 1234567890 1234567890																											
January	B	S	S	W	W	W	W	W	S	S	W	W	W	W	W	S	W	W	W	S	S	W	W	W	W	W	S	S
February	W	W	W	W	W	S	S	W	W	W	W	W	W	W	S	S	W	W	W	W	S	W	W	W	W	W	S	S
March	W	W	W	W	W	S	S	W	W	W	W	W	W	W	S	S	W	W	W	W	S	W	W	W	W	W	S	W
April	W	W	S	S	W	W	W	W	B	S	S	B	W	W	W	S	S	W	W	W	W	W	W	W	W	W	W	W
May	S	S	B	W	W	W	W	S	S	W	W	W	W	W	S	S	W	W	W	W	W	W	W	W	W	S	S	
June	W	W	W	W	S	S	W	W	W	W	W	S	W	W	W	W	S	W	W	W	W	W	W	W	S	W	W	
July	W	W	S	S	W	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	W	W	S	S	C	C	
August	S	W	W	W	W	S	S	W	W	W	W	S	W	W	W	W	S	W	W	W	W	W	W	W	S	S	B	
September	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	W	W	S	W	W	W	
October	W	S	S	W	W	W	W	S	S	W	W	W	W	W	S	S	W	W	W	W	W	W	W	S	W	W	S	
November	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	W	W	W	W	W	W	S	W	W	W	
December	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	W	W	S	S	B	W	

F3=Exit F12=Previous



Select **F3=Exit** to return to the menu.