

-
-
-
-
-

Chapter 4

Service Maintenance



Engineer Master File Maintenance

1... **1/SSM** **2...**

Use this option to maintain the details of all engineers employed within the service operation.

The engineer details are used:

- To link an engineer with a stock location, enabling generation of inventory movements against that stock location when the engineer uses parts to effect a repair.
- To link an engineer with a region for reporting purposes.
- To record an engineer's absence status, and hence (optionally) prevent new jobs being assigned.
- To enable the cost of an engineer's time to be calculated on each service job.
- To distinguish between field and workshop engineers, who may be charged out at different hourly rates.

Engineer Maintenance Initial Screen



Select Engineer Master File.

SS045	Demonstration Company CENTRAL BRANCH	USER BRERETM	22/11/93 12:29:40
Engineer Maintenance			
Engineer.....?.. <u>E0001</u>			
F3=Exit F4=Prompt			

Fields:

Engineer

Enter an engineer.



Press **Enter** to display the Engineer Maintenance screen.

Engineer Maintenance Screen



To display this screen select the engineer on the Engineer Maintenance Initial Screen and press **Enter**.

SS045	61 - 61 - Demonstration Company	USER SSV3	11/12/95
	CENTRAL BRANCH		14:45:32
Engineer Maintenance			
Engineer.....	E0001	UPDATE	
Name.....	ARCHIE ABLETT		
Address Line 1	32 ACACIA BOULEVARD		
2	GREENLANDS		
3	REDDITCH		
4	WORCS		
5		Geo. Code...	B9B BKK
Telephone.....	01527 588665	Ext.	
Supply Stockroom.		Radio	Page Code...
Stock Location...	01	Team Code...?	TM1 Team 1
Vehicle Reg.No...		Absent Code...?	
Manager's Code...			
Grading Code...?	FE Field engineer		
Cost Per Hour....	25.00000	Region...?..	CT Central
Workshop Engineer.....	0 (1=yes 0=no)		
Include Engineer in Automatic Call Assignment....	1		
Engineer Account.	EAC01 000		
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F14=Skills Matrix			
06-18	SA	MK	KS IM II KENB20A PET113S1

Fields:

Name

Enter the full name of the engineer.

Address Lines 1 to 5

Enter the engineer's address.

Geo Code (2 Fields)

Identify the first and second part of the engineer's home location code using up to five alphanumeric for both parts of the code.



Tip: The engineer's geocode is for information only. The engineer's team, with its link to a territory or patch, is used in engineer allocation, not the geocode.

Post Code (2 Fields)

Enter the first and second parts of the engineer's postcode, if required. The format should comply with Post Office regulations, but the field is not validated.

Telephone

Enter the engineer's contact telephone number.

Ext

Enter a telephone extension number for the engineer, if one exists.

Radio Page Code

If the remote communications link is active, this field must hold the engineer's designated terminal code.

Supply Stockroom



Note: This field is only displayed if the DRP libraries have been included in the Service Management library list.

Enter an existing supply stockroom which has been set up in Inventory Management (company profile) with item/stockroom details.

The stockroom is the source of spare parts for replenishing the engineer's stock location. It is the default supply stockroom for the engineer used in DRP parts orders which are originated during technical reporting.

Stock Location

Enter a stockroom.

Define the engineer's stock location in Inventory company profile and with item/stockroom details; set up physical stocks.

Where DRP orders are to be used, set up a valid Accounts Receivable account with delivery code 001. In DRP maintenance, attach the account to the stock location as the sole customer for all Distribution orders to the location.

In service job technical reporting, parts used by the engineer are debited to this stock location code.

Team Code

Enter the team for the engineer. Teams are used in engineer allocation, if the Assign By Territory field is set on in the company profile (screen 1 of 4).

Vehicle Reg No

Enter the registration number of the engineer's vehicle.

Absent Code

If this field holds anything other than blank, 0 or 1, automatic allocation will ignore this engineer for calls.

There are two uses for this field:

1. When you create a non-job activity in the engineer's diary, you can give it an absent code, and that code will appear here, and ensure that the engineer is not allocated work.

The field needs to be reset manually; the system will not remove the absent code.

Absent codes are set up under parameter type ABSC in the Codes/Parameter File option.

2. If you are using remote communications, then this field remains blank until the engineer logs on. Once logged on, the system enters 1 in this field, and the Radio Page field holds the engineer's reference.

Manager's Code

Enter the manager's code if required (it could be the manager's initials).

Grading Code

Identify the grade of the engineer if required, this must be valid on the codes file under code type EGRD.

Cost Per Hour

The hourly rate to be charged to the job cost database, for work done and travel time expended by the engineer. The value is expressed in base currency.

Region

Identify the service region in which the engineer works. This must be valid on the codes file under code type REGN.

Workshop Engineer

Enter one of the following:

0 - Either the contract or non-contract rate from the price list will be used depending on the job.

1 - The workshop rate from the labour rate price list will be used when charging for an engineer's time.

Include Engineer In Auto Call Assignment

Enter one of the following:

0 - The engineer will be excluded from auto call assignment.

1 - The engineer will be included in automatic call assignment (ACA) for his team; the absent code must also be blank.

You can also limit ACA operation using settings on system parameters, model and job category files.

Engineer Account

Enter the account number for the engineer, which has been set up and is validated in Accounts Receivable.

The account number is used as the customer for non-job activities, set up for the engineer using the diary function.

Untitled

Enter the address code, with the account number for the engineer, which has been set up and is validated in Accounts Receivable.

The account and address codes are used as the customer for non-job activities, set up for the engineer using the diary function.

Functions:

F14

Skills Matrix. Select this to maintain the engineer skills matrix.

F16

Alternate Engineer Maintenance. Display screen to maintain alternative engineers (if the Assign By Territory Or Alternative Engineer field on Company Profile Maintenance screen 1 is set to 0).



Select **F8=Update** to save any changes you have made.

Engineer Maintenance Skills Matrix (F14)



To display this screen select **F14=Skills Matrix** on the Engineer Maintenance screen.

SS045	Demonstration Company	BRERETM	22/11/93
	CENTRAL BRANCH		12:30:03
Engineer Maintenance			
Engineer.....	E0001	JOHN SMITH	
Model	Division	Model Group	Model Subgroup Job Cat
_____	10	_____	_____
	Environmental	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
			+
F3=Exit F4=Prompt F8=Update F12=Previous F13=Fold/Truncate			

Fields:

Model

Enter the models on which the engineer has been trained. If the engineer has been trained on all the models in the model sub-group, this entry is not necessary.

Division

Enter the division for the engineer. This implies the engineer is trained on all products within the division if no further qualification is entered, (that is, for model group, model sub-group, model or job category).

Model Group

Enter the model group for the engineer. This implies the engineer is trained on all products within the model group if no further qualification is entered, (that is, for model sub-group, model or job category).

Model Sub-Group

Enter the model sub-group for the engineer. This implies the engineer is trained on all products within the model sub-group if no further qualification is entered, (that is, for model or job category).

Job Cat

Enter the job category for which the engineer has been trained. This will restrict the selection of the engineer to the jobs within the division, model group, model sub-group or models which are defined with the job category.

Leave this field blank if the engineer is skilled to do all.

Functions:

F13

Fold/Truncate for further details.



Select **F8=Update** to save any changes you have made.

Alternative Engineer Maintenance Screen (F16)



To display this screen select **F16=Alternate Engineer Maint** on the Engineer Maintenance screen.



Note: This screen is only available if you have set the Assign By Territory Or Alternative Engineer field on Company Profile Maintenance screen 1 to 0.

Use this screen to enter all the engineers who can be considered as alternatives to the selected engineer.

Fields:

Opt

Enter 4 against an engineer to delete it as an alternative to the selected engineer. This does not delete the engineer's details from the system.

Engineer

Enter the engineer you want to set up as an alternative to the selected engineer, then press **Enter** to see the engineer appear in the list towards the top of the screen.

Functions:

F9

Next. This takes you back to the Engineer Maintenance Selection screen.



When you have included all the engineers you want to set up as alternatives, select **F12=Previous** to return to the Engineer Maintenance screen.

Geocode/Territory Maintenance

1... **2...** 2/SSM

Use this option to define the geographical territories for service operations, by means of full or partial geographical or postal codes.

A service territory is a geographical area, defined as a number of full or partial postcodes. They are used to automatically assign an engineer team to a service job. The customer geocode is used to establish the territory in which the installation falls, and the most suitable engineer covering this territory will then be selected.

A geocode cannot exist in more than one territory, but a territory can be assigned to more than one team.

All the geocodes which fall within a territory are entered. These can be full (for example, district plus area plus road), or partial (district only, or district plus area) geocodes depending on how precisely the territory needs to be defined (and how far the format of the local postcode allows this definition).

Geocode/Territory Maintenance Initial Screen



Select Geocode/Territory.

SS064	Demonstration Company CENTRAL BRANCH	BRERETM	22/11/93 12:31:26
Geocode/Territory Maintenance			
Territory..?. ?__			
F3=Exit F4=Prompt			

Fields:

Territory

Enter a new or existing territory.



Press **Enter** to display the Geocode/Territory Maintenance screen.

Geocode/Territory Maintenance Screen



To display this screen select the territory on the Geocode/Territory Maintenance Initial screen and press **Enter**.

SS064

Demonstration Company
CENTRAL BRANCH

BRERETM

14/02/94
10:09:22

Geocode/Territory Maintenance

Territory.... T01 Territory 1

Geocode	Geocode	Geocode	Geocode
CT1			

F3=Exit F8=Update F12=Previous

Fields:

Territory Description

Enter a territory description.

Geocode

Enter the geographic code (usually the postcode) to be included for selecting this territory.



Enter all the geocodes in this territory, and select **F8=Update** to save any changes.

Job Category Maintenance

1... **2...** 4/SSM

Use this option to define and maintain all your job categories.

A job category code defines the type of call (for example, service visit, return call - fit part), or the type of activity carried out in the process of repairing or maintaining equipment.

Together with the contract type, it is used as the basis for deciding if the task is chargeable. The details of whether to charge, and if so how much, or not to charge, are set up in the cover type/job category charge matrix.

Implications

Job categories are used to log jobs and to create planned maintenance schedules for contracts. They are also required for the entry of engineer technical reports.

The information associated with a job category is used:

- To determine the default values for nine frequently used job categories, which will be used at call logging.
- In conjunction with contract type data, to make up the charge matrix which determines if cost elements in a call are chargeable or not: this concerns labour hours, mileage charges, travel hours, miscellaneous costs and parts used, by four, user defined types (for example, major, minor, consumables and supply items).

Job Category Maintenance Selection Screen



Select Job Category Maintenance

Fields:

Job Category

Enter the job category you wish to set up or maintain.



Press **Enter**, to display the Job Category Maintenance screen.

Job Category Maintenance Screen



To display this screen enter a new or existing job category on the Job Category Maintenance Selection screen and press **Enter**.

SS031	Demonstration Company	USER BRERETM	14/02/94
	CENTRAL BRANCH		11:47:09
Job Category Maintenance		UPDATE	
Job Category.....	CSR	<u>Customer Service Request</u>	
Category Type.....	1	(1-Breakdown 2-Planned 3-Non Job 4-Other)	
Default category.....	I	(0 Not a default)	
		(1 Breakdown category default)	
		(2 Installation category default)	
		(3 Withdrawal category default)	
		(4 Return job category default)	
		(5 Repeat call default)	
		(6 Specialist call default)	
		(7 Return for Knowledge)	
		(8 Return for Other Reasons)	
		(9 Warranty Call)	
Include category in repeat call calculation....		1	(0/1)
Include category in automatic call assignment..		I	(0/1)
Average hours factor....		_____	
F3=Exit		F11=Delete F12=Previous	

Fields:

Description

Enter the description for the job category.

Category Type

Enter one of the following:

- 1 - Breakdown.
- 2 - Planned.
- 3 - Non-job.
- 4 - Other.

Default Category

Each category type should have a default job category, which can be retrieved automatically at call logging and displayed on the call logging screen. You can define one default job category for each type.

Enter a single numeric, in the range 1 to 9, if this job category is the default for a particular type.

If it is not, enter 0.

Include Category In Repeat Call Calculation

Enter one of the following:

0 - This job category is to be excluded from the repeat call calculation.

1 - This job category is to be included in the repeat call calculation.

Repeat calls are checked at call logging. They depend on the number of days, and/or the copies/vends produced since the last technically reported service call to the equipment.

Days and copies between calls are defined on the volume segment, which is linked directly to a specific model.

Include Category In Automatic Call Assignment

Enter one of the following:

0 - Calls of this job category are to be excluded from the automatic call assignment (ACA) of engineers to calls within their team.

1 - Calls of this job category are to be included in the automatic call assignment (ACA) of engineers to calls within their team.

ACA operation may also be limited by settings in the System Parameters File Maintenance option, and by settings for the model and engineer.

Average Hours Factor

This field is for future development.



Press **Enter**, then **F8=Update** to update.

Cover Type/Job Category Maintenance



5/SSM

It is important to understand the difference between the contract type and the cover type:

Contract type defines the billing charges and meterage pricing and control to be applied to the contract.

Cover type defines the equipment price to be charged for an item of equipment in contract pricing and the charge matrix to be used in job pricing.

Use this option to define and maintain a charge matrix for all job categories. The charge matrix specifies the invoicing rules relating to each combination of job category and cover type; it determines which elements are chargeable, whether overrides apply and which elements are not chargeable.

Concepts

You must set up a list of all the job categories which are valid for each cover type (including *NO - no contract). The list ensures that invalid types of work are not booked against a contract; and tells the system whether the labour, travel and/or parts and/or miscellaneous costs are to be charged to the customer.

Implications

The matrix of cover types/job categories must be defined before an engineer can be despatched to a call, or technical reports can be logged. Entries of labour and travel hours, parts used and miscellaneous costs can only be made against job categories which are set up in a matrix with the cover type covering the piece of equipment on the technical report.



*Note: A set of job categories valid for non-contract work must be defined against the special cover type code *NO, to allow technical report entries for non-contract work.*

The matrix is also important for the job invoicing routines. As each completed job line is processed, the indicators held for the appropriate cover type/job category combination are accessed, to decide whether labour hours, miscellaneous costs and parts used are to be charged to the customer.



Note: If a valid contract type/job category charge matrix does not exist when a job is logged, a warning message is displayed on the job line details screen. The call can still be logged, but the error condition should be corrected before attempting to process the technical report.

Cover Type/Job Category Maintenance Initial Screen



Select Cover Type/Job Category.

```

SS033          Z1 - GB Demonstration Company   USER GBJBATD0   24/09/97
              "BRAUM" TRAINING & SERVICE BRANCH 15:23:33
Cover Type/Job Category Maint.

Cover Type .....?..  *NO
Currency Code.....?..  GBP

Based on:-

Cover Type .....?..  █
Currency Code.....?..  █

F3=Exit  F4=Prompt

14-25  SR  MW  KS  CL  IM  DM  II  EDN400A  KB  PKH317S1
  
```

Fields:

Contract Type

Enter a new or existing contract type.

Currency Code

Enter an existing currency using three characters.

Based On Contract Type

To base a new matrix on an existing one, enter the existing contract type.

Based On Currency Code

To base a new matrix on an existing one, enter the existing currency code.

You will need to revise all fixed charge overrides for labour and travel if a different currency is involved.



Press **Enter** to display the Cover Type/Job
Category Maintenance Detail screen.

Cover Type/Job Category Maintenance Detail Screen



To display this screen press **Enter** on the Cover Type/Job Category Initial screen.

This lists all job categories linked to the cover type. The line of input fields (the invoice fields) above the list of job categories is where the actual set up or maintenance takes place.

To enter a new line, enter a job category in the Job Category field, and enter 1 in the appropriate invoice fields.

To amend an existing line, enter 1 against the relevant line in the job category list. The category you have chosen will appear in the Job Category field, and all the invoice fields appear in the input fields for amendment.



Tip: Where invoice field values are highlighted, that means there is a fixed charge attached.

```

SS033          Z1 - GB Demonstration Company      USER GBJBATD0  24/09/97
               "BRUM" TRAINING & SERVICE BRANCH
Cover Type/Job Category Maint. (Detail)           15:24:33

Cover Type ..... *NO No user contract
Currency Code..... GBP
Job Category..... CAL Calibration
Invoice? Labour   Mileage Travel Misc. Major      Minor      Consume      Supplies
(1/0)            1       1       1       1         1         1         1         1

Job Category..... LBR MLG TRV MSC MAJ MIN CON SUP
- AAI Annual Ammunition Inspection      1       1       1       1       0       0       1       0
1 CAL Calibration                      1       1       1       1       1       1       1       1
- CID Customer Inflicted Damage        1       1       1       1       1       1       1       1
- CSR Customer Service Request          1       1       1       1       1       1       1       1
- FOC Free-Of-Charge Call               0       0       0       0       0       0       0       0
- INS Installation                     1       1       1       1       1       1       1       1
- PCV Pending Contract Visit            0       0       0       1       0       0       1       0
- RCC Repeat call - chargeable          1       1       1       1       1       1       1       1
- RCN Repeat Call - No Charge           0       0       0       1       0       0       1       1
- RTN Return Call : Standard            1       0       0       1       1       1       1       1
                                         +

F12=Previous F14=Pos.Cur. Changing Overrides F16=Changing Overrides

-----
9-13  SA  MW  KS  CL  IM  DM  II  EDN400A  KB  PKH317S1
  
```

Fields:

Job Category

To add a new charge matrix for a cover type/job category combination, enter a valid job category.



Warning: Do not enter a valid job category here and immediately select an existing job category by entering 1 in an option field. This will result in an unnecessary record-locking of the first job category.

Labour

Enter one of the following:

0 - The labour hours will not be invoiced; no fixed charge will apply.

1 - The labour hours will be invoiced. Fixed charge overrides may be set up by **F14=Pos.Cur. Charging Overrides** or **F16=Charging Overrides**; be sure to page through the charge window, as the latest price is on the last page.

If a copy, based on another currency, has been made, the override charges must be converted to the appropriate value for the different currency.

Mileage

Enter one of the following:

0 - Mileage is not to be charged.

1 - Miles or kilometres are to be charged; there are no fixed charge overrides on distance travelled.

The appropriate value will be displayed on the technical report screen, where it may be changed.

Travel

Enter one of the following:

0 - Travel hours will not be invoiced. No fixed charge will apply.

1 - Travel hours will be invoiced, you can set up fixed charge overrides using **F14=Pos.Cur. Charging Overrides** or **F16=Charging Overrides**. Make sure to page through the charge window, as the latest price is on the last page.

The appropriate value will be displayed on the technical report screen, where it may be changed.

If a copy, based on another currency, has been made, the override charges must be converted to the appropriate value for the different currency.

Misc

Enter one of the following:

0 - Miscellaneous charges are not to be invoiced.

1 - Miscellaneous charges are to be invoiced; there are no fixed charge overrides on miscellaneous charges.

The appropriate value will be displayed on the technical report screen, where it may be changed.

Major

Enter one of the following:

0 - The parts used will not be invoiced, unless an override charge % is keyed in technical reporting - parts used.

1 - Major parts will be invoiced. If you want to specify which parts are to be charged, use **F14=Pos.Cur. Charging Overrides** or **F16=Charging Overrides**.

You specify which of the four types that you want to charge for, and in what order here. You can specify this information for each individual piece of equipment on each individual contract.

These types are selected from the Item Types to be Invoiced details you specified in System Parameters Maintenance (screen 3 of 5).

The Item Type codes are initially defined in Inventory Management's Description Maintenance.

Minor

Enter one of the following:

0 - The parts used will not be invoiced, unless an override charge % is keyed in technical reporting - parts used.

1 - Minor parts will be invoiced. If you want to specify which parts are to be charged, use **F14=Pos.Cur. Charging Overrides** or **F16=Charging Overrides**.

You specify which of the four types that you want to charge for, and in what order here. You can specify this information for each individual piece of equipment on each individual contract.

These types are selected from the Item Types to be Invoiced details you specified in System Parameters Maintenance (screen 3 of 5).

The Item Type codes are initially defined in Inventory Management's Description Maintenance.

Consume

Enter one of the following:

0 - The parts used will not be invoiced, unless an override charge % is keyed in Technical Reporting - Parts Used.

1 - Consumable parts will be invoiced. If you want to specify which parts are to be charged, use **F14=Pos.Cur. Charging Overrides** or **F16=Charging Overrides**.

You specify which of the four types that you want to charge for, and in what order here. You can specify this information for each individual piece of equipment on each individual contract.

These types are selected from the Item Types to be Invoiced details you specified in System Parameters Maintenance (screen 3 of 5).

The Item Type codes are initially defined in Inventory Management's Description Maintenance.

Supplies

Enter one of the following:

0 - The parts used will not be invoiced, unless an override charge % is keyed in Technical Reporting - Parts Used.

1 - Supply parts will be invoiced. If you want to specify which parts are to be charged, use **F14=Pos.Cur. Charging Overrides** or **F16=Charging Overrides**.

You specify which of the four types that you want to charge for, and in what order here. You can specify this information for each individual piece of equipment on each individual contract.

These types are selected from the Item Types to be Invoiced details you specified in System Parameters Maintenance (screen 3 of 5).

The Item Type codes are initially defined in Inventory Management's Description Maintenance.

Unnamed (Option)

Enter one of the following:

1 - Select a job category for maintenance. There is no need to press **Enter**, as the job category charge details are displayed for amendment automatically.

4 - Select a category for deletion from this matrix.

Or leave the field blank.

Functions:

F14

Position Cursor: Charging Overrides. This displays a special override entry window for the item on which the cursor has been positioned.

F16

Charging Overrides. This displays the same windows as **F14=Position Cursor Charging Overrides**, but it displays each in turn, so you can enter overrides for labour, travel, major, minor, consume and supplies.

Charging Overrides Window (F14/F16)



To display this window select **F14=Position
Cursor Charging Overrides** or **F16=Charging
Overrides**

These vary depending on the charge being
overridden, so a selection of the fields below
will be shown.

SS033		Z1 - GB Demonstration Company		USER GBJBATD0		24/09/97	
		"BRUM" TRAINING & SERVICE BRANCH				15:26:04	
Cover Type/Job Category Maint. (Detail)							
Cover Type		*NO No user contract					
Currency Code.....		GBP					
Job Category.....		CAL Calibration					
Invoice? Labour		Mileage	Travel	Misc.	Major	Minor	Consume
(1/0)		1	1	1	1	1	1
Job Category.....		LBR	MLG	TRV	MSC	MAJ	MIN
- AAI Annual Ammunition Inspection		1	1	1	1	0	0
1 CAL Calibration							
- CID Customer Inflicted Damage							
- CSR Customer Service Request							
- FOC Free-Of-Charge Call							
- INS Installation							
- PCV Pending Contract Visit							
- RCC Repeat call - chargeable							
- RCN Repeat Call - No Charge							
- RTN Return Call : Standard							
F12=Previous		F14=Pos.Cur. Changi		F7=Accept F12=Previous			

LABOUR HOURS FIXED CHARGES

The first		
'n' Hours	for a Min. Charge	Eff.Date
1:00	100.00	1/05/96

0:00

21-40 SA MW KS CL IM DM II EDN400A KB PKH317S1

Fields:

The First N Hours

Enter the number of hours this charge is to apply for.

For A Min Charge

Enter the value to be charged.

Eff Date

Enter the date from which this charge is to be made.

Select Parts To Include

Enter one of the following:

0 - You do not want to bring up a list of parts and select those to be overridden.

1 - You want to display a list of parts and select those to be overridden.

Select Parts To Exclude

Enter one of the following:

0 - You do not want to bring up a list of parts and select those to be excluded from the override.

1 - You want to display a list of parts and select those to be excluded from the override.

Select All Parts

Enter one of the following:

0 - You do not want to select all parts for the override.

1 - You want to select all parts for the override.



Select **F7=Accept** to update.

Tax Codes Maintenance

1... **2...** 6/SSM

You can allocate different VAT/sales tax codes to elements, excluding parts, in the charge matrix and for the various countries involved.

Concepts

You can set specific VAT/sales tax codes for four of the elements in the contract type/job category charge matrix. These override the customer account and site settings of the VAT indicator and the VAT code fields, which would otherwise apply.

You can set up different tax codes for different countries.

Description

To set up the tax codes, specify a contract type and country. You can set up default values for the tax codes to apply to travel labour, chargeable travel, labour hours and miscellaneous charges.

The system applies these settings to all job category records for the contract type and country. Individual codes can be changed, if necessary. Alternatively, all the tax codes can be set up individually for a country.

Contract Type/Job Category Tax Code Maintenance Initial Screen



Select Tax Codes Maintenance.

```

SS985          Z1 - GB DEMO. SERVICE COMPANY      USER GBJBABL  6/03/96
                  "BRUM" TRAINING & SERVICE BRANCH      10:42:35
Contr.Type/Job Category Tax Code Maintenance

Contract Type.....?. BOS
Country Code.....?. GB

Default Tax Codes
Travel.....?. ____
Miles/Kilometres....?. ____
Labour.....?. ____
Miscellaneous.....?. ____

F3=Exit  F4=Prompt

07-30  SF  MW  KS  IM  II  KENB20A  PED129S1
  
```

Fields:

Contract Type

Enter contract type using a three character code which are held on the contract type file.

Country Code

Enter a country code using a three character code which are held on the world trade country file.

Default Tax Codes

Select the typical tax code for each element. The system will automatically apply this to the various matrices. The few exceptions can then be edited manually.

These values do not override any existing ones on the next screen. They are only used to set up new codes.

Travel

Enter a travel code using a three character code. These codes are held on the General Ledger VAT codes file, to be applied to travel labour.

Miles/Kilometres

Enter a three character code. These codes are General Ledger VAT codes to be applied to miles/kilometres.

Labour

Enter a three character code. These codes are General Ledger VAT codes to be applied to labour.

Miscellaneous

Enter a three character code. These codes are tax codes to be applied to any miscellaneous charges.



Press **Enter** to display the Contract Type/Job
Category Tax Code Maintenance Detail screen.

Contract Type/Job Category Tax Code Maintenance Detail Screen



To display this screen press **Enter** on the Contract Type/Job Category Tax Code Maintenance Initial screen.

```

SS985          Z1 - GB DEMO. SERVICE COMPANY      USER GBJBABL  6/03/96
               "BRUM" TRAINING & SERVICE BRANCH    10:43:02
Contr.Type/Job Category Tax Code Maintenance - UPDATE

Contract Type..... B05 S&V Adv
Country Code..... GB United Kingdom
Job Category.....?  █

VAT Code.....?  █

1 Job Category      Trv   M1/   Lbr   Msc
- AAI Annual Ammunition Inspection  001  001  001  001
- CAL Calibration                001  001  001  001
- CSR Customer Service Request    001  001  001  001
- PMA Schedule "A" : Planned Maint. 001  001  001  001
- PMB Schedule "B" : Planned Maint. 001  001  001  001
- PMC Schedule "C" : Planned Maint. 001  001  001  001
- PSV Planned service visit        001  001  001  001
- SBI Statutory Boiler Inspection   001  001  001  001
- SLG Statutory Lifting Gear Insp'n. 001  001  001  001
- 406 AF406 Equipment Inspection   001  001  001  001
1=Select  4=Delete
F3=Exit  F4=Prompt  F8=Update  F12=Previous

07-28  █ MW KS IM II KENB20A PED129S1
  
```

Fields:

Job Category

Enter a job category code of up to three alphanumerics.

Trv, M1/Km, Lbr, Msc

Enter four VAT/sales tax codes of up to three alphanumerics for travel, mileage or kilometers, labour and miscellaneous charges.

The system allocates any default codes entered on the Initial screen to the four elements in all the matrices for the contract type. You can then edit any code to which the default value should not apply.

1

Select. Must be blank, 1 or 4.

1 - To update an existing code.

4 - To delete an existing code.



Select **F8=Update** to save any changes made.

District File Maintenance



7/SSM

Use this option to authorise groups of teams to a user, for the purpose of work control.

Most users can log a call, but only users which are authorised to control specific teams can progress calls through Engineer Work Allocation.

District File Maintenance Initial Screen



Select the District File Maintenance.

SS057	Demonstration Company CENTRAL BRANCH	USER BRERETM	22/11/93 12:33:09
District Maintenance			
District Number....?... <u>D1</u>			
F3=Exit F4=Prompt			

Fields:

District Number

Enter a new or existing district of up to two alphanumerics.



Press **Enter** to display the District File Maintenance Detail screen.

Team File Maintenance

1... 8/SSM **2...**

Use this option to assign to an engineer team the service territories it is to cover, by field service group (that is, by the skills required for servicing equipment within the specified division, model group, model sub-group, or model).

Concepts

A team is a group of engineers who cover the same geographical area and product set. Effectively a pool of labour to meet the call target time, allowing an available member of the team to be automatically assigned to a task.

If you want a team to carry out service jobs in more than one territory, then assign it to a list of the appropriate territories. A team can cover all types of work in a territory, or only specific model groups, sub-groups, and/or divisions, or a combination of these, according to the field service groups which are defined.

Team Maintenance Initial Screen



Select the Team Maintenance.

SS058	Demonstration Company	USER BRERETM	22/11/93
	CENTRAL BRANCH		12:35:14
Team Maintenance			
Team Number.....?.. <u>TM1</u>			
F3=Exit F4=Prompt			

Fields:

Team Number

Enter a new or existing team.



Press **Enter** to display the Team Maintenance
Detail screen.

Team Maintenance Detail Screen



To display this screen press **Enter** on the Team Maintenance Initial screen.

SS058	Demonstration Company CENTRAL BRANCH	BRERETM	22/11/93 12:35:16
Team Maintenance		UPDATE	
Team Number.....	TM1 Team 1		
Field Service Group ...?..	—		
Territory.....?..	—		
Job Category.....?..	—		
X Field Service Group	Territory	Job Category	
_ G1 Group 1	T01 Territory 1	** ALL CATEGORIES **	
4-Delete			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			

Fields:

Untitled

Enter a team description of up to 30 alphanumerics.

Field Service Group

Enter a field service group code of up to two alphanumerics.

Territory

Enter a valid territory code of up to three alphanumerics. You can only allocate a field service group and territory code combination to one team.

Job Category

Enter a job category. If the field is left blank, all job categories will be set up for the selected combination of field service group and territory.

X

Enter 4 to delete a line



Select **F8=Update** to update.

Field Service Group Maintenance



9/SSM

A field service group defines the responsibilities of a team of engineers with regard to the service division and the model families.

Implications

The engineer team and territory definitions are used when the system tries to assign an engineer from a team to a service job automatically.

The customer geocode establishes the territory in which the installation falls; the most lightly loaded engineer covering this territory and field service group will then be selected.

Field Service Group Maintenance Initial Screen



Select Field Service Group Maintenance.

SS059	Demonstration Company	USER BRERETM	22/11/93
	CENTRAL BRANCH		12:35:46
Field Service Group Maint.			
Field Service Group...?... <u>G1</u>			
F3=Exit F4=Prompt			

Fields:

Field Service Group

Enter a new or existing field service group.



The Field Service Group Maintenance Detail screen is automatically displayed.

Field Service Group Maintenance Detail Screen



This screen is displayed when you enter a field service group on the Field Service Group Maintenance Initial screen.

SS059	Demonstration Company CENTRAL BRANCH	BRERETM	22/11/93 12:35:49
Field Service Group Maint.		UPDATE	
Field Service Group..... G1 Group 1			
Model	Division	Model Group	Model Subgroup
_____	10 Environmental	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F13=Fold/Truncate			

Fields:

Unnamed

Enter the field service group description, in up to 36 alphanumeric.

Model

Enter the specific models to which the skills of the field service group are restricted.

You do not need to enter a model if the field service group is competent to service all the models in the model sub-group.

If you enter a model code you must enter a division code, but you do not need to enter model group and model sub-group codes.

Division

Enter the product division(s) covered by the field service group. This implies that the field service group is competent to service all products within the division if no further qualification is entered (that is, for model group, model sub-group or model).

Model Group

Enter the specific model group(s), within a division, which is covered by the field service group. Leave blank if all model groups in the division are covered.

This implies that the field service group is competent to service all products within the model group if no further qualification is entered (that is, for model sub-group or model).

Model Sub-Group

Enter the specific model sub-group(s) within a model group, which are covered by the field service group. Leave blank if all model sub-groups in the model group are covered.

This implies that the field service group is competent to service all products within the model sub-group if no further qualification is entered at model level.

Functions:

F13

Fold/Truncate to display more details.

3-D Matrix Maintenance

1... **2...** 10/SSM

The 3-D matrix allows the response time, retrieved from the contract header, line, or type, to be reduced by a percentage.

This depends on:

- The importance of the customer placing the call.
- The volume segment set at model level.
- The seriousness of the problem (that is, the machine is up and working, but in need of attention, or is down and completely out of action).

Description

When you select the 3-D Matrix option you see a list of the volume segments for which a percentage reduction in response time has been defined by customer importance, and whether the machine is up (that is, working, but in need of attention), or down (that is, out of action).

3-D Matrix Maintenance Detail Screen



Select 3-D Matrix Maintenance.

SS055		Demonstration Company CENTRAL BRANCH				USER BRERETM		25/11/93 15:42:50	
3-D Matrix Maintenance		PRIORITY 1 MACHINE		PRIORITY 2 MACHINE		PRIORITY 3 MACHINE		PRIORITY 4 MACHINE	
Vol Seg		UP	DOWN	UP	DOWN	UP	DOWN	UP	DOWN
10		1	2	2	3	3	4	4	5
20		2	3	3	4	4	5	5	6
30		3	4	4	5	5	6	6	7
99		5	10	10	15	15	20	20	25
F3=Exit F8=Update									

Fields:

Vol Seg

All codes set up on the volume segment file are displayed.

Machine Up: Priorities 1 to 4

Enter the percentage reduction to be made to the response time for this volume segment. The valid entries are 0 to 100, with no decimals.

If the Machine up and running and the parameter on the Call Logging Job Line Detail screen is set to Yes (the default value), the percentage reduction entered for the volume segment (defined to the model) and the customer priority (defined in the site's additional service details) is applied to the appropriate response hours, to set the target time for the call.

The Response Time hierarchy looks for the response hours in:

1. The special serial numbers file. If it finds a response time here it does not apply the 3-D matrix reduction.
2. It then looks at the contract line.
3. It then looks at the contract header.
4. It then looks at the contract type (incl *NO).
5. It then looks at the default branch response time, set on the escalation control file.

The system takes the first of these five that it finds and applies the 3-D matrix reduction (but not if 1. is taken), to establish the call response.

Call target time=(call rec'd date/time + call response)

Machine Down: Priorities 1 to 4

Enter the percentage reduction to be made to the response time for this volume segment. The valid entries are 0 to 100, with no decimals.

If the Machine Up field on the second Job Line Detail screen is set off (that is, the machine is down and not running), the percentage reduction entered for the volume segment (defined to the model) and the customer priority (defined in the site's additional service details) is applied to the appropriate response hours, to set the target time for the call.

The response time hierarchy looks for the response hours in:

1. The special serial numbers file. If it finds a response time here it does not apply the 3-D matrix reduction.
2. It then looks at the contract line.
3. It then looks at the contract header.
4. It then looks at the contract type (incl *NO).
5. It then looks at the default branch response time, set on the escalation control file.

The system takes the first of these five that it finds and applies the 3-D matrix reduction (but not if 1 is taken), to establish the call response.

Call target time=(call rec'd date/time + call response)



Select **F8=Update** to save any changes.

Special Serial Numbers Maintenance



11/SSM

Use this option to set up an actual response time in hours and minutes for a specified item of equipment. This will normally be used as an exception, to provide a short-term, special service to an item of equipment.



Tip: The response time you enter here is at the top of the response times hierarchy, and so will override any model, contract or other response times set up elsewhere.

Special Serial Numbers Maintenance Detail Screen



Select Special Serial Numbers, select a valid serial number and model combination, to display the detail screen.

SS054	Demonstration Company CENTRAL BRANCH	USER BRERETM	14/01/94 16:42:20
-------	---	--------------	----------------------

Special Serial Numbers Maint.

Serial Number.....	22581039	Model.....	WA10
Account Number.....	C03 / 001	Jones & Crossland (Northern) Ltd	
Response time	<u>4:00</u>		

F3=Exit F8=Update F12=Previous

Fields:

Response Time

Enter the response time in hours and minutes (hh:mm) to be applied to the model and serial number.

This response time will take priority when calculating the target time for a call to this machine.

The Response Time hierarchy looks for the response hours in:

1. The special serial numbers file. If it finds a response time here it does not apply the 3-D matrix reduction.
2. It then looks at the contract line.
3. It then looks at the contract header.
4. It then looks at the contract type (incl *NO).
5. It then looks at the default branch response time, set on the escalation control file.

The system goes through each in turn, and takes the first that it finds. The 3-D matrix reduction is applied to all but the special serial number response time to establish the call response.



Select **F8=Update** to update.

Engineer Master File Enquiry

1... 21/SSM
2...

To enquire on the details of engineers, on an ad hoc basis.

Engineer Enquiry Initial Screen



Select Engineer File Enquiry.

SS545	Demonstration Company CENTRAL BRANCH	USER BRERETM	25/11/93 14:48:33
Engineer Enquiry			
Engineer.....?..		<u>E0001</u>	
F3=Exit F4=Prompt			

Fields:

Engineer

Enter a engineer code as defined on the engineer master file.



Press **Enter** to display the Engineer Enquiry
Detail screen.

Engineer Enquiry Detail Screen



To display this screen press **Enter** on the Engineer Enquiry Initial screen.

```

SS545          61 - 61 - Demonstration Company   USER SSV3      11/12/95
                  CENTRAL BRANCH                  14:47:41

Engineer Enquiry

Engineer..... E0001
Name..... ARCHIE ABLETT
Address Line 1 32 ACACIA BOULEVARD
                2 GREENLANDS
                3 REDDITCH
                4 WORCS
                5
Telephone..... 01527 588665      Ext.      Radio Page Code...
Supply Stockroom.
Stock Location... 01              Team Code..... TM1   Team 1
Vehicle Reg.No...                Absent Code.....
Manager's Code...
Grading Code.... FE   Field engineer
Cost Per Hour....      25.00000      Region..... CT   Central
Workshop Engineer..... 0   (1=yes 0=no)
Include Engineer in automatic call assignment..... 1
Engineer Account. EAC01      000

F3=Exit   F12=Previous   F14=Skills Matrix

07-24      SP      MK      KS      IM      II   KENB20A   PET113S1
  
```

Fields:

Engineer Code

This is the engineer number from the previous screen.

Engineer Name

This is the engineer's full name.

Address Lines: 1 To 5

This is the engineer's address.

Geocode 1 And 2

The geocode is not used in Engineer Allocation.

Postcode 1 And 2

The postcode is not used in Engineer Allocation.

Telephone No.

The engineer's telephone number.

Telephone Extension No.

The engineer's telephone extension number, if applicable.

Radio Page Code

This is engineer's terminal code if the remote communications link is active.

Supply Stockroom

This is only displayed if the DRP libraries have been included in the Service Management library list. It is the source of spare parts, to replenish the engineer's spare parts location via DRP, ordered at technical reporting.

Stock Location

If the interface to the Inventory Management application is switched on, each engineer must be linked to a stock location which must be valid on the Inventory stockroom profile file.

Team Code/Description

Displays the team code to which the engineer has been defined. Team codes are used in Engineer Allocation, if Assign by Territory is set 1 on company profile maintenance (screen 1 of 4).

Vehicle Registration No.

This is the engineer's vehicle registration number if applicable.

Absent Code

This is the reason for the engineer being unavailable. If the field has a value other than blank, 0 or 1, Automatic Call Allocation will ignore the engineer for calls.

Manager's Code

This is the engineer's manager's code.

Grading Code

This identifies the grade of the engineer from the codes set up under parameter type EGRD on the codes/parameters file.

Cost Per Hour

This is the hourly rate, in base currency, to be charged to the job cost database, for work done and travel time expended by the engineer.

Service Region Code

This identifies the service region in which the engineer works.

Service Region Description

Displayed only, cannot be amended; interprets the code in the preceding field, by reference to codes/parameter file: REGN.

Workshop Engineer ?

This can be one of the following:

0 - When the charge for an engineer's time is being calculated, either the contract or non-contract rate from the Price List file will be used, depending upon the job.

1 - When the charge for an engineer's time is being calculated, the workshop rate from the labour rate price list file will be used.

Include Engineer In Automatic Call Assignment

1 - The engineer will be included in the Automatic Call Assignment program.

2 - The engineer will be excluded from the Automatic Call Assignment program.

Engineer Account/Locn codes

Displays the account which has been defined for the engineer on the sales ledger.

The account is used as the Customer for Non-Job Activities, set up by the diary function.

Functions:

F14

Skills matrix.To display the skills of the selected engineer.

F16

Alternative engineer (if parameter 8 on company profile screen 1 of 4 is set 0).

Engineer Enquiry Skills Matrix Screen (F14)



To display this screen select **F14=Skills Matrix** on the Engineer Detail screen. Select **F13=Fold/Truncate** to display the codes' descriptions.

Use this screen to view a skills record for the selected engineer.

SS545	Demonstration Company	BRERETM	25/11/93
	CENTRAL BRANCH		14:49:19
Engineer Enquiry			
Engineer.....	E0001	JOHN SMITH	
Model	Division	Model Group	Model Subgroup Job Cat
	10	100	
	Environmental	Analysers	
			+
F3=Exit F12=Previous F13=Fold/Truncate			

Fields:

Engineer Code

This is the engineer code selected on the Initial screen.

Engineer's Name

This is the engineer's name.

Model Code

These are model codes of equipment in which the engineer is skilled.

If the engineer has been trained on all the models in the model sub-group, this field will be blank.

Product Division Code

This is the product division code(s) of equipment in which the engineer is skilled.

This implies the engineer is trained on all products within the division, if no further qualification is entered for model group, model sub-group, model, or job category.

Model Group Code

This is the model group code(s) of equipment in which the engineer is skilled.

This implies the engineer is trained on all products within the model group, if no further qualification is entered for model sub-group, model, or job category.

Model Sub-Group Code

This is the model sub-group code(s) of equipment in which the engineer is skilled.

This implies the engineer is trained on all products within the model sub-group, if no further qualification is entered for model, or job category.

Job Category Code

This is the job category code for the particular product hierarchy set specified in the record, in which the engineer has been trained.

This will restrict the selection of the engineer to the jobs within the division, model group, model sub-group or models to this job category. A blank in the job category field indicates the engineer is skilled to carry out all job categories within the set specified in the record.

Functions:

F13

Fold/Truncate - for extra details.

Geocode/Territory Enquiry



22/SSM

Use this option to enquire on the geographical territories defined for service operations.

Description

You define Geographical territories by grouping together one or more geographical codes (usually postcodes).

Geocode/Territory Enquiry Initial Screen



Select Geocode/Territory Enquiry option.

SS564	Demonstration Company CENTRAL BRANCH	BRERETM	25/11/93 14:50:25
Geocode/Territory Enquiry			
Territory...?... <u>T01</u>			
F3=Exit F4=Prompt			

Fields:

Territory code

Enter a valid territory code.



Press **Enter** to display the Geocode/Territory Enquiry Detail screen.

Job Category Enquiry



24/SSM

Use this option to enquire on job category codes and associated data, on an ad hoc basis.

Job Category Enquiry Initial Screen



Select Job Category Enquiry.

SS531	Demonstration Company	USER BRERETM	25/11/93
	CENTRAL BRANCH		15:43:09
Job Category Enquiry			
Job Category..... <u>CSR</u>			
F3=Exit F4=Prompt			

Fields:

Job Category

Enter an existing job category code.

These codes are used in various parts of the application to define different types of service work to be undertaken, for example, in job maintenance, in scheduled service visit maintenance.

They are also used within the technical reporting module of the application to identify how the work undertaken is to be costed/charged.



Press **Enter** to display the Job Category Enquiry Detail screen.

Job Category Enquiry Detail Screen



To display this screen select a job category on the Job Category Enquiry Initial screen and press **Enter**.

SS531	Demonstration Company CENTRAL BRANCH	USER BRERETM	18/01/94 10:59:49
Job Category Enquiry			
Job Category..... CSR Customer Service Request			
Category Type.....: 1	(1-Breakdown 2-Planned 3-Non Job 4-Other)		
Default category.....: 1	(0 Not a default)		
	(1 Breakdown category default)		
	(2 Installation category default)		
	(3 Withdrawal category default)		
	(4 Return job category default)		
	(5 Repeat call default)		
	(6 Specialist call default)		
	(7 Return on knowledge)		
	(8 Return for other reasons)		
	(9 Warranty Call)		
Include category in repeat call calculation..... 1			
Include category in automatic call assignment... 1			
Average hours factor			
F3=Exit F12=Previous			

Fields:

Job Category Code

This is the category you entered on the initial screen.

Job Category Description

This is the description of the job category.

Category Type

Displays the job category type (that is, breakdown, planned, non-job or other).

Default Category

If this is the default job category for a particular type of call, the type of call is indicated as follows:

- 0 - Not a default.
- 1 - Breakdown.
- 2 - Installation.
- 3 - Withdrawal.
- 4 - Return job.
- 5 - Repeat call.
- 6 - Specialist call.
- 7 - Return, for knowledge.

8 - Return, other reasons.

9 - Warranty.

Include In Repeat Call Calculation

Indicates if the category will be included in the repeat call calculation: 1 - Yes, or 0 - No.

Include In Auto Call Assignment

Indicates if the category will be included in Automatic Call Assignment: 1 - Yes, or 0 - No.

Average Hours Factor

This is the average number of hours which a job for this job category will take to complete. The value is used in the calculation of engineer work points. The field is not supported in the current system.

Cover Type/Job Category Enquiry

1... 25/SSM
2...

Use this option to enquire on the list of job category codes which are valid for a cover type within a currency, and the invoicing rules relating to each combination.

Cover Type/Job Category Enquiry Initial Screen



Select Cover Type/Job Category Enquiry.

SS533	Z1 - GB DEMO. SERVICE COMPANY	USER GBJBATD0	10/10/97
	"BRUM" TRAINING & SERVICE BRANCH		16:17:57
Cover Type/Job Category Enq'y			
Cover Type.....?.. : *A			
Currency Code....?.. GBP			
F3=Exit F4=Prompt			
5-25	SA	MW	KS CL IM DM II STUD140 KB PKH317S1

Fields:

Cover Type

Enter a code of up to three alphanumerics.

Currency Code

Enter code of up to three alphanumerics.



Press **Enter** to display the Cover Type/Job Category Enquiry Detail screen.

Cover Type/Job Category Enquiry Detail Screen



To display this screen select a cover type on the Cover Type/Job Category Enquiry Initial screen and press **Enter**.

```

SS533          Z1 - GB DEMO. SERVICE COMPANY      USER GBJBATD0  10/10/97
                "BRUM" TRAINING & SERVICE BRANCH  16:18:19
Cover Type/Job Category Enq'y

Cover Type..... *A  Total Copier Cover
Currency Code..... GBP
Job Category.....
Invoice? Labour  Mileage  Travel  Misc.  Major      Minor      Consume  Supplies
(1/0)

Job Category.....      LBR  MLG  TRV  MSC  MAJ  MIN  CON  SUP
■ CAL Calibration      0    0    0    1    0    0    0    0
- CSR Customer Service Request  1    1    1    1    0    0    0    0
- PMA Schedule "A" : Planned Maint. 0    0    0    1    0    0    0    0
- PMB Schedule "B" : Planned Maint. 0    0    0    1    0    0    0    0
- PMC Schedule "C" : Planned Maint. 0    0    0    1    0    0    0    0
- WTY Warranty Call      0    0    0    1    0    0    0    0

1=Select
F3=Exit  F12=Previous

12-2  SA  MW  KS  CL  IM  DM  II  STUD140  KB  PKH317S1

```

Fields:

Job Category Code & Description

This is the job category and description for the record, selected from the table lower down the screen.

Invoice Labour

This will be one of the following:

0 - Labour hours are not chargeable for this cover type/job category combination.

1 - Labour hours are chargeable for this cover type/job category combination.

If the value is highlighted, special charges have been applied, which can be displayed using **F14=Pos.Cur. Charging Overrides** or **F16=Charging Overrides**.

Invoice Mileage

This will be one of the following:

0 - Mileage is not chargeable for this cover type/job category combination.

1 - Mileage is chargeable for this cover type/job category combination.

Invoice Travel

This will be one of the following:

0 - Travel hours are not chargeable for this cover type/job category combination.

1 - Travel hours are chargeable for this cover type/job category combination.

If the value is highlighted, special charges have been applied, which can be displayed using **F14=Pos.Cur. Charging Overrides** or **F16=Charging Overrides**.

Invoice Misc. Charges

This will be one of the following:

0 - Misc. charges are not chargeable for this cover type/job category combination.

1 - Misc. charges are chargeable for this cover type/job category combination.

Invoice Parts: 4 Types

This will be one of the following:

0 - Parts fitted are not chargeable for this cover type/job category combination.

1 - Parts fitted (up to four user defined groups) are chargeable for this cover type/job category combination.

If any values are highlighted, special conditions apply, which can be displayed using **F14=Pos.Cur. Charging Overrides** or **F16=Charging Overrides**. This will show whether all parts have been included for charging, or whether some of the parts in the group have been included in, or excluded from, invoice charging.



Note: The combination of cover Type and Job Category is used when the application prices completed jobs, to determine if Hours and/or

Parts and/or Miscellaneous Charges are to be invoiced.

Functions:

F14

Position Cursor. Charging Overrides. Displays a special entry window for the item on which the cursor has been positioned.

F16

Charging Overrides. Steps through those items which may have special overrides applied to them, displaying each item's options in turn.

Charging Overrides Enquiry Window (F16)

 To display this screen select a job category with 1, and select **F16=Charging Overrides** on the Cover Type/Job Category Enquiry Detail screen.

SS538

Z1 - GB DEMO. SERVICE COMPANY

USER GBJBATD0

10/10/97

"BRAUM" TRAINING & SERVICE BRANCH

16:18:40

Cover Type/Job Category Enq'y (Detail)

Cover Type..... *A

Total Copier Cover

Currency Code..... GBP

Calibration

Job Category..... CAL

Invoice? Labour Mileage Travel Misc. Major Minor Consume Supplies

(1/0)

Job Category....

1 CAL Calibration

- CSR Customer Ser

- PMA Schedule "A"

- PMB Schedule "B"

- PMC Schedule "C"

- WTY Warranty Cal

F12=Previous

F14=

Position to :

More : +

1 Item Number	Description
1 SN0008	Deck Chains : "Titanic" (Nearly New)
1 SN0009	Deck Chains : "Olympic" (Well Worn)
1 SN001	Piston Flange Plate 83mm
1 SN002	Air-Brake Pressure Release Lever
1 SN006	Ball-Cock Arm 26"
1 SN014	Anchor Chain 3.5" Link (Titanic)
1 SN025	Cable Harness - complete 12v 60a

*** ALL ***

11-37

SA

MW

KS

CL

IM

DM

II

STUD140

KB

PKH317S1

Fields:

Position To

Enter the code of the item you wish to view. The system displays the list of items starting at that code.

Tax Codes Enquiry



26/SSM

Use this option to enquire upon the tax codes which have been set up for a contract type/job category charge matrix within a specified country.

Contract Type/Job Category Tax Codes Enquiry Initial Screen



Select Tax Codes Enquiry.

SS986	Z1 - GB DEMO. SERVICE COMPANY	USER GBJBABL	6/03/96
	"BRUM" TRAINING & SERVICE BRANCH		10:53:12
Contr.Type/Job Category Tax Code Enquiry			
Contract Type.....?. <u>B05</u>			
Country Code.....?. <u>GB</u>			
F3=Exit F4=Prompt			
07-30		MW	KS IM II KENB20A PED129S1

Fields:

Contract Type

Enter contract type using a three character alphanumeric code.

Country Code

Enter country using a three character alphanumeric code from the World Trade country code file.



Press **Enter** to display the Contract Type/Job
Category Tax Codes Enquiry Detail screen.

Contract Type/Job Category Tax Codes Enquiry Detail Screen



To display this screen press **Enter** on the Contract Type/Job Category Tax Codes Enquiry Initial screen.

This screen displays a list of job categories and associated (travel, miles, labour and miscellaneous) tax codes for a selected contract type and country.

```

SS986          Z1 - GB DEMO. SERVICE COMPANY      USER GBJBABL  6/03/96
               "BRUM" TRAINING & SERVICE BRANCH    10:54:12
Contr.Type/Job Category Tax Code Enquiry

Contract Type..... B05 S&V Adv
Country Code..... GB United Kingdom

Job Category              TRV   MLG   LBR   MSC
AAI Annual Ammunition Inspection  001   001   001   001
CAL Calibration              001   001   001   001
CSR Customer Service Request    001   001   001   001
PMA Schedule "A" : Planned Maint. 001   001   001   001
PMB Schedule "B" : Planned Maint. 001   001   001   001
PMC Schedule "C" : Planned Maint. 001   001   001   001
PSV Planned service visit       001   001   001   001
SBI Statutory Boiler Inspection  001   001   001   001
SLG Statutory Lifting Gear Insp'n. 001   001   001   001
406 AF406 Equipment Inspection  001   001   001   001

F3=Exit  F12=Previous

07-30  S2  MW  KS  IM  II  KENB20A  PED129S1
  
```

Fields:

All Fields

These are the tax codes which apply to the job category charge matrix elements, set up for the selected contract type and country. They are used in job pricing and invoicing. They overwrite the account or site's VAT indicator and VAT code settings.

District File Enquiry



27/SSM

Use this option to enquire on the User IDs, authorised to teams, within a district.

You will not be able to access Engineer Work Allocation and progress any jobs if you are unauthorised.

District Enquiry Detail Screen



To display this screen, enter a District Code on the District Enquiry Initial Screen.

This screen displays users who have the authority to access teams in Engineer Work Allocation.

SS557

Demonstration Company
CENTRAL BRANCH

USER BRERETM

25/11/93
14:51:41

District Enquiry

District Number..... D1 District 1

Team	Description	User Id
TM1	Team 1	BRERETM
TM1	Team 1	QSECOFR

F3=Exit

F12=Previous

All Fields

Displays, for each District Number, the Teams and Team Descriptions defined to the User IDs.

Team File Enquiry



28/SSM

Use this option to display the territories, field service groups and job categories which have been defined to a team.

Team Enquiry Detail Screen



To display this screen enter a team number on the Team Enquiry Initial screen.

SS558	Demonstration Company CENTRAL BRANCH	BRERETM	25/11/93 14:52:11
Team Enquiry			
Team Number.....		TM1	Team 1
Field Service Group	Territory	Job Category	
G1 Group 1	T01 Territory 1	** ALL CATEGORIES **	
F3=Exit F12=Previous			

All Fields

This displays, for each team, all the field service groups, with their territories and job categories, which are defined to it.

Field Service Group Enquiry



29/SSM

Use this option to display field service group details, which link divisions and model families within a group.

A Team of engineers is set up by allocating certain combinations of field service group, territory and job category characteristics.

Field Service Group Enquiry Detail Screen



To display this screen enter a field service group on the Field Service Group Enquiry Initial screen.

SS559	Demonstration Company	BRERETM	25/11/93
	CENTRAL BRANCH		14:52:28
Field Service Group Enquiry			
Field Service Group..... G1 Group 1			
Model	Division	Model Group	Model Subgroup
	10		
	Environmental		
F3=Exit F12=Previous F13=Fold/Truncate			

All Fields

These display a list of divisions, model groups, model sub-groups and models which are defined to the selected field service group.

Functions:

F13

Fold/Truncate, to display descriptions of the codes used.

3-D Matrix Enquiry



30/SSM

Use this option to display the percentage change to be applied to the call response time depending on the customer priority, the volume usage of the model and whether or not the machine is working, but in need of attention, or completely out of action.

3-D Matrix Enquiry Detail Screen



Select 3-D Matrix Enquiry.

SS555		Demonstration Company CENTRAL BRANCH				USER BRERETM		25/11/93 14:52:55	
3-D Matrix Enquiry		PRIORITY 1 MACHINE		PRIORITY 2 MACHINE		PRIORITY 3 MACHINE		PRIORITY 4 MACHINE	
Vol	Seg	UP	DOWN	UP	DOWN	UP	DOWN	UP	DOWN
10		1	2	2	3	3	4	4	5
20		2	3	3	4	4	5	5	6
30		3	4	4	5	5	6	6	7
99		5	10	10	15	15	20	20	25
F3=Exit									

All Fields

The 3-D Matrix displays for each volume segment record set up on the volume segment file.

The screen shows the percentage reduction to be applied to the call response time for up to four customer priorities; the reduction is defined depending on whether the machine is up (that is, working), or down (that is, not working).

Special Serial Numbers Enquiry



31/SSM

Use this option to display the response times for specific model and serial number combinations, with account or address codes or both and installation site names.

Serial Number Enquiry Initial Screen



Select Special Serial Numbers Enquiry.

SS554	Demonstration Company CENTRAL BRANCH	USER BRERETM	25/11/93 14:53:26
Special Serial Numbers Enquiry			
Serial Number.....	<u>W930001</u>	Model.....	<u>WA10</u>
F3=Exit F4=Prompt F6=List of Serial Numbers			

All Fields

Enter a serial number to display the models for selection (if more than one exists for the serial number).

Functions:

F6

Displays a list of the serial numbers, for selection, which have had their response times defined.



Press **Enter** to display the Serial Number Enquiry Detail screen.

Serial Number Enquiry Detail Screen



To display this screen enter the serial number/model combination on the Serial Number Enquiry Initial screen and Press **Enter**.

SS554	Demonstration Company CENTRAL BRANCH	USER BRERETM	25/11/93 14:53:42
-------	---	--------------	----------------------

Special Serial Numbers Enquiry

Serial Number.....	W930001	Model.....	WA10
Account Number.....	C03 / 000	Jones and Crossland Ltd.	
Response time	1:15		

F3=Exit F12=Previous

All Fields

These display details of the customer account or address codes and installation site name, with the response time defined for the machine for your selected serial number and model combination.