

-
-
-
-
-

Chapter 5

Service Operations



Service Call Logging

1/SSS

Use this option to enter the details of a new service call from a customer, and update an existing call.

You can use the remote communications link to transmit call details to field engineers.

A service job is a defined set of work at a single customer site, identified by a unique module-generated job number. It may consist of one or more job lines, that is, pieces of equipment. Each job line is treated as a separate unit of work within the job, with its own job category, fault code, customer contact name, target response date and time, status and engineer.

Access

This option is extremely flexible with regard to the information you can use to get to the job you want to set up or maintain. You can enter just the serial number, or the model; the customer or customer and account, and so on.

Whichever fields you complete on the Job Maintenance Selection screen, when you press **Enter** the system automatically displays lists of missing information so that you can make a selection. So, if you enter just the account number, when you press **Enter** you see a list of addresses for that customer, and have to select one. You then select the machine, and so on.

These selection screens are not included in this documentation, as there are several of them. They are easy to use; they simply list the addresses, contract types, machines, models, locations, or whatever the system needs, and you make your selection.

When the system has enough information to identify the job you are setting up or maintaining, the Job Line Details screen 1 is displayed.

Specific Test Data



Note: To allocate a new job to a team, check that certain default information is set up covering the default team for the company, where Z1 is the demonstration company.

1. Division Code Maintenance: Z1 *D default division: Z1 team allocation.
2. Field Service Group Maintenance: Z1 *D all field service groups for team *DF *D (division field).
3. Geocode/Territory Maintenance: Z1 CT *DF all territories for team *DF *DF *DF.
4. Team File Maintenance: Z1 CT *DF default branch team *D *DF *blank.
5. District File Maintenance: authorise users to the *DF team. You will need to change branch to the one which originally created the default district. A query on the district file (SSP68) will show you which branch this was.

The geocode/territory and team entries will work successfully for all branches in the demonstration company.

Use the Function key options to:

- Access the contract numbers and dates relating to this equipment, and to the charge matrix for each.
- Access the team for engineer selection for the job line.
- Access the machine message file for sending and receiving messages.
- Access the job history enquiry, to view details of previous jobs done on this piece of equipment.
- Access any peripheral equipment fitted to the machine, as indicated by the configuration codes.
- Set the status of the job line to telephone call required.
- Access the dates and times this call has been updated and the User ID making the updates.
- Call completion, with the entry of a reason code.

Job Maintenance Selection Screen



Select Service Call Logging.

You can choose the field the cursor is in when the screen comes up by specifying it in the System Parameters Maintenance option, on the fourth screen.

SS210	Z1 - C&T TEST COMPANY	USER GBJBAJKG	1/03/96
	BIRMINGHAM BRANCH		11:27:39
Job Maintenance			
Serial Number.....		Model.....?..	
Or: Account Number...?.. C03		Account Address.....	
Or: Contract Number.....		Contract Type.....?..	
Or: Customer Order No...			
Or: Job Number.....			
Breakdown (0/1)..... 1			
F3=Exit F4=Prompt F10=New Customer			
07-30	82	MW	KS
		IM	II
		KENB20A	PED129S1

Fields:

Serial Number

To log a new job, the quickest access is by entry of the serial number of the machine requiring service.

If more than one job line is found for that machine, they will all be displayed.

If a job is already outstanding for the machine, it will be displayed to allow selection for update; alternatively, a new job may be added.

Model

Enter an existing model. If this is all you enter, you will then see a list of all machines of this model at all installation sites. This list can be lengthy, and this method is not recommended when taking a new call.

Account Number

Enter the customer account.

If a customer who does not have an account phones in, you can still take the call by setting them up as a cash customer. To do this, you must still enter an existing account: a special dummy number can be reserved for this purpose. You can enter a new address code. You then enter the name and address of the new installation, followed by the pieces of equipment installed at the site. You can then log the job details.

If the cursor is to be positioned on the account number field when the screen is first displayed, set the Position Cursor field to 1 on System Parameters Maintenance screen 4.

Account Address

If you enter an account number, you can enter the address if you know it. If you do not, you will have to select one from a list displayed when you press **Enter**.

Contract Number

If you enter a contract number, and optionally a contract type, a list of existing jobs relating to the contract is displayed. If there are no existing jobs for the contract, a new job number will be allocated. For a new job, if only one piece of equipment is covered by the contract, the first Job Line Details screen is presented immediately. If multiple pieces of equipment are covered, these are listed.

If the cursor is to be positioned on the contract number field when the screen is first displayed, set the Position Cursor field to 2 on System Parameters Maintenance screen 4.

Contract Type

If you enter a contract number you can also enter the type. This will save you selecting the type from a list displayed when you press **Enter**.

Customer Order No

Enter the customer order number. It must be valid on at least one job.

The customer order number can be used to access an existing job. A list of jobs relating to the entered customer order number is displayed.

If the cursor is to be positioned on the customer order number field when the screen is first displayed, set the Position Cursor field to 3 on System Parameters Maintenance screen 4.

Job Number

If you enter a job, it must be an existing job which has not yet been completed through technical reporting. When you press **Enter** you see a list of equipment on this job.

Breakdown

The breakdown indicator is normally 1. This sets the Job Cat field on the Job Line Details screen 2 to the default breakdown job category; the latter is defined in the Job Category Maintenance.

Functions:

F18

New Customer. This enables you to enter a new customer.

Job Header/Line Selection Screen



For a new job, if only one piece of equipment is installed at the site you select, the first Job Line Details screen is shown.

If multiple pieces of equipment are installed, the Job Header/Line Selection screen is shown, so that those items to be included on the new job can be selected.

Use this screen to enter the customer order reference and contact, and select the pieces of equipment to be included on the current job number. You can add new pieces of equipment, not yet recorded on the installation database, for the installation site. For each piece of equipment selected, the first Job Line Details screen is displayed.

SS220	Z1 - C&T TEST COMPANY	USER GBJBAJG	1/03/96
	BIRMINGHAM BRANCH		11:31:35
Job Header/Line Selection		Job Number	5485
Account Location....	C03	000 Jones and Crossland Ltd	
Contract No./Type/Dt	JMMNVAT	B05 S&V Adv	
Customer Order No....		Contact date	16/02/96
Job Contact.....		Contact time	17:39
Jb.Cat	Model	Serial	Sts Location of equipment
- CAL	AA-M01		00
- CAL	AA-M02		00
1=Select job line 4=Delete job line			
F3=Exit F4=Prompt F7=Job Story			
F12=Previous F13=Fold/Truncate F21=Text			
07-24	82	MW	KS IM II KENB20A PED129S1

Fields:

Customer Order No

Enter the customer order number, if required.

This is mandatory, if you have set the site's Additional Service Details to 1=Yes to customer ref. for job.

Job Contact

Enter the name of the person placing the call, or the person to be contacted on site by the engineer. The job contact defaults through to the Job Line Details screen 1.

The job contact may cover a number of job lines, if the More Than One Machine Allowed On A Breakdown Call is set to 1 on the System Parameters Maintenance screen 4.

Model

You can add a model to the list.

Serial

Enter the serial number, if known, together with the model code.

If you do not enter a serial number a quantity of 1 will be assumed. The installation record is updated with this model and serial number.

Untitled

Select. Enter one of the following:

- 1 - Select the item for service.
- 4 - Cancel the job line for that item of equipment and delete it from the job.

Functions:

F7

Job Story. This displays the Free Format Text screen, where you can enter text for the job.

F13

Fold/Truncate. This toggles between displaying more or less detail for each model listed.

F21

Text. This displays the Free Format Text screen, where you can enter text for the job.

Job Line Details Screen 1



For a new job, if only one piece of equipment is installed at the site you select, the first Job Line Details screen is shown.

If multiple pieces of equipment are installed, the Job Header/Line Selection screen is shown, so that those items to be included on the new job can be selected.

Use this screen to amend the customer details for this call only. This does not directly update the customer address in Accounts Receivable.

If the call is a repeat call (that is, a call-back to the same piece of equipment within a user predefined number of days or machine cycles or both), the Call History Window displays the last five calls.

SS221	Z1 - C&T TEST COMPANY BIRMINGHAM BRANCH	USER GBJBAJKG	1/03/96 11:45:48
Job Line Details			
Machine.....: ANS01	/ JKG001	Job number.....: 6086	ANS MODEL #01
Customer number.: C01	005		
Customer name...: Keith Pugh Delivery Point 5		Currency customer 1	
Customer address: Bristol		Currency code...?: GBP	
		Curr rate code...?: PERD	
		VAT code.....?: 001	
Machine location:			
Contact person..:		Geo code.....: FD1	
Telephone number:		Fax number...:	
Opening hours...:	Mon	Tue	Wed
From...:	8:00	8:00	8:00
Until...:	17:00	17:00	17:00
From...:			
Until...:			
F3=Exit F4=Prompt F8=Update F12=Previous			
18-68	S2	MW	KS IM II KENB20A PED129S1

Fields:

Customer Name

Change the customer name as required. This will not update the customer in Accounts Receivable.

Customer Address

Change the address as required. This will not update the customer in Accounts Receivable.

Currency Customer

Enter one of the following:

0 - This is not a currency customer.

1 - This is a currency customer.

Currency Code

This defaults from the customer additional service details, but you can change it.

Curr Rate Code

This defaults from the customer additional service details, but you can change it.

VAT Code

This defaults from the customer additional service details, but you can change it.



Note: Tax codes on the charge matrix will override this value.

Machine Location

This is the exact location of the item selected for service.

Contact Person

This defaults from the contact set up for the selected machine. If you change the name here, the machine will be updated at **F8=Update** for this machine only. If there is more than one machine on the job, the equipment for the second and subsequent machines are not changed.

If you did not enter a job contact on the Job Header/Line Selection screen, this name will default through to the Job Line Detail screen 1 for each machine included in the job.

Geo Code

This is the geocode from the customer additional service details. You can change it.

The geocode/territory link directly influences the team to be selected for the call. You select the team on Job Line Details screen 2.

Telephone Number

This is the telephone number from the customer additional service details. You can amend or set up the number and update the service details.



If you change the name and address for this job only and you also enter a different phone number, be aware that the override address only holds 15 figures. Do not overtype a 20 figure telephone number because the last five characters will simply be lost.

Fax Number

This is the facsimile number from the customer additional service details. The number can be amended, or set up.

Opening Hours

These are the opening or closing hours from the customer additional service details. They can be amended, or set up.



Select **F8=Update**.

If you are adding a new job and its default job category is assessed by the system to be for a

repeat call or for a specialist call, then the Call History Window is displayed.

Otherwise, **F8=Update** displays the Job Line Details screen 2.

Call History Window



To display this screen Select **F8=Update** on the Job Line Details screen 1, when you add a new job, and its default job category is assessed by the system to be for a repeat call or for a specialist call.

```

SS221          Z1 - C&T TEST COMPANY          USER GBJBAJKG    1/03/96
Job Line Details                               11:42:50
Job number...: 7338                            UPDATE
Status...: 00=Open                          Serial number.:
Sub Status...:                               Model number...: AA-M01
Contract type: B05 S&V Adv                    Configuration.:
Customer.....: Jones and Crossland Ltd       Account/loc...: C03      000
Call received: 16/02/96 17:39                 Warranty exp...: 0/00/00
Response time:
Target date...: 30/04/96 8:00
Job cat.....?: CAL Calibration : BS5750
Contact.....: JOHN JENSEN
Travel/Labour Chargeable
Parts Chargeable
WARNING -No Charge Matrix exists

Call History
Call Reception C A Resp Engr J F M S C V R Labour Meter 1 P E
Date Time H P Time Code C C S S A T C Hours Only F C
16/02/96 17:44 0 0 0:00 CAL 0 0 0 0 0 0 0:00 000000 0
16/02/96 17:39 0 0 0:00 CAL 0 0 0 0 0 0 0:00 000000 0
16/02/96 17:32 0 0 0:00 PSV 0 0 0 0 0 0 0:00 000000 0
23/11/95 9:02 0 0 0:00 PSV 0 0 0 0 0 0 0:00 000000 0 0
4/08/95 15:04 0 0 0:02 JOHN JC1 ELE RPU 0 3:00 005000 1 0

Enter=Continue
F9=Assign Eng. F10=Messages F12=Previous F13=Hist. Enq. F14=Peripherals

16-04  S4 MW KS IM II KENB20A PED129S1
  
```

Fields:

Untitled

Select. Enter 1 to review a previous call.

Call Reception Date

The date the call was logged.

Call Reception Time

The time the call was logged.

C H

Enter one of the following:

0 - The call has not been on credit hold.

1 - The call has been on credit hold.

A P

Enter one of the following:

0 - There was no appointment date and time for the call.

1 - There was an appointment date and time for the call.

Resp Time

This is the actual response time, established at the technical report stage.

Engr Code

The code for the engineer who completed the call.

J C

The job category first included in the technical report for the job line.

F C

The fault code for the job line.

M S

The machine section repaired. The code is validated against parameter type SECT in the Codes/Parameter File Maintenance option.

S S

The machine sub-section repaired. The code is validated against parameter type SSCT in the Codes/Parameter File Maintenance option.

C A

The corrective action taken by the engineer. The code is validated against parameter type CORA in the Codes/Parameter File Maintenance option.

V T

Enter one of the following:

0 - Contract maintenance visit type.

1 - Service visit type.

R C

Return call reason code. The RVTY codes, 0 to 7, are hard-coded in a table and are not user-maintainable. They are displayed on the Return Visits Window, if prompted, on exiting call reporting, if the Return Visit field on the Call Reporting screen is set on.

The RVTY codes are:

0 - Return visit not required.

1 - Return visit on parts required.

2 - Return visit on knowledge required.

3 - Return visit required at end of day - customer.

4 - Return visit required at end of day - engineer.

5 - Return visit required for personal reasons.

6 - Engineer could not gain access to machine.

7 - Call stopped by despatching.

Labour Hours

The time taken by the engineer to complete the call.

Meter 1 Only

This displays the last 6 digits of the meter reading entered on the Call Reporting screen of the technical report.

P F

Enter one of the following:

0 - Parts not fitted.

1 - Parts fitted.

E C

Enter one of the following:

0 - No emergency code.

1 - Emergency code. The call target time would have been set to the call reception date and time.



Having reviewed any of the calls in the Call History Window, press **Enter** to continue. The full Job Line Details screen can then be maintained.

If remote communications is active, the value can be updated from the field; the despatcher can also qualify the job status by entering a user defined, but valid, sub-status code.



Note: If this field has any entry other than blank, this job will be excluded from Automatic Call Assignment.

Contract Type

This identifies the type of contract.

Configuration

Enter the configuration code. There are up to five alphanumeric codes which indicate the peripherals attached to the machine. They are entered against the model, but set up in the Codes/Parameter File Maintenance option, under parameter type CONF.

Customer

This is the site name and the account or address codes.

Call Received

The date and time of call receipt can be amended if the call screen is in addition mode. This is to allow for calls taken out of hours and so on, Once the call has been updated, no further changes may be made to these fields.

Warranty Equipment

Non-metered equipment:

1 - This equipment is still under warranty.

Metered equipment:

1 - This equipment is still under warranty, and has not yet used up the warranty copies specified.

Parts

Enter one of the following:

0 - There is no special parts warranty still in force for this equipment.

1 - There is at least one special parts warranty in force for this equipment.

The presence of parts with extended warranty has no effect on the job category of the equipment on the call.

Response Time

The response time (hhh:mm) is used to calculate the target time for work to be started on the call.

Response hours are retrieved, through the response time hierarchy, starting with special serial number data, then contract line (machine), contract header, contract type, down to branch default time in escalation control maintenance. The time may be affected by the 3-D matrix percentages, but not if it is set up as a special serial number.

If you change the value of the Machine Up field, blank out the response time field and press **Enter**. The response time is re-calculated to reflect the change, and the new effect of the 3-D matrix machine up or machine down percentage.

Bad Credit Status

If the customer exceeds their credit limit a warning is displayed. You can still log the call.

Target Date

The target date and time are displayed as calculated by the system. It is call received time plus response time, with allowance for the Branch Service Window.

Charge Matrix

This warns if no charges have been set up on the contract type/job category file.

Displays the charge elements involved, if charges have been set up for the call's contract type/job category combination.

Job Cat

A default job category is displayed, to indicate what type of job is involved: breakdown, warranty, repeat and so on, Defaults are defined in job category maintenance.

In update mode, the job category may only be amended if the job is at, or is changed to, status 00 (Open).

Contact

The name defaults from the Job Header screen, or from the first Job Line Details screen, which extracts it from the installed equipment file for the first machine on the job.

The name may be changed. The change will only apply to the particular Job Line Details record.

Machine Locn

This is the machine location. The data may have been updated on the first Job Line Details screen.

Fault

Enter a fault code or prompt for an existing code. This field can be made mandatory in the Codes/Parameter File Maintenance option using type VLDN.

Untitled

Fault description. If a fault code has been entered, its associated description will be displayed.

Re-transmit

Enter one of the following:

0 - No re-transmission (the default).

1 - For use with the remote communications link. An amended record should be re-transmitted to the engineer's terminal.

Untitled

Fault description. This enables a further description of the fault to be entered.

Team

Team allocation is based on engineer territory, including geocode and field service group, and the installation site's geocode. If no match is found, the allocation is to *DF: the default team.

To move the job from team *DF, prompt on the field, to display other teams whose skills are appropriate to the machine on the job.

Machine Up

Enter one of the following:

0 - The machine is down, and out of action.

1 - The machine is still operational, but in need of service attention. This is the default.

Whenever the value is changed, blank out the response time value and press **Enter**. The response hours are recalculated, to allow for the effect of the 3-D matrix percentage values.

Eng No

This must be a valid engineer.

The call can be automatically allocated to an engineer, if an engineer is set up on the machine on the job line.

The engineer field can be made mandatory in the Codes/Parameter File Maintenance option using type VLDN.

Maintenance

This indicates if a service has been carried out with the repair.

Appoint Date

If a valid date and time are entered, they become the call's target date and time.

If a valid date, time and engineer are entered, they will also be booked in the engineer's diary as an appointment.

An appointment call must be made to use the assisting engineer function. The **F20=Assist Eng** is displayed once the call status is 01 (Assigned).

Job Duration

A time can be entered in hours and minutes for the estimated job duration. The value displayed as a default is retrieved from the model details.

Order No

Enter the customer order number. This may authorise the work to be done.

If Customer Ref. for Job ? is set to 1 - Yes in the customer additional service details, and there are any chargeable elements involved in the job, this field is mandatory.

Estim Arrival

The date and time are system-maintained, once the job status is 02 (Scheduled).

Emergency

Enter 1 (Yes) to change the target date and time to the current system date and time.

The number of consecutive times the emergency flag can be set is limited by the Minimum Number Of Calls Between Emergency Calls field on screen 1 in System Parameters File Maintenance.

Despatched

The date and time are system-maintained, once the job status is 03 (Despatched).

Functions:

F5

Equip Maint. This displays the standard Equipment Detail Maintenance screen.



Note: If you grant additional warranty via this screen, the system will not update the job category for you. You will have to change the job category yourself.

F6

Contract. Contract details and charge matrix.

F7

Text. You can enter text for the whole job.

F9

Assign Eng. Assign engineer (select from a team window display, other than *DF).

F10

Messages. Send machine message.

F13

Hist Enq. Job history enquiry.

F14

Peripherals.

F15

Complete Call. Complete call (only displayed if job status is 00 (Open)).

F16

Message Retrieval. Machine message retrieval.

F17

Audit. Displays the Job Audit Enquiry Window.

F20

Assist Eng. To nominate assisting engineer(s).

The job status must be 01 (Assigned), and an appointment date and time must be set.

F21

Job Story. You can enter text for the job line - for this piece of equipment on this job.

F22


Phone Call Req'd. Change the status of the job line to Phone Call Required.

F23

Name + Address. Name and site address maintenance.

F24

More Keys.



Note: To view this screen the job status must be at 01 (assigned) and the appointment date and time must be set.

```

SS060          Z1 - C&T TEST COMPANY          USER GBJBAJKG      6/03/96
                  BIRMINGHAM BRANCH
Assisting Engineer Maintenance

Prime Engineer..... A-03   A.CRANFIELD          Job Number.... 0006096
Appointment Date... 15/03/96   Time.... 10:00      Job Duration..    2

Assisting Engineer.....?.. A-01

X  Assisting Engineer          Reason for Unassignment

4-Delete
F3=Exit   F4=Prompt   F8=Update   F12=Previous

08-38    Sf          MW          KS          IM          II  KENB20A  PED129S1

```

X

Select. Enter 4 to cancel an engineer from the job.

Assisting Engineer

This details each assisting engineer allocated to the job.

Reason For Unassignment

This field displays the reason code if automatic call assignment cannot schedule the assisting engineer.



Press **F8=Update** to save any details to file.

Engineer Work Allocation

1...
2...

2/SSS

Use this option to provide a list of outstanding jobs and their status. Engineers calling in can report jobs which are completed or awaiting parts, and can have further work allocated to them.

Information can be passed to and from the engineers either by traditional means (telephone, fax, office visits, and so on) or by using the remote communications link.

Description

The initial screen provides a number of different methods of selecting the display of outstanding jobs.

Enter a single engineer to view only those jobs assigned to this engineer.

Enter a team to display all the jobs for the team, or all unassigned jobs for the service branch (that is, those which have no engineer assigned to them).

Further fields mean you can select jobs of a certain status or type (that is, planned or breakdown).

A list of all job lines matching the entered selection parameters is displayed.

The job lines displayed can then be updated individually as required, to assign, allocate or despatch the engineer, or flag as status work in progress, awaiting parts, or completed.

You can also enter engineer and team messages. There is no facility to receive engineer messages in Engineer Work Allocation.

Engineer Work Allocation Initial Screen



Select Engineer Work Allocation.

SS240	Demonstration Company CENTRAL BRANCH	USER BRERETM	26/11/93 12:26:09
Engineer Work Allocation			
Jobs for an Engineer.....?.: ____			
OR			
Jobs for a Team.....?.: <u>TM1</u>			
OR			
Jobs for the Branch (1).....: <u>0</u>			
Contracted Maint (1) or Emergency (2): <u>2</u> (Blank for Both)			
Status Ranges.....: 00 to 04			
00=Open	01=Assigned	02=Scheduled	03=Despatched
04=Work in Progres	05=Telephone	06=Parts	07=Credit Hold
08=Complete (Not D	09=Partial Report	10=SOP Job	
Status of call for Serial Number.....: _____			
All calls for Account No./Location.?: _____			
F3=Exit F4=Prompt F6=Work Control Screen F8=Message Entry F10=Diary			

Fields:

Jobs For An Engineer

Enter an engineer code.

Only call-out jobs within the status range 00 to 04 will be displayed for the engineer, unless the default values are changed.

Any outstanding engineer messages (that is, to the engineer himself, to his team, or to all at his branch) will be displayed prior to the job list.

Jobs For A Team

Enter a team code.

This will display the jobs, for the selected team and status range.

Any outstanding team messages will be displayed prior to the job list.

Jobs For The Branch

Enter one of the following:

0 - The default. To select engineer or team jobs.

1 - For branch jobs. In this case leave the previous fields blank. This will display jobs for the branch and the selected status range.

Messages for the branch are not displayed prior to the job list; they can be checked by taking the menu option for Engineer Messages.

Scheduled PM Or Callout

Enter one of the following:

- 1 - Display jobs generated by running the Load Planned Maintenance Jobs option.
- 2 - Display emergency jobs; those generated by call logging. This is the default.
- Blank - Display both planned and emergency jobs.

Status Ranges

Valid entries are 00 to 09. These are set up in the Codes/Parameters File Maintenance option, parameter type JLST. As a default, all active jobs in the range 00 to 04 are displayed.

To select an individual status code, enter the same value in the From and To fields.

Status 10 (SOP job) is not used by the current system.

Status Of Call For Serial Number

Enter a serial number to display all outstanding calls for that serial number.

All Calls For Account No

Enter an account number to display all outstanding jobs for the account.

All Calls For Location

Enter the location to display a list of all jobs outstanding for the installation address.

Functions:

F6

Work Control screen. To view the Scheduled/Appointment Calls screen.

F10

Engineer Diary. Select this to display the Engineer Work Allocation Engineer Diary screen.

Scheduled/Appointment Calls Screen (F6)



To display this screen select **F6=Work Control screen** from the Engineer Work Allocation Initial screen



Tip: The display uses colour: avoid monochrome screens if you can.

The screen displays scheduled and unscheduled jobs for a team, in graphical format, with colours representing the time remaining to target.

Engineers for the displayed team are represented by their code number. Up to twenty engineers can be represented in two rows: the eleventh engineer's details appearing below the first's, and so on.

Place the cursor on an engineer code and press **Enter** to display his work queue.

Place the cursor on the unscheduled calls line and press **Enter**; select the job category required, or leave blank, and press **Enter** - the Engineer Work Allocation screen is displayed, and the required job can then be selected.

The blocks below each engineer are the calls to be scheduled to that engineer, and are listed in the preferred order of completion. Only 4 jobs can be displayed for an engineer. If more than four jobs are allocated to his job queue, the subsequent jobs will no longer be Unscheduled, but equally they will no longer be displayed as Scheduled.

The colour of each block represents the job's time from target, as follows:

Red & Flashing **** - Within 0:30 hrs:mins of target time.

Red - Within 0:30 and 2:30 hrs:mins of target time.

Amber - Within 2:30 and 4:30 hrs:mins of target time.

Green - Within 4:30 and 6:30 hrs:mins of target time.

Blue - Within 6:30 and 8:30 hrs:mins of target time.

White - More than 8:30 hrs:mins from target time.

```

SS244          Z1 - GB Demonstration Company      2/01/97 15:01:40
Scheduled/Appointment Calls   Team: Heat & Vent : "Brum" Trg.

+++++ HV001  HV002  HV003  HV004  HV005  HV006  HV007  HV008  HV009
****   ****   ****   ****   ****   ****   ****   ****   ****   8:30
****   ****   ****   ****   ****   ****   ****   ****   ****   8:30
****   ****   ****   ****   ****   8:30   ****   ****   ****   8:30
                                ****   8:30   ****   8:30   ****

HV010 HV011 HV012 HV013 HV014 HV015 HV016 HV017 HV018 HV019
****   ****   ****   ****   ****   ****   ****   ****   ****   8:30
****   ****   ****   ****   ****   ****   ****   ****   ****   ****
****   ****   ****   ****   ****   ****   ****   ****   ****   8:30
                                ****   ****   ****   ****   ****

                               Unscheduled Calls

****   ****   ****   ****   ****   ****   ****   ****   ****   ****
****   ****   ****   ****   ****   ****   ****   ****   ****   ****
8:30   8:30   8:30   8:30   8:30   8:30   8:30   8:30   8:30   8:30
8:30   8:30   8:30   8:30   8:30   8:30   8:30   8:30   8:30   8:30
8:30   8:30   8:30   8:30   8:30   8:30   8:30   8:30   8:30   8:30
8:30   8:30   8:30   8:30   8:30   8:30   8:30   8:30   8:30   8:30

```

F5=Refresh F11=Move F12=Previous

01-02 SA MW KS IM II EDN400A PET179S2

Functions:

F11

Move. Place the cursor on a job block and select **F11=Move**, this will move the job to an engineer queue and schedule it. You can insert the moved job as job 1, 2, 3 or 4 on the engineer's queue if four jobs are already scheduled. Position the cursor on the job before which the new job is to be scheduled, and press **Enter**. An error message is displayed if the call cannot be scheduled. Certain errors can be overridden by **F14**.

Engineer Work Allocation Engineer Diary Screen (F10)



To display this screen select **F10=Diary** from the Engineer Work Allocation Initial screen.

Five days are displayed, starting with the current system date.

Select an engineer to make best use of the diary. If you select a team, the completion date, completion time and absence code are not available. You can enter non-machine-related jobs (holidays, sickness and so on,), as well as displaying appointment jobs. These entries are used by job scheduling.



Tip: Once you have completed an entry, the best way to amend any detail is to delete the existing one and add another.

SS831	Z1 - GB Demonstration Company		USER GBJBABL	16/01/97
Team Number.....		"BRUM" TRAINING & SERVICE BRANCH		12:21:24
BTH		Engineer Number..	HV002 LEM PUTT	
Thursday 16/01/97	Friday 17/01/97	Saturday 18/01/97	Sunday 19/01/97	Monday 20/01/97
	■ NJA 687 0:09 ---->	- NJA 687 6:00 0:00		
+				
1=Select 4=Delete 6=Details				
F10=Add Activity F12=Previous F14=Move To Date F16=Next Day F18=Prev Day				
08-18 SF MK KS IM II KENB20A PET17988				

Fields:

Untitled

Select. Enter one of the following.

- 1 - Redisplay the entry window for review and amendment.
- 4 - Delete the activity.
- 6 - Display the Job Line Detail Enquiry screen.

Or leave blank.

F10

Add Activity. Displays window to allow diary activity to be entered.

F14

Move To Date. Displays window to allow entry of date to move to.

F16

Next Day. Moves diary forward one day.

F18

Prev Day. Moves diary back one day.



Press **Enter**.

Non-Job Activity Maintenance Window (F10)



To display this window select **F10=Add Activity** on the Engineer Work Allocation Engineer Diary Screen (F10)

Use this window to add an activity to an engineer's diary.

SS831	Z1 - GB DEMO. SERVICE COMPANY	USER GBJBABL	16/01/97	
	"BRUM" TRAINING & SERVICE BRANCH		11:13:09	
Team Number.....	BTH	Engineer Number..	HV002	
Thursday	Friday	Saturday	Sunday	Monday
16/01/97	17/01/97	18/01/97	19/01/97	20/01/97

Non-Job Activity Maintenance		ADDITION
Job category..	☐	
Start date....	_____	Time...: _____
Duration.....	_____	
Comple. date:	_____	Time...: _____
Absence code..	_____	

F4=Prompt F8=Update F12=Previous

1=Select 4=Delete 6=Details
F10=Add Activity F12=Previous F14=Move To Date F16=Next Day F18=Prev Day
16-S2 S2 MK KS IM II KENB20A PET179S8

Fields:

Job category

All non machine related activities set up in the diary require a job category. You can set up codes in Job Category Maintenance.

Start Date

Enter the date on which the appointment starts.

Time

Enter the start time of the appointment.

Duration

If the duration will fit within the working day, enter the duration in hours and minutes.

If the duration would go beyond the end of the working day, leave duration blank and set the completion date and time - this ensures that a job entry is made in each of the working days affected.

Comple. Date

Enter the date on which the appointment will finish.

The field is not displayed when adding or updating activity for a team.

Time

Enter the completion time of the appointment.

The field is not displayed when adding or updating activity for a team.

Absence Code

Enter an absence code. The code will update the absent code on the engineer master file with immediate effect - not just for the diary date(s).

The code is only displayed at Add Activity. If amendment is required, delete the existing entry and add a new one. The field is not displayed when adding an activity for a team.



Note: Use Engineer Master File Maintenance to reset the Absent codes amended by engineer diary.

Engineer Work Allocation Team Job Lines



To display this screen enter a team code and accept the default values for the status range on the Engineer Work Allocation Initial screen and press **Enter**.

On the team screen, a job with assisting engineers will only be displayed for the assigned engineer. On an individual engineer's work allocation screen, jobs where he is assisting are displayed with *AST* in the Engr. column, instead of the normal code.

The Engineer Work Allocation screen for the selected team displays job lines details.

SS240	Z1 - C&T TEST COMPANY	USER GBJBAJKG	26/04/96
	BIRMINGHAM BRANCH		15:39:14
Engineer Work Allocation			
ALL JOBS FOR TEAM BRN Birmingham Nuts & Bolts			
	Target	ETA	E C
n Sta Engr. Pos Tx	Date/Time	Date/Time	M I Cat Model
ASS A-02	0 00 26/04 10:27	99/99 99:99	0 2 CSR AA-M02
			Geo Code
			GB
00-Open 01-Assign 02-Schedule 03-Despatch 04-WIP 05-Telephone 06-Parts 08-Complete 22-Ch Jb Dur 23-Story 24-Call enq. 25-Call maint. 26-Close/Ret. 98-Cancel 99-Tech.Rep. F3=Exit F6=Work Ctl F8=Messages F10=Diary F12=Previous F24=More Keys 08-02 SA MW KS IM II KENB20A PED129S1			

Fields:

Select Option

Enter a two character numeric code to change the Job status.

For jobs, valid options are 00 to 08, 22 to 26, 98 and 99.

For non-job activities, valid options are limited to 01, 08, 23, 98 and 99.

Option descriptions are shown towards the bottom of the screen.

Calls allocated to a team in call logging will be displayed as status 00 (Open). Enter 01, in the Select column against a call to see the Assign Engineer Window.



Note: If an engineer number was selected on the Initial screen, in addition to displaying jobs assigned to the engineer, the screen displays (at the top of the list) any unassigned jobs for the branch these jobs have a target response date and time prior to the earliest response date and

time of the jobs assigned to the engineer, that is, unassigned urgent jobs.

Functions:

F6

Work Ctl. Work Control screen.

F10

Diary. Engineer Diary.

F13

Fold/truncate for extra details.

F21

Text entry (Engineer).

F24

More Keys. Display more function keys.

Assign Engineer Window (Option 1)



To display this window enter 01 against a job line on the Engineer Work Allocation Team Job Lines screen .

```

SS240          Z1 - C&T TEST COMPANY          USER GBJBAJKG  26/04/96
                  BIRMINGHAM BRANCH                      15:39:14

Engineer Work Allocation

      ALL JOBS FOR TEAM BRN Birmingham Nuts & Bolts
      Target      ETA      E C
n Sta Engr. Pos Tx Date/Time Date/Time M I Cat Model      Geo Code
01 ASS A-02    0 00 26/04 10:27 99/99 99:99 0 2 CSR AA-M02    GB

Assign Engineer

Job :      7244  Model : AA-M02
          Serial:

From Engineer.....: A-02  A.BERTIE

To Engineer.....?: A-02

F4=Prompt  F8=Update  F12=Previous

00-Open      01-Assign      dule      03-Despatch  04-WIP
05-Telephone 06-Parts      08-Com
24-Call enqu. 25-Call maint. 26-Close/Ret. 98-Cancel  99-Tech.Rep.
F3=Exit  F6=Work Ctl F8=Messages F10=Diary F12=Previous F24=More Keys
16-S2    S2    MW    KS    IM    II  KENB20A PED129S1
  
```

Fields:

To Engineer

Enter an engineer. This will display the job's skill requirements and the engineers in the team with their skills.

By re-setting the status range on the parameter screen, only jobs within the selected status range will be displayed.

Settings on the job line status parameter code determine if the status allows technical report entry and whether escalation should include jobs at this status. The detail is set on parameter type JLST on the Codes/Parameter File Maintenance option.



*Note: Warnings on skills, team membership and absence can be overridden by **F14**, or **F8=Update**, as indicated in the various Warning Windows which may be displayed.*



Select **F8=Update** to assign the call to the selected engineer.

Engineer Work Allocation Job Schedule Window (Option 2)



To display this screen enter 02 against a job line on the Engineer Work Allocation Team Job Lines screen.

This will set the ETA (date and time) for the job. The finish time of the previous job plus the standard branch travel time equals the ETA of the next job.



Note: The Assign Engineer Window is again displayed, but there is the added facility to set the job's position in the work queue.

SS240	Z1 - C&T TEST COMPANY	USER GBJBAJKG	26/04/96
	BIRMINGHAM BRANCH		15:39:14
Engineer Work Allocation			
ALL JOBS FOR TEAM BRN Birmingham Nuts & Bolts			
	Target	ETA	E C
n Sta Engr. Pos Tx	Date/Time	Date/Time	M I Cat Model Geo Code
02 ASS A-02 0 00	26/04 10:27	99/99 99:99	0 2 CSR AA-M02 GB

Assign Engineer

Job : 7244 Model : AA-M02
Serial:

From Engineer.....: A-02 A.BERTIE

To Engineer.....?: A-02

Position in queue : 0

F4=Prompt F8=Update F12=Previous

00-Open	01-Assign	02-Assign	03-Despatch	04-WIP
05-Telephone	06-Parts	08-Com		
24-Call enq.	25-Call maint.	26-Close/Ret.	98-Cancel	99-Tech.Rep.
F3=Exit	F6=Work Ctl	F8=Messages	F10=Diary	F12=Previous F24=More Keys
16-52	SF	MW	KS	IM II KENB20A PED129S1

Fields:

To Engineer

Enter an engineer. This will display the job's skill requirements and the engineers in the team with their skills.

Position In Queue

You can use this to add a job after jobs already scheduled, or to insert a job ahead of an existing one. If this affects another job's target date and time, a warning is displayed, which may be overridden with **F14**.

Engineer Work Allocation Job Despatch Screen (Option 3)



To display this screen enter 03 against a job line;
if the correct job line has been selected, take
F8=Desp to confirm on the Engineer Work
Allocation Team Job Lines screen.

If the job is subject to an override name and address, the override details will be displayed.



Tip: The asterisk after **F10=Msgs** indicates there
is a machine message for the machine on this
job.

```

SS242                21 - GB Demonstration Company    USER GBJBABL  2/01/97
                    "BRUM" TRAINING & SERVICE BRANCH    16:21:05

Service Call Enquiry
Call Number.....: 388
Ser No/Model/Config.: M:25T-S0031 / 25-TCLR /
Cat./Maint/Fault....: INS / / INS Installation : SOP M/c
Account/Order No.....: TQA005 011 / TPIW/H096-ssv30214
Customer Name.....: The Pilchard Inn
Address 1.....: The Quay
                2.....: Burgh Island
                3.....: KINGSBRIDGE
                4.....: Devon
Address S/P.Code.....: T05 1PI
Service Location.....: CAUSEWAY TRACTOR HOUSE ROOF : 1N
Contact/Telephone....: AMBROSE NETTLEFOLD 01422-208802
Labour/Travel Chargeable  Parts Chargeable  Appoint.  0/00/00  0:00
Customer hours.: Mon   Tue   Wed   Thur   Fri   Sat   Sun
                From..: 9:30  9:30  9:30  9:30  9:30  9:30
                Until.: 12:15 12:15 12:15 12:15 12:15 12:15
                From..: 14:30 14:30 14:30 14:30 14:30 14:30
                Until.: 17:30 17:30 17:30 17:30 17:30 17:30

F6=Contr. F8=Desp. F10=Msgs F12=Prev. F13=Per iphs F16=Text F18=History
                01-02  SP      MW      KS      IM      II  EDN400A  PET179S2
  
```



*Note: Calls can only be despatched in the order
of the engineer's scheduled work queue.*

To change the sequence, take **F12=Previous** to return to the Engineer Work
Allocation screen, then enter 02 (Schedule) against the job to be deferred. Enter
a Position In Queue greater than the jobs to be completed before it, then enter
03 for the job to be despatched next and **F8=Update** to confirm.

Change ETA Window (Option 22)



To display this window select option 22 against a job line on the Engineer Work Allocation Team Job Lines screen.

```

SS240          Z1 - C&T TEST COMPANY          USER GBJBAJKG  26/04/96
                  BIRMINGHAM BRANCH                      15:39:14

Engineer Work Allocation

      ALL JOBS FOR TEAM BRN Birmingham Nuts & Bolts
      Target      ETA      E C
n Sta Engr. Pos Tx Date/Time Date/Time M I Cat Model      Geo Code
22 SCH A-01    1 00 26/04 10:27 26/04 16:46 0 2 CSR AA-M02      GB

Change ETA
Job : 7244 Model : AA-M02
Engr : A-01 Qty : 1

Target
Date : 26/04/96 Time : 10:27

Estimated Labour
Hours: 0:01

F8=Update F12=Previous

00-Open      01-Assign      02-Schedule      03-Despatch      04-WIP
05-Telephone 06-Parts      08-Complete      22-Ch Jb Dur      23-Story
24-Call enq. 25-Call maint. 26-Close/Ret.    98-Cancel      99-Tech.Rep.
F3=Exit F6=Work Ctl F8=Messages F10=Diary F12=Previous F24=More Keys
18-46      S2      MW      KS      IM      II KENB20A PED129S1
  
```

Fields:

Hours

You can enter a different estimate of the labour hours. This may impact on the start times of jobs later in the engineer's work queue.

Engineer Work Allocation Call Maintenance Screen

Please refer to the Service Call Logging And Maintenance section of the product information.

Return Visits Window (Option 26)



To display this window select option 26 against a job line on the Engineer Work Allocation Team Job Lines screen.

```

SS240          Z1 - UK Demonstration Company   USER GBJBALTW  18/05/98
                  CENTRAL BRANCH                15:03:10

Engineer Work Allocation

      ALL JOBS FOR TEAM TM1 Team 1
      Sub      Target      ETA      E C      Geo
n Sta Sta Engr.
-- DES BUZZ
-- OPN
-- OPN
-- OPN
-- OPN
-- OPN
-- OPN
26 ASS E0001
-- OPN
-- ASS BFE01
-- ASS BFE01
-- OPN

00-Open      01
05-Telephone 06
24-Call enq. 25-Call maint. 26-Close/Ret. 98-Cancel 99-Tech.Rep.
F13=Fold/Truncate                                F24=More Keys

      MA a                                09/054
  
```

Return Visits

Which Return Visit is required: 1 (1/0)

Is the Machine up now.....: 1 (1/0)

Engineer for Return Visit.....: E0001

JOHN SMITH

Keep Existing job: 1 (1/0)

If Return Visit on Parts

Parts must be delivered to....: 0 1=Engineers Van
2=Customer

Urgency Indicator.....: -

F4=Prompt F8=Update F12=Previous

Fields:

Which Return Visit Is Required

The RVTY codes, 0 to 7, are hard-coded in a table and are not user maintainable. Enter one of the following:

0 - Return visit not required.

1 - Return visit on parts required. If this code is used, and DRP is linked to Service, on update of the return visit window, the DRP order entry screens will be displayed, to allow spare parts to be ordered. (See further detail in call reporting - parts ordering).

2 - Return visit on knowledge required.

3 - Return visit required at end of day - customer.

4 - Return visit required at end of day - engineer.

5 - Return visit required for personal reasons.

6 - Engineer could not gain access to machine.

7 - Call stopped by despatching.

Is The Machine Up Now

Enter one of the following:

0 - No.

1 - Yes.

Engineer For Return Visit

Defaults to the engineer who carried out the job just completed and reported. The entry can be overridden; enter a valid engineer code, or prompt for the code selection window.

Keep Existing Job

This field enables you to choose whether a new job should be generated or not.

0 - Create a new job.

1 - Keep the existing job.

Jobs waiting for parts through DRP are set to status 06 automatically.

Parts To Be Delivered To

0 - For return visit codes other than 1 - Parts.

When the return visit code is 1 - Parts, enter here (for memo purposes only):

1 - Engineer's van.

2 - Customer.

Urgency Indicator

Leave blank unless the return visit code is 1 - Parts.

If the return visit code is 1 - Parts, enter a valid alphanumeric code as set up on the Inventory descriptions under SPED, or prompt for the code selection window.



*Note: At **F8=Update**, the system creates the return job, assigned to the engineer selected in the window. The job line status of the original job is set to 08=Comp on the job header and job details files. This allows the job to be taken to status 99, priced and invoiced when the return job is successfully completed.*

Cancel Job Line Reason Window (Option 98)



To display this window select option 98 against a job line on the Engineer Work Allocation Team Job Lines screen.

SS240	Z1 - C&T TEST COMPANY	USER GBJBAJKG	26/04/96
	BIRMINGHAM BRANCH		15:39:14
Engineer Work Allocation			
ALL JOBS FOR TEAM BRN Birmingham Nuts & Bolts			
	Target	ETA	E C
n Sta Engr. Pos Tx	Date/Time	Date/Time	M I Cat Model Geo Code
98 SCH A-01	1 00 26/04 10:27	26/04 16:46	0 2 CSR AA-M02 GB
Cancel Job Line Reason			
Enter Reason Code			
—			
F4=Prompt F8=Update F12=Previous			
00-Open	01-Assign	02-Schedule	03-Despatch
05-Telephone	06-Parts	08-Complete	22-Ch Jb Dur
24-Call enq.	25-Call maint.	26-Close/Ret.	98-Cancel
F3=Exit	F6=Work Ctl	F8=Messages	F10=Diary
12-49	SA	MW	KS
			IM
			II
			KENB20A
			PED129S1

Fields:

Enter Reason Code

Enter a code are set up in the Codes/Parameters File Maintenance option under parameter type CREA.



Select **F8=Update** to update.

Engineer Technical Reporting (Option 99)

This option:

- Records the details of work done (labour hours, travel hours, parts used, miscellaneous costs incurred) by engineers in completing service jobs.
- Allows orders to be placed for spares required to complete a job, provided that the DRP libraries have been included in the Service Management library list.

If remote communications is active, details are added or updated automatically.

Concepts

A technical report (sometimes known as a service report or service sheet) is a document completed by an engineer after performing a service call at a customer site.

A technical report must have a unique number, which is the job number to be reported, plus a TWO digit suffix. A technical report relates to a visit on a specific date by a specific engineer to a specific installation address. It can only include one job number on it, but the job could include more than one piece of equipment.

Description

To enter a new technical report (or update an existing report), enter 99 on the job line to be reported in Engineer Work Allocation. The Call Reporting screen is displayed.

Implications

The data recorded from technical reports is used:

- To maintain historical details of work carried out by engineers.
- To facilitate automatic pricing and invoicing of service jobs.
- To generate stock transactions for the parts used from engineers' vans.

Serially-numbered spares must only be purchased, stocked and issued in singles (often coded EA). Batch and lot controlled spares may be purchased, stocked or issued in units other than singles.

A job line can only be completed if the prime engineer and any assisting engineers have reported finishing with **F9** or **F10**. Until then, the call's status will be displayed as 09=Partial Report.

Call Reporting Screen (Option 99)



To display this screen enter 99 on the appropriate job line on the Engineer Work Allocation Team Job Lines screen.

You enter the basic visit details here, including the hours. You record parts used and miscellaneous costs and charges on the Call Reporting Parts Used screen and the Call Reporting Miscellaneous Charges screen, which are accessed by function keys.

All entries must be logged against a job category code, which together with the type of contract covering the equipment when the job was raised, determines if the customer is to be billed. The system will use a billing indicator of 100% for chargeable and 0% for non-chargeable, but you can change this.

If you reported a job for the wrong piece of equipment, you can change it to another existing model or serial number at the customer site; or you can add a new model or serial number.

SS280	Z1 - C&T TEST COMPANY	USER GBJBABL	11/07/96
Call Reporting	"BRUM" TRAINING BRANCH	Team: *DF	15:13:47
Engineer.....: *****			
Customer Details..:	TQA004 000	Old Mutual Properties Limited	
Model/Serial.....:	AA-M01	131295A	
Call Number.....:	0007578 00		
Call Category?....:	CSR Customer Service Request		
Call Received.....:	11/07/96 15:06	Labour Time	
Arrival Date/Time:	11/07/96 0:00	BASE	THRD HALF DBLE
Customer/Engineer Travel...:	0:00 0:00	:00	:00 :00 :00
Maintenance Done..:	0		
Fault Code.....?:	ELE Electrical fault		
Machine Section.?:	---		
Machine Sub-Sect?:	---		
Activity Code...?:	---		
Meter Reading 1...:	0 2: 0	Credit Copies: ---	
Return Visit 1/0..:	0		
New Job Required?:	0	Ref. Field...: 000757800	
Miles Travelled...:	---	Charge Labour: 100%	
Charge Mileage...:	1	Cust. Ord. No: RW01	
F4=Prompt F8=Update F9=Comp. Report Line F10=Comp. Job Line			
F11=Messages F12=Previous F15=Parts F16=Misc. Charges F24=More Keys			
10-30 52 MW KS IM II KENB20A PET178S2			

Fields:

Call Category

This is the current job category. You can overwrite it with another valid code, if now found to be incorrect for the work done.

Engineer Arrival Date

Defaults to the system date, but can be changed if required.

Engineer Arrival Time

Enter the time of the engineer's arrival on site.

Customer Travel Time

Enter the travel time in hours and minutes to be charged to the customer.

Engineer Travel Time

Enter the actual time in hours and minutes the engineer has spent travelling to the customer.

Labour Time - Type 1

Labour Hour Type Codes are held on the codes/parameter file under parameter type LHTY: the code IDs provide up to four column headings; the records hold the factors by which to increase the standard hourly labour rates. Set up just the number of labour types you require on the codes/parameter file; there is no need to set up the maximum of four.

Enter the engineer's basic labour time in hours and minutes for this job category.

If zero labour hours are required, enter 0 and field exit (and again, if you return to the screen later and only press **Enter**); otherwise, the system will fill the field with the value of (system date and time; engineer's arrival date and time): this is relevant to users who need real-time technical reporting of engineers' time, but not otherwise.



*Note: Additional hours can be entered for other job categories for the job line, by taking **F23=Additional Job Lines.***

Labour Time - Type 2

Enter the labour hours and minutes spent by the engineer at the appropriate overtime rate, as defined on the codes file.



*Note: Additional hours can be entered for other job categories for the job line, by taking **F23=Additional Job Lines.***

Labour Time - Type 3

Enter the labour hours and minutes spent by the engineer at the appropriate overtime rate, as defined on the codes file.



*Note: Additional hours can be entered for other job categories for the job line, by taking **F23=Additional Job Lines.***

Labour Time - Type 4

Enter the labour hours and minutes spent by the engineer at the appropriate overtime rate, as defined on the codes file.



*Note: Additional hours can be entered for other job categories for the job line, by taking **F23=Additional Job Lines.***

Maintenance Done

The field is for memo purposes only, to indicate if a planned maintenance service has been carried out with the repair.

Fault Code

The fault quoted by the customer at call logging is displayed. It may be changed to the fault reported by the engineer. Existing fault codes (parameter type FLTC, codes/parameter file) can be prompted for.

Machine Section

Optional entry of the main section of the machine which was faulty. The sections are defined on the codes file (parameter type SECT) and can be prompted for.

Machine Sub-Section

Enter a valid 3 character code, or prompt for the code selection window.

Optional entry of the sub-section of the machine which was faulty. The sections are defined on the codes file (parameter type SSCT) and can be prompted for.

Activity Code

This records the corrective action taken by the engineer to remedy the fault. Corrective action codes are defined on the codes file (parameter type CORA) and can be prompted for.

Meter Reading 1

If the Model record includes meters on the machine, the engineer's service readings are entered here. The Meter 1 value is displayed in the Call History Window when another call is logged for the machine.

Meter Reading 2

As for meter 1, except that no meter 2 is displayed in the Call Logging Window.

Return Visit

0 - No return visit is required.

1 - A return visit is required. On closure of the job, a window displays selection parameters to generate a new job.

If a return visit on parts is required and DRP is attached, the parts can be ordered by using the DRP order entry screens, which will be displayed.

New Job Required

Valid entries are 0 or 1: The field is only displayed if the corresponding field on Systems Parameters maintenance (screen 1 of 5) is set to 1.

After the current job is technically reported, and any return visit set up, a job header screen is displayed so that a call can be logged for a new or existing machine at the customer site. This field is displayed only if the Allow New Job at Technical Reporting field is set to 1 in the System Parameters File option.

Reference Field

The field defaults to the same value as the job number, plus the report suffix. If the report is updated, subsequent entries to add new reports will increment the report suffix.

It may be overwritten if an alternative reference for the job is required (for example, a pre-printed service report number).

Miles/Kms Travelled

Enter the distance travelled by the engineer. The maximum valid entry is limited to 99999.

The entry is not mandatory, but if no positive value is keyed in, it may result in no mileage charge being invoiced.

If Actual Distance Driven is the basis for chargeable travel for the site, a positive number must be entered. That number will be multiplied by the site charge per mile/km at job pricing.

Charge Labour

The default value, a percentage, is extracted from the contract type/job category charge matrix.

If chargeable, the value is set to 100;

If non-chargeable, it is set to 0. The value may be changed as required to any percentage value between 0 and 100.

Charge Miles/Kms

The default value is set by the call's contract type/job category charge matrix for mileage: 0 - No Charge and 1 - Charge. The value may be changed as required: for example, the charge may be set to 1 for one of the machines, but to 0 for any other machines included in the site visit.

If the setting is 1 - Charge, the charge miles/kms type defined on the customer additional service details file, or on the company profile file, will be applied to this technical report suffix number at job pricing.

Charge miles/kms types are:

- Standard Distance Value: a flat rate for the site.
- Actual Distance Driven: site charge per mile/km.
- Zone Code to Charge: code charge, by branch, set in the zone charges file.

Customer Order Number

The current customer order number will be displayed.

It may be amended; if blank, it may be entered.

Functions:

F5

Ord Parts. This takes you into DRP, to the Distribution Order Entry Delivery Address Override screen.

Use this to order spare parts for the job.

(This is only displayed if DRP libraries are included in the Service Management library list. The order entry screens are standard parts of DRP. Refer to the DRP product information for guidance on the processing of a DRP order.)

F6

This displays a window showing all priced lines for the job.

Use the window to price the job interactively. If the price is accepted for update, it will be written to the pending invoice file and will close the job. No further reports can be entered for the job-line/machine.

If there are still outstanding DRP orders for this job, you will be given a warning, which you can override.

F7

Text (job story) entry/update. Use to enter text against a job.

F9

Complete the visit report. This prevents any further entries against the job line on the technical report, and should be used only if all job lines which have been added to the technical report are completed on this visit report.

It does not complete the job line and does not prevent its inclusion on other technical reports. The job line is not released for job pricing at this stage (subsequent visit details are recorded on another technical report number, that is, 01, 02, 03 and so on).

Parts are sent through to Inventory Management, if attached. The parts used are updated in the engineer's stockroom and the appropriate stock movement records generated. The parts cost is extracted from Inventory Management at this stage, and is stored on the technical report.

F10

Complete a job line. This will set its status to complete, preventing any further technical report entries, and enabling it to be prepared for invoicing, through the Price Jobs option. This will also cause the report line to be completed. Invoicing will now be allowed for this job line for all technical reports it has been added to.

If there are still outstanding DRP orders for this job, you will be given a warning, which you can override.

Parts are sent through to Inventory Management, if attached. The parts used will be updated in the engineer's stockroom and the appropriate stock movement records generated. The parts cost is extracted from Inventory Management at this stage, and is stored on the technical report.

F11

Messages. Access the message function to send or retrieve machine messages.

F15

Parts maintenance for this job line.

F16

Miscellaneous charges maintenance for this job line.

F17

Serial Maintenance. Displays screen for the maintenance of the machine serial number and history movement.

F18

Maintain the serial number, to amend incorrect numbers and choose to move previous service history. The function is only available until the technical report on the original machine is entered: thereafter, no change can be made.

F19

Name and address maintenance.

F20

Access peripherals attached to the machine

F21

Text entry (booked hours).

F22

Job detail enquiry for the piece of equipment on this Job line.

F23

Displays window for entry of additional job line hours.

F24

More keys.

Parts Ordering Header Screen (F5)



To display this screen update from the Call Return Window where the reason for the return call is to fit parts,

Or: Select **F5=Ord Prts** on the technical report screen.

Once the first three fields on the screen have been validated, extra fields are displayed, but only the DRP delivery name and address details can be amended.

DR300	Service Demonstration	User SSV3	11/12/95 17:41:02
Distribution Order Entry			
From Stockroom..... CT Central			
To Stockroom..... 03 Engineer 3			
Despatch due date..... 11/12/95			
Internal Customer..... EAC03 001			
Delivery name and address:			
<u>Charlie Chapman</u>			
<u>123 Cardiff St</u>			
<u>Sketty</u>			
<u>Swansea</u>			
<u>SA3 6 SW</u>			
F3=Exit F12=Previous F21=Internal Text F22=External Text			
15-04	SF	ML	KS IM II KENB20A PET113S1

Fields:

From Stockroom

This is the supply stockroom from which the engineer's stock location is replenished. This is set up on the engineer's master record and in Inventory.

To Stockroom

This is the stockroom to which the ordered stock is transferred, and is usually the engineer's vehicle (or bench). It is set up in Inventory and defined on the engineer's master file.

Despatch Due Date

The original default was today's date, but it may have been overwritten. It is the date on which the parts should be shipped.

Internal Customer Account Number

This is from the DRP customer file. It is the DRP customer delivery address assigned to the To Stockroom. The address sequence number can only be 001.

The Account is included on the engineer master file, but with the address sequence 000.

Internal Customer Sequence Number

This is from the DRP customer file. It is the DRP customer delivery address assigned to the To Stockroom. The address sequence number can only be 001.

The account is included on the engineer master file, but with the address sequence 000.

DRP Delivery Name and Address

Defaults to the name and address details of the internal customer, but may be changed to any name and address required for shipping purposes.

Over key any revisions as necessary.

Functions:

F21

Internal text entry/update.

F22

External text entry/update.

Call Reporting Interactive Job Pricing Window (F6)



To display this window select **F6=Pricing** from any of the Call Reporting screens.

Interactive job pricing achieves the same result as taking **F10=Complete Job Line** from the Engineer Technical Reporting screen and then running Job Pricing.

SS265		Z1 - GB Demonstration Company		USER GBJBABL	2/01/97
		"BRUM" TRAINING & SERVICE BRANCH			16:52:01
Technical Report - Misc.Costs					
Account Location....	TQA005	002	The Royalists' Retreat Hotel		
Engineer.....	HV003		Technical Report No.	000039000	
Visit Date:	2/01/97		Job Number.....	390	
Contract No./Type/Dt			*NO	0/00/00	
Model.....	ARCH			196001	
Interactive Pricing Charges					
Charge ?	Currency		Fixed Labour	.00	Charge VAT
---	Code ?		T&M Labour	842.50	001
---	GBP		Parts	.00	Chargeable @
---			Miscellaneous	.00	
---			Fixed Travel	.00	Chargeable @
---			T&M Travel	.00	
---			Std Mileage*	.00	Chargeable @
			Total	842.50	Chargeable @ +
F8=Price F12=Previous					
F3=Exit	F4=Prompt	F6=Job Pricing	F7=Job Story	F8=Update	
F9=Comp. Report Line		F10=Comp. Job Line	F12=Previous	F14=Hours	
F15=Parts		F21=Text			
09-31	S	MW	KS	IM	II EDN400A PET179S2



Select **F8=Price** to price the job. A job price audit report is produced for the job line. The job line may be invoiced without having to be included in the batch run to price jobs.

Call Reporting Parts Used Screen (F15)



To display this screen select **F15=Parts** from any of the Call Reporting screens.

SS264	Z1 - GB Demonstration Company		USER GBJBABL	14/05/96
"BRUM" TRAINING & SERVICE BRANCH		15:09:58		
Technical Report - Parts				
Account Location....	MOD(TA) 000	Ministry of Defence (Territo		
Engineer.....	HV003	Technical Report No. 000009500		
Visit Date:	14/05/96	Job Number..... 95		
Contract No./Type/Dt		*NO 00/00/00		
Model.....	DONQ	Serial Number..... 040196015		
Part.....	Job Category.....	Qty Used/Rtnd	Src	Chrg
P873626/1	CSR Customer Service Request	2	E0002	100%
				0%
				0%
				0%
				0%
				+
F4=Prompt F6=Job Price F7=Job Stry F8=Update F9=Comp.Rep.Line				
F10=Comp. Job Line F12=Previous F14=Hours F16=Misc.Chrg F21=Text				
13-02 S MW KS IM II KENB20A PED129S1				

Fields:

Part

This must be a valid part number on the Inventory item master file.

If you do not enter a source in the Src field, then this part must be set up as existing in the engineer's stockroom.

If you do enter a source, and that source engineer stocks this part, then this part need not be set up in the engineer's stockroom. The system will create the part in the stockroom automatically.

If the part is subject to batch, lot or serial number control on item master (BATC35), a window to enter the batch details is displayed when you select **F8=Update**, **F9=Comp Rep Line** or **F10=Comp Job Line**.

Job Category

Must be a valid job category on the job category file.

Qty Used/Rtnd

The quantity used or returned.

Entry of a positive number signifies parts used; this reduces the available stock in the engineer's stockroom.

Entry of a negative number denotes parts returned; this increases the amount of frozen stock in the engineer's stock location.

This field does not allow you to enter decimals.

Both of these transactions are reflected in Inventory stock movement records.

If the item used or returned is defined in the Item master file as either lot, batch or serial number controlled, a window is displayed for the entry of the appropriate lot, batch or serial number when you select **F8=Update**, **F9=Comp.Rep.Line** or **F10=Comp. Job Line**.

Call reporting, where a DRP order for parts is involved, will display the Parts screen automatically, regardless of the status of the DRP order. Parts are transferred into the engineer's stock location immediately after confirmation of despatch from the supply stockroom.

Once the parts are available in the engineer's stock location, the DRP order quantities are displayed on the Parts screen. If usage equals or exceeds the order quantities, the stocks will be reduced; if usage is less than the DRP order, the actual amount used is taken off the stocks and the unused order amount is added to them.

Srcce

Enter an engineer's code, if the part has been sourced from another engineer in the same country.

A valid engineer code must be entered.

The part sourced will be transferred from the supplying to the fitting engineer's stockroom, before usage is updated by this technical report.

If you enter a source here, then you can enter an item which is not set up for this engineer's stockroom.



Note: World Trade and multi-currency will bar sourcing from a different country.

Charge %

The default value (retrieved when a part number is entered) is set in the call's contract type/job category charge matrix for parts: 0% - Non-Chargeable, 100% - Chargeable.

The value may be changed as required, to any percentage between 0 and 100%. The override will be effective even if the type of part is 0 on the charge matrix.

Whatever the charge % on a negative value, parts returned record, there will be no charge on the pricing audit report, nor on the job invoice. The cost of the frozen stock will be increased by the normal cost held on the item/stockroom record.

Functions:

F5

Ord Parts. This takes you into the DRP module, if you have it. You will see the Distribution Order Entry Delivery Address Override screen.

This key is not displayed if you have not installed DRP.

F6

Job Price. This displays a window showing all priced lines for the job, and you can price interactively from here.

If there are still outstanding DRP orders for this job, you will be given a warning, which you can override.

F7

Text (job story) entry/update.

F9

Complete the visit report. This key should be used only if all job lines which have been added to the technical report are completed on this visit report. No further access to the technical report suffix number will be permitted. Job line details are not released for job pricing (subsequent visit details will be recorded on another technical report number, that is, 01, 02, 03 and so on).

F10

Complete the job line. No further maintenance of this job line will be allowed on any technical report. Invoicing will now be allowed for this job line for all technical reports it has been added to.

If there are still outstanding DRP orders for this job, you will be given a warning, which you can override.

F14

Redisplays the hours screen for this job line.

F16

Miscellaneous charges maintenance for this job line.

F21

Text (booked hours) entry/update.

Call Reporting Miscellaneous Charges Screen (F16)



To display this screen select

F16=Miscellaneous Charges from various Call Reporting screens.

SS265	Z1 - GB Demonstration Company		USER GBJBABL	2/01/97
"BRUM" TRAINING & SERVICE BRANCH				
17:05:44				
Technical Report - Misc.Costs				
Account Location....	TQA005	011	The Pilchard Inn	
Engineer.....	HV011		Technical Report No.	000030000
Visit Date:	2/01/97		Job Number.....	300
Contract No./Type/Dt			*NO	0/00/00
Model.....	25-TCLR		Serial Number.....	M:25T-S0031
Charge ?	Currency	Job	Cost	% uplift
HTL	GBP	INS	45.00000	20
Crown Hotel		Installation		54
				Chargeable 1
				Chargeable @
				Chargeable @
				Chargeable @ +
F3=Exit F4=Prompt F6=Job Pricing F7=Job Story F8=Update				
F9=Comp. Report Line F10=Comp. Job Line F12=Previous F14=Hours				
F15=Parts				
14-02 SP MW KS IM II EDN400A PET179S2				

Fields:

Charge Type code

Must be on the codes file under code type CHGT. This code indicates what kind of miscellaneous cost and/or charge is being entered.

Charge Description

This normally displays the description of the charge type code (parameter type CHGT), but it can be over keyed.

If an Invoice is produced, it will show the over keyed text, instead of the charge code description.

Currency Code

Defaults, on the first line only, from the customer additional service details file; it may be overwritten with another valid currency code (a prompt is available).

Job Category Code

Must be a valid job category on the job category file.

Cost

Enter the cost of the item being entered, at the rate for the currency in the previous field. The cost will be recorded on the job file for use in reporting, but will be converted to base currency value, if multi-currency is in operation.

% Uplift

If entered, this percentage will be applied to the cost to calculate the charge value.

Valid % uplifts are from 100.00 to 999.99; 0 indicates no uplift; blank is not valid.

If not entered and an actual charge is, the % uplift will be calculated from the cost compared to the actual charge.

Charge

The charge can be entered, or if left blank, will be calculated from the cost and uplift %. If the charge is entered with the cost, the uplift is calculated.

VAT Code

The 3 character VAT code defaults from the additional service details file, or from the Installed equipment file if the machine is subject to a non-standard rate prompted by the VAT indicator. The value can be overwritten but the VAT code must be valid in General Ledger.

Chargeable

Valid entries are 1=Yes or 0=No. The default value is set by the call's contract type/job category charge matrix for Misc.. The value may be changed as required.

Functions:

F6

This displays a window showing all priced lines for the job, and you can price interactively from here.

If there are still outstanding DRP orders for this job, you will be given a warning, which you can override.

F7

Text (Job Story) entry/update.

F9

Complete the visit report, that is, this job line on this technical report. No further maintenance of this job line on this technical report suffix number will be allowed.

Any parts entered on the Parts Used screen will be taken out of stock.

Job line details are not released for job pricing. Subsequent visit details will be recorded on another technical report suffix number, that is, 01, 02, 03 and so on,

F10

Complete the job line. No further maintenance of this job line will be allowed on any technical report. Invoicing will now be allowed for this job line for all technical reports it has been added to.

Any parts entered on the Parts Used screen will be taken out of stock.

If there are still outstanding DRP orders for this job, you will be given a warning, which you can override.

F14

Hours maintenance for this job line.

F15

Parts used for this job line.

F21

Text (miscellaneous charge) entry/update.

Call Reporting Serial Number Maintenance Screen (F17)



To display this screen select **F17=Serial Number Maintenance** from the Call Reporting Hours/Details screen.

Use this screen to change or correct the serial number on the job. You may not change to a serial number which already exists on the equipment file: the **F18=Model Maintenance** function may be more appropriate for such a change.

SS077	Demonstration Company	USER BRERETM	30/11/93
	CENTRAL BRANCH		15:08:20
<u>Serial Number Maintenance</u>			
Account Number.....	C03	Account Address.....	000
Account Name.....	CENTRAL BRANCH		
Present Model.....	WA10	Serial....	W920100
<u>Enter Serial Numbers</u>			
Serial	History	Serial	History
W920110	1		
F3=Exit F12=Previous			

Fields:

Serial Number

Enter a serial number, which does not already exist. This is to correct a serial number for an existing piece of equipment, or to insert one where none previously existed. You may enter individual serial numbers in line with the quantity of equipment shown.



Note: The change of serial number is only effective once the day end routine has been run.

History

This must be 1 or blank.

Where there is more than one serial number to be entered, at least one must have 1 entered against it here.

This means that all previous job history will be held against this particular serial number in future.

Call Reporting Model Maintenance Screen (F18)



To display this screen select **F18=Model Maintenance** from the Call Reporting screen.

Use this screen to change of model and serial number to a machine on the site.



Note: The function is not available after technically reporting against the original machine on the job.

SS079	Demonstration Company	USER BRERETM	30/11/93
	CENTRAL BRANCH		15:08:41
Change Model/Serial No.		Job/Report No.	501134 00
Account Number.....	C03	Account Address.....	000
Account Name.....	Jones and Crossland Ltd.		
Model.....	WA10	Serial....	W920100
Quantity	1		
	Model	Serial	Quantity
-	WA10	W930001	1
-	WA10	22581038	1
1=Select			
F3=Exit F8=Update F12=Previous F14=Amend Machine			

Fields:

Untitled

Select. Enter 1 against the machine to which the job record must now be changed. The machines listed are from the Installed Equipment records for the site.



*Note: **F14** will allow you to add a machine not previously recorded in Service Management, to the site's installed equipment records, and to amend the job record.*



*Note: **F18** is only available if no details have been technically reported against the original machine.*

Model, Serial Number And Quantity

Display only: from the installed equipment records for the site.

If a serial number is displayed, the quantity will always be 1, if no serial number, the quantity shows how many of the model code are installed.

Functions:

F14

Amend machine window, to add a new model or serial number. and amend the job record.



Update the details by using **F8=Update** - if the model code is valid, and the model or serial number is unique to the system, the job record is amended, and a new installed equipment record set up.

Enter the engineer's basic labour time in hours and minutes for this job category.

Labour hour type codes are held on the codes/parameter file under parameter type LHTY; the code IDs provide the four column headings; the record holds the factor by which to increase the standard hourly Labour Rates.

Labour Time - Types 2, 3 And 4

Enter the labour hours and minutes spent by the engineer at the appropriate overtime rate as defined on the Codes file (Parameter Type LHTY).

Charge %

If the job category for the line is chargeable, this value will default to 100%; if it is non-chargeable, it will default to 0%.

The field may be changed to any intermediate value between 0 and 100, and the variable labour will be charged accordingly.



Note: This value has no effect on fixed labour charges retrieved from the contract type/job category file.

Call Reporting Return Visits Window (F10) (Option 26)



To display this window.

Close a technical report using **F10=Comp Job Line**, and the Return Visit field is set to 1 (It is not displayed if you take **F8=Update** or **F9=Comp Rep Line**).

Or: Enter 26 against a job line on the Engineer Work Allocation Team Job Lines screen.

```
SS280      Z1 - C&T TEST COMPANY      USER GBJBABL  11/07/96
Call Reporting  "BRUM" TRAINING BRANCH  Team: *DF    15:20:45

Engineer.....: *****
Customer Details.: TQA004  000          Old Mutual Properties Limited
Model/Serial.....: AA-M01          131295A
Call Number.....:
Call Category?...:
Call Received....:
Arrival Date/Time:
Customer/Engineer:
Maintenance Done.:
Fault Code.....?:
Machine Section.?
Machine Sub-Sect?
Activity Code....?
Meter Reading 1..
Return Visit 1/0.
New Job Required?
Miles Travelled..
Charge Mileage...

Return Visits
Which Return Visit is required: 1
Is the Machine up now.....: 1 (1/0)
Engineer for Return Visit.....:

If Return Visit on Parts
Parts must be delivered to.....: 0 1=Engineers Van
                                   2=Customer
Urgency Indicator.....:

F4=Prompt  F8=Update  F12=Previous
F7=Job Story  F19=Name & Address Maintenance  F21=Text
              F23=Additional Job Lines          F24=More Keys
09-54  SF  MW  KS  IM  II  KENB20A  PET178S2
```

Fields:

Return Visit Code

The RVTY codes, 0 to 7, are hard-coded in a table and are not user maintainable.

Enter one of the following:

0 - Return visit not required.

1 - Return visit on parts required. If this code is used, and DRP is linked to Service, on update of the return visit window, the DRP order entry screens will be displayed, to allow spare parts to be ordered. (See further detail in Call Reporting - Parts Ordering).

2 - Return visit on knowledge required.

3 - Return visit required at end of day - customer.

4 - Return visit required at end of day - engineer.

5 - Return visit required for personal reasons.

6 - Engineer could not gain access to machine.

7 - Call stopped by despatching.

Is The Machine Up Now

Enter one of the following:

0 - No, the machine is not up.

1 - Yes, the machine is up.

Engineer For Return Visit

Defaults to the engineer who carried out the job just completed and reported. The entry can be overridden: enter a valid engineer code.

Keep Existing Job

Enter one of the following:

0 - Create a new job.

1 - Keep the existing job.

Jobs waiting for parts through DRP are set to status 06 automatically.

Parts Must Be Delivered To

If the Return Visit Code is not 1 - Parts, then leave this field as 0.

If the Return Visit Code is 1 - Parts, set this field to 1 - Engineers Van or 2 - Customer. The setting is for memo purposes only.

Urgency Indicator

Leave blank, unless the Return Visit Code is 1 - Parts.

If the Return Visit Code is 1 - Parts, enter a valid urgency code, set up in the Inventory Management Descriptions file option, under major type SPED.



*Note: At **F8=Update**, the system creates the return job, assigned to the engineer selected in the window.*

Credit Call Maintenance

1... **2...** 4/SSS

Use this option to cancel or release calls which have been put into credit hold status.

Concepts

Calls placed by customers who are on credit stop are filtered out of the engineer workload until authorised. The system still allows calls to be logged. The decision to advise the customer of an account problem is yours.

Description

Calls which have been recorded as status 07 - credit hold can be viewed by selecting the status for engineer, branch or team in Engineer Work Allocation.

You can review any of the company's held calls unless credit call maintenance is limited to branch. Branch credit control is set up in System Parameters File Maintenance (screen 4 of 5), if the Credit Control By Branch field is set on. If you need to carry out credit control across the company, leave the field set off.

The credit stop flag is only checked when the call is logged. Jobs already logged will need to be manually released, if an account is cleared of credit hold.

Credit Call Maintenance Initial Screen



Select Credit Call Maintenance.



Tip: Leave all fields blank and press **Enter** to see all orders on credit hold

SS230	Demonstration Company CENTRAL BRANCH	USER BRERETM	30/11/93 17:40:25
-------	---	--------------	----------------------

Credit Call Maintenance

Account No.....?. C03
Location.....? 001

Or

Serial Number.....
Model Number.....?.

Or

Job Number.....

F3 = Exit F4 = Prompt

Fields:

Account No

If entered, this must be an existing customer. Entry of an account code displays account addresses for selection.

Location

If entered with the account code, the calls at Status 7 - Credit Hold will be displayed for the account location.

Serial Number

Enter a serial number to display any jobs for that unit for credit maintenance.

Model Number

Enter a model number to display all models for further selection by serial number and account.

Job Number

Enter an outstanding job number to display that job for credit maintenance.

Credit Call Maintenance Detail Screen



To display this screen enter an account number and a location code on the Credit Call Maintenance Initial screen.



Tip: Select **F13=Fold/Truncate** to expand each single line of detail by a further two lines.

SS230	Demonstration Company CENTRAL BRANCH	USER BRERETM	26/01/94 12:41:42
-------	---	--------------	----------------------

Credit Call Maintenance
Account..... C03 / 001 Jones & Crossland (Northern) Ltd

X Account No/Locn	Site Name	Target	Call Date	Txt	Resp
- C03 / 001	Jones & Crossland (Northern) L	29/11/93	26/11/93		IM
Contact:	MIKE JONES	Tel:		Call Recp:	BRERETM
Serial Number	911001	Model:	WA10	Cat:	WTY Job No. 0501136

1-Cancel	3-Release	5-Text	7-Job Enquiry	9-Ledger Enquiry
F3 = Exit	F12 = Previous	F13 = Fold/Truncate		

Fields:

X

Select. Enter one of the following:

- 1 - Cancel the call. A window is displayed for entering a reason code. Call cancellation reason codes are maintained under parameter type CREA in the Codes/Parameter File Maintenance option.
- 3 - Release the call from credit hold. A window is displayed for entering a reason code. Credit release reason codes are maintained under parameter type RRES in the Codes/Parameter File Maintenance option.
- 5 - Enter job line text. This is also available from the call screen in Engineer Work Allocation.
- 7 - Access the Job Line Detail screen for the job.
- 9 - Access the standard Accounts Receivable enquiry.

Functions:

F13

Fold/Truncate. This expands the screen display for each call from one line to three, to display additional information.

Load Planned Maintenance Jobs



10/SSS

Use this option to convert planned maintenance schedules into actual service jobs, with engineers assigned, for specified service periods in advance.

Take this option after running the Period End Routines option, when contracts have been added during a service period. All planned maintenance visits generated for the selected periods, including the new visits extended by the latest Period End Routine run, are converted to actual jobs.



Note: This procedure requires exclusive use of the company.

Planned maintenance schedules are created within Contract Maintenance, at equipment line level. These schedules are not converted into actual jobs until you take this option.

Description

When the process is complete all scheduled maintenance visits for the selected periods(s) will have been given a job number, assigned an engineer (if possible), and added to the list of outstanding open jobs.

The customer order number from the contract header will only be included in each job if the customer additional service details record has Customer Refs for Contracts field set to 1, indicating that a customer reference must be included on the contract header.

Either single line or multi-line jobs will be generated by this routine, depending on the setting of the company profile field One Machine Per PM Job.

If the field is set to 1, each piece of equipment due to receive a planned maintenance visit in a service period will be assigned its own job number.

If the field is set to 0, one job number will be assigned to any group of pieces of equipment which are all on the same contract, are at the same customer site, and are due to receive a planned maintenance visit in the same service period; each piece of equipment will form a job line within the single job.

Load Planned Maintenance Jobs Screen



Select Load Planned Maintenance Jobs.

SS250P	Demonstration Company CENTRAL BRANCH	USER BRERETM	30/11/93 17:41:20
Load Planned Maintenance Jobs			
Enter a period with the format YYPP in both fields			
From Period:	<u>9346</u>		
Until Period:	<u>9347</u>		
F3=Exit F8=Submit Job			

Fields:

From Period

Enter the service period, in the format YYPP (year then period), from which to begin the load of planned maintenance jobs.

The significant calendar fields and current period are maintained in the Calendar File Control Maintenance option and the Daily Calendar File Maintenance option.

Until Period

This is the service period up to which the load of planned maintenance jobs is to occur. Enter 4 numerics in the format YYPP (year then period).

This cannot be more than six periods ahead of the current period.



Select **F8=Submit Job** to submit a job to perform the load. No report is produced, but the Engineer Work Allocation option will display the results when the batch job is complete.

Automatic Call Assignment



20, 21/SSS

Automatic Call Assignment processes open jobs which have been selected for a team in call logging, and schedules them for an engineer within the team based on skill profile. This will set an estimated time of arrival, within the target time for the call.

Concepts

To assist in the management of work scheduling by automatically selecting the most available engineer to assign to a call based on the workload of the team, and to schedule the call.

Description

Service Management can allocate jobs to engineers automatically. Automatic Call Assignment runs so long as the Service Management sub-system is active.

Automatic Call Assignment is a sleeper program which runs periodically according to the interval set up in the System Parameter File Maintenance option. On each run it selects those jobs which are available for inclusion in call assignment (as defined by their job category), and attempts to assign and schedule them to engineers who are available for automatic call assignment (as defined in the Engineer Master File Maintenance option).

It also takes account of engineer availability from the engineer's absent field, which can be set from within the engineer diary.

Only the number of jobs for the time period defined in the System Parameter File Maintenance option are included in the run.

Jobs which cannot be assigned within target are rejected with the appropriate reason code recorded on the job detail.

Jobs which are successfully scheduled are given an estimated time of arrival (that is, engineer on site), an engineer and a job position in the engineer's work queue.

To schedule calls, a job duration is necessary. This is calculated by adding the standard travel time (defined on the branch), to the job fix time (defined on the model).

Implications

Engineers need to be defined to teams. If a team with the necessary skills cannot be found when a call is logged, the call is allocated to a default team *DF; manual reallocation of the call to an actual team will be necessary.

The Service Management sub-system must have been started and the sub-system library list tailored to take account of:

- The use of consolidated files' libraries in place of IN, OE, SL and GL files' libraries.
- The version of Business Manager in use, for adjusting the four IPG libraries.



Tip: To see the subsystem library list if you are on an AS/400 and are using Version 3 of System 21, enter the command CHGJOB and **F4**. Enter OSLSSP in the Job Description field, and OSLS2P3 in the Library field. Then select **F10=Additional Parameters**, and page down.

Appropriate settings must have been made on the system parameters, model, job category and engineer files, so as not to limit the Automatic Call Assignment operation inadvertently.

Start Auto Call Assignment Screen



Select Start Automatic Call Assignment.

SS840P	Demonstration Company CENTRAL BRANCH	USER BRERETM	30/11/93 17:37:05
Start Auto Call Assignment			
You have requested to submit the Automatic Call Allocation Sleeper program. To proceed and submit the program, press F8 now. If you do not wish to submit the program at this stage, press F3 to return to the menu.			
F3=Exit F8=Submit			

Functions:

F8

Submit. Starts Automatic Call Allocation.

Stop Auto Call Assignment Screen



Select Stop Automatic Call Assignment.

SS840E	Demonstration Company CENTRAL BRANCH	USER BRERETM	20/01/94 13:55:42
Stop Auto Call Assignment			
You have requested to terminate the Automatic Call Allocation Sleeper program. To proceed and end the program, press F8 now. If you do not wish to end the program at this stage, press F3 to return to the menu.			
F3=Exit F8=Terminate			

Functions:

F8

Terminate. Terminate Automatic Call Allocation.

Re-Assign Calls For A Team



22/SSS

This option re-organises the workload for a team on demand, so long as automatic call assignment is inactive.

Description

During normal running of the call assignment sleeper program, the system attempts to shuffle the jobs already loaded, in order to schedule new work within target times.

This option means that all except despatched or appointment jobs can be removed for a selected team, and reloaded, based on the current settings of the engineers' availability. This is useful when engineers are reported as unavailable for work *after* calls have been assigned to them, and a full refresh of the team workload is required.

Implications

Jobs which have an appointment, or have been despatched, will not be re-assigned by this procedure; they will need to be handled manually if re-assignment is required.

The service sub-system must be active.

Re-Assign Calls For A Team Screen

 Select Reassign Calls For A Team.

SS846P	Demonstration Company CENTRAL BRANCH	USER BRERETM	30/11/93 17:37:37
Re-Assign Calls for a Team			
Team.....?: <u>TM1</u>			
F3=Exit F4=Prompt F8=Submit			

Fields:

Team

Enter a team.

All calls for the selected team, except despatched and appointment calls, will be removed from the engineers in the team and reallocated.

 Select **F8=Submit** to submit job.

Reassign Undespached Calls



23/SSS

Use this option to reorganise the workload for all teams on demand, so long as automatic call assignment is inactive.



Note: This is also run as part of the day end procedure.

Description

The option will remove all jobs, except despatched or appointment jobs, for all teams and reload them, based on the current settings of the engineers' availability flags.

This is useful as an end of day option (and is run as part of day end), after engineer availability has been updated for the next working day.

It will also check each engineer's diary for all activities with end dates, such as holidays. If an end date has been passed, the program resets the Absent flag on the engineer master file to blank.

Implications

Jobs which have an appointment, or have been despatched, will not be reassigned by this procedure. They will need to be handled manually if reassignment is required.

Automatic call assignment must be stopped while this reassignment is running.

The service sub-system must be active.

Re-Assign Undespached Calls Screen

 Select Reassign Undespached Calls.

SS845P	Demonstration Company CENTRAL BRANCH	USER BRERETM	30/11/93 17:37:54
--------	---	--------------	----------------------

Re-assign Undespached Calls

You have requested to submit the Automatic Call Allocation Overnight Re-Assignment Routine. To continue and submit the program press F8 now. If you do not wish to submit the program at this stage, press F3 to return to the menu.

F3=Exit F8=Submit

 Press **F8=Submit** to continue with the submission.

Job History Enquiry



30/SSS

Use this option to enquire on the details of both current and completed jobs against a piece of equipment, in order to obtain its service history.



*Note: This enquiry can also be accessed from
Service Call Logging/Maintenance.*

Job History Initial Screen



Select Job History.

The following information is available through this enquiry:

- Job header/line selection.
- Job line details.
- Hours details.
- Parts details.
- Miscellaneous charges details.
- Free format text.

The Job History Initial screen provides a number of different access routes to the detailed enquiry on job details. Whatever you enter, appropriate selection lists are displayed to help you select the correct job.

SS442	Demonstration Company CENTRAL BRANCH	USER BRERETM	26/11/93 12:54:40
Job History Enquiry			
Serial Number.....		Model.....	
Or: Account Number..... C03		Account Address..... 000	
Or: Contract Number.....		Contract Type.....	
Or: Customer Order No....			
Or: Job Number.....			
F3=Exit F4=Prompt			

Fields:

Serial Number

Enter the serial number. The model and serial number combination must exist on the installation file. You can only enter a serial number in conjunction with a valid model number.

Entry of both the model and serial number provides a list of jobs recorded against that machine, and one can be selected for detailed enquiry. The job header screen is then displayed.

Model

Entry of both the model and serial number provides a list of jobs recorded against that machine, and one can be selected for detailed enquiry. The job header screen is then displayed.

If you enter only the model number you see a list of all the equipment of this model at all sites. This list can be lengthy and the method is therefore not recommended.

Account Code

Entry the account code to display account addresses for selection. This must exist on the customer file

Account Address

Account address code must exist for the entered account. The account address code cannot be entered without an account code.

Contract Number

The contract number must exist on the contract file. A list of jobs which exist for the selected contract number will be displayed. No records will be displayed if the contract has expired.

Contract Type

The type must exist on the contract type file. The contract number/type combination must be a valid contract on the application.

Contract type cannot be entered without a contract number.

Customer Order No.

Enter the customer order number you see a list of jobs bearing the entered number, and one may be selected for enquiry. The job header screen is then displayed must be a valid customer order number on at least one job.

Job Number

This must be an existing job which has not yet been completed through technical reporting.

Entering the job number takes you directly to the job header enquiry screen. This displays all the job lines (pieces of equipment included on the job number) and allows selection of a line for further enquiry. For each piece of equipment selected, the job line details enquiry screen is displayed.

Entry will display a list of equipment on this job. If there is only one piece of equipment, the call details screen will be displayed.

This is the job category for the job line.

Fault Code

This is the latest fault code for the job line.

Contact Date

This is the date the job was created.

Contact Time

This is the time the job was created.

Job History Line Selection Screen



To display this screen select a job on the Job History Selection screen.

Use this screen to select a particular job line to display job details. Three extra detail lines per job line record are displayed at **F13=Fold**.

SS443	Z1 - C&T TEST COMPANY	USER GBJBABL	19/07/96
	"BRUM" TRAINING BRANCH		11:39:10
Job History - Line Selection		Job Number	3640
Account Location.... C03 000 Jones and Crossland Ltd			
Customer Order No...		Contact date 28/02/95	
Job Contact.....		Contact time 12:38	
Jb.Cat	Model.....	Serial....	Sts Location of equipment
-	CSR MODEL1	456	99
TEST MODEL 1			
Engineer GB001		Original Engineer	Priority
Fault DED Completely dead			
1=Select			
F3=Exit		F7=Job Story	F12=Previous
F13=Fold/Truncate		F21=Text	
11-02	SE	MW	KS IM II KENB20A PET178S2

Fields:

Customer Order No.

This is the customer order number as previously entered.

Contact Date

This is the date of the first contact for the job.

Job Contact

This is the customer contact name for the job.

Contact Time

Displayed only, cannot be amended. Time of first contact for the job.

Select Option

Must be 1 or blank: 1 selects the job line required for enquiry.

Job Category code

This is the job category which was assigned to each piece of equipment on the job.

Model Code

This is the list of models previously added to the job.

Serial Number

This is the list of serial numbers previously added to the job.

Status

This is the status of the job line is shown.

Equipment Location

The location details are held on the installation details file, for the piece of equipment on the job line.

Functions:

F7

Text for the job.

F13

Fold/truncate for more detail.

F21

Text for the job header.

Job History Line Detail Screen (Option 1)



To display this screen select a job line on the Line Selection screen and press **Enter**.

SS444		Demonstration Company		USER BRERETM	26/11/93
Job Line Detail		CENTRAL BRANCH			12:56:55
Job number...: 501130		Serial number..: 22581038			
Job status...: 99=Complete (Fully Documented)		Model number...: WA10			
Contract type: *NO No user contract		Configuration..:			
Customer.....: Jones and Crossland Ltd.		Account/loc...: C03		000	
Call received: 25/11/93 18:24		Warranty exp...: 6/07/92			
Response time: 12:00 Actual resp.: 18					
Target date...: 29/11/93 11:00					
Job cat.....?: CSR Customer service req					
Contact.....: GORONWY LEWIS					
Machine locn.: DEVELOPMENT LAB : RM 06 GRD FL					
Fault.....?: DED Completely dead					
Machine up...: 1		Team.....: TM1 Team 1			
Maintenance...:		Eng no.....: E0001			
Appoint. date: 0/00/00 0:00		JOHN SMITH			
Order no.....:		Job Duration...: 0:30			
Emergency.....: 0		Estim. arrival: 25/11/93 18:42			
		Despatched....: 25/11/93 18:39			
F3=Exit		F6=Contract		F7=Job Story	
F17=Misc. Costs		F14=Peripherals		F15=Hours	
		F21=Text		F12=Previous	
				F16=Parts Used	

Fields:

All Fields

For details of each field's functionality, please refer to the Service Call Logging Maintenance section (Job Line Detail screen 2 of 2).

In addition, if a machine's record includes meters:

Service Reading (1)

Displays the meter reading entered via technical reporting.

Service Reading (2)

Displays the meter reading entered via technical reporting.

Functions:

F6

Contract and charge matrix.

F7

Job story - text for the whole job.

F14

Peripherals.

F15

Hours (lists reported labour hours for this job line).

F16

Parts used (lists reported parts for this job line).

F17

Misc. costs (lists reported misc. costs for this job line).

F19

Audit. This displays the Job Audit Enquiry Window, which lists any changes made to the job line, with the most recent change at the top of the list.

F20

Assisting engineer is only displayed if an assisting engineer has been assigned to an appointment call.

F21

Text for job line.

F23

Name and address.

Job History Labour Hours Screen (F15)



To display this screen select **F15=Hours** from other Job History Enquiry screens. Two extra detail lines are displayed when you select **F13=Fold/Truncate**.

SS446	Z1 - C&T TEST COMPANY	GBJBAJG	6/03/96
	BIRMINGHAM BRANCH		12:21:26
Job History - Labour Hours			
Job Number.....	3653	Serial Number.....	F6TEST
Model.....	MODEL1	Account Address.....	000
Account Number.....	C03	Contract Type.....	*NO
Contract Number.....			
Visit Date	Job Category.....	Recorded Fault.....	Eng. No
28/04/95	CSR Customer Service Req	ELE Electrical fault	MXBE1
	Report 000365300	Date 28/04/95	Chg% 100.00
	Trav Time 1:00	Corr. Actn ADJ M/c	Mileage
			50
F3=Exit F7=Job Story F12=Previous			
F13=Fold/Truncate F16=Parts Used F17=Misc. Costs F21=Text			
01-02	SA	MW	KS IM II KENB20A PED129S1

Fields:

Job Number

The job number selected previously.

Model

The model for the piece of equipment on the job.

Serial Number

The serial number of the piece of equipment on the job.

Account Code

The account code of the customer for the job.

Account Address

The account address code of the customer for the job.

Contract Number

If the piece of equipment on the job was under contract, the contract number is shown.

Contract Type

Contract type of the contract.

Visit Date

Lists the dates of all visits to this piece of equipment on this job where labour hours were entered.

Job Category

Lists the job category entered on the technical report, and its description retrieved from the job category file, for the visits.

Recorded Fault

Lists the fault code entered on the technical report and its description retrieved from the codes file using type FLTC.

Engineer No.

Lists the engineer who carried out the visit to the piece of equipment on the job.

Hours

Lists the time spent on this piece of equipment on this job.

Functions:

F7

Job story text.

F13

Fold/truncate for more details.

F16

Parts used on job.

F17

Misc. costs on job.

F21

Text for job line.

Job History Parts Used Screen (F16)



To display this screen select **F16=Parts Used** from other Job History Enquiry screens. Two extra detail lines are displayed when you select **F13=Fold/Truncate**.

SS447	Demonstration Company CENTRAL BRANCH	BRERETM	26/11/93 12:59:07
Job History - Parts Used			
Job Number.....	501130	Serial Number.....	22581038
Model.....	WA10	Account Address.....	000
Account Number.....	C03	Contract Type.....	*NO
Contract Number.....			
Visit Date	Part		Eng. No
25/11/93	UM2511832	Variable Speed Controller	E0001
Qty Used	1	Job Category CSR Customer service req	
	Source E0001	Charge Parts% 100.00	Report No 050113000
25/11/93	UM2511061	Vee Belt : 10mm nylon	E0001
Qty Used	2	Job Category CSR Customer service req	
	Source E0001	Charge Parts% 100.00	Report No 050113000
F3=Exit F7=Job Story F12=Previous F13=Fold/Truncate F15=Hours F17=Misc. Costs F21=Text			

Fields:

Job Number

The job number selected previously.

Model Code

The model for the piece of equipment on the job.

Serial Number

The serial number of the piece of equipment on the job.

Account Code

The account code of the customer for the job.

Account Address

The site, or installation address code of the customer for the job.

Contract Number

If the piece of equipment is under a contract, the contract number is displayed.

Contract Type

Contract type of the contract.

Visit Date

Lists the dates of the visits to this piece of equipment on the job.

Part Number

Lists the part numbers, and retrieves the descriptions of the items from the Inventory parts file, used for the job.

Engineer No.

Lists the engineer who carried out the visit to the piece of equipment on the job.

Qty Used

The used quantity of the part

No record is kept of returns

Job Category Code And Desc.

The code for this particular part record, with the description from the job category file.

Source

The engineer's code to indicate the stockroom from which the part was issued. If the part is sourced from another engineer in the same country, Inventory Management transfers stock from this engineer's stockroom to the stockroom of the engineer on the first line of the record and then debits the quantity used.

Charge Parts %

The value between 0 and 100 is the one entered at technical reporting to show how much of the list price has been charged for the part.

Report No

The first seven digits are the job number: these start at 00 and are incremented for each **F9** for the job line, or **F10** on other job lines within the job.

Functions:

F7

Job story text.

F13

Fold/truncate for extra details.

F15

Hours for job line.

F17

Misc. costs for job line.

F21

Text for job line.

Job History Miscellaneous Charges Screen (F17)



To display this screen select **F17=Misc. Costs** from other Job History Enquiry screens. One extra detail line is displayed when you select **F13=Fold/Truncate**.

SS445		Z1 - C&T TEST COMPANY		USER GBJBAJKG		10/07/96	
		BIRMINGHAM BRANCH				13:53:09	
Job History - Misc. Charges							
Job Number.....		3830		Serial Number.....			
Model.....		AA-M01		Account Address.....		000	
Account Number.....		C03		Contract Type.....		B05	
Contract Number.....		T2					
Visit Date	Charge Type.....	Job Category.....			Amount		
4/08/95	HTL Hotel bills	JC1 Job Category : type			562.50		
Vat	Eng JOHN Rep 000383000	Uplift% 12.50	Act.	500.00000	Chg 1		
F3=Exit F7=Job Story F12=Previous							
F13=Fold/Truncate		F15=Hours	F16=Parts Used	F21=Text			
01-02	SS	MW	KS	IM	II	KENB20A	PET178S2

Fields:

Job Number

The job number selected previously.

Model

The model for the piece of equipment on the job.

Serial Number

The serial number of the piece of equipment on the job.

Account Code

The account code of the customer for the job.

Account Address

The account address code of the customer for the job.

Contract Number

If the piece of equipment on the job is under a contract, the contract number is shown.

Contract Type

Contract type of the contract.

Visit Date

Lists the dates of all visits to this piece of equipment on this job where misc. charges were incurred.

Charge Type Code

This is the reason for the charge. The codes are held on the codes/parameter file under parameter type CHGT.

Charge Type Description

Displays the code description from the codes/parameter file. If the file description was overwritten in call reporting, the overwritten detail will be displayed.

Job Category

Lists the job category entered on the technical report and its description retrieved from the job category file.

Amount

Lists the value of the miscellaneous charge entered on the technical report. Whether or not this will be invoiced depends on the charge flag, found on the Fold/Truncate (**F13**) window.

VAT Code

The VAT code applicable to this record.

Engineer Code

The prime engineers code for this record.

Report Number

The first seven digits are the job number and the last two digits are the report number: these start at 00 and are incremented for each **F9** for the job line, or **F10** on other job lines within the job.

Uplift %

The relationship between cost and the invoiced charge for the miscellaneous record.

Act.

The actual cost of the miscellaneous expenditure

Chg

0 means non-charge, 1 means charge.

Functions:**F7**

Job story text.

F13

Fold/truncate for extra details.

F15

Hours for job line.

F16

Parts used for job line.

F21

Text for job line.

Escalation Enquiry



31/SSS

Use this option to enquire on outstanding service jobs which are close to, or have exceeded, their response time guarantee.

You can use this enquiry to monitor and take action on jobs approaching a critical status.

Concepts

Service Management alerts you to any service jobs which are approaching their designated response time and are still outstanding. Job escalation runs while the Service Management sub-system is active.

In job escalation enquiry, each job is stamped with a target response date and time.

For unscheduled (call out) jobs, the target date and time is calculated as the date and time the call was first logged, (or the appointment date and time if one is entered), plus the response hours from the call logging screen (defaulted from the contract covering the piece of equipment), taking into account the service window as defined on the company profile, and the working and non-working days as defined on the daily calendar file.

For scheduled (planned maintenance) jobs, the target date is set to the last working day of the service period in which the visit is due, and the target time is set to the start time of the service window.

A continuous batch job runs within the application, which regularly recalculates the escalation step of all jobs which are within the escalation time fence and have a status defined as being eligible for escalation. The step is calculated as:

$$\frac{\text{target time} - \text{current time}}{\text{reporting interval for escalation}}$$

Rounded up to the nearest integer if necessary. This means that the escalation step will move from high to low value as a job moves towards its target time. Step 00 means that the job has either reached or gone beyond its target time.



Note: The application assumes a seven day working week. If less than this is actually worked, the system still escalates Monday's jobs on Sunday, not on the preceding Friday.

Escalation Enquiry Initial Screen



Select Job Escalation Enquiry.

```

SS852          Demonstration Company          USER BRERETM    26/11/93
                  CENTRAL BRANCH                               13:00:11

Escalation Enquiry

Jobs Assigned To Engineer.....?. E0001
OR
Jobs For A Team.....?.     
OR
All Jobs For The Branch (1)..... 0

Scheduled PM (1) or Callout (2)..... (Leave blank for all)
Contracted Responses Only? (1/0)..... 0
Escalation Step.....      (Leave blank for all)

Status Range..... 00 to 03

00=Open          01=Assigned          02=Scheduled          03=Despatched
04=Work in Progres 05=Telephone          06=Parts              07=Credit Hold
08=Complete (Not D 09=Partial Report    10=SOP Job

F3=Exit  F4=Prompt
  
```

Fields:

Jobs Assigned To Engineer

Enter an engineer or a team number, or All Jobs For The Branch must be set to 1.

If you enter an engineer, a list of all job lines currently assigned to this engineer, irrespective of the job line branch, which satisfy the other selection criteria, will be displayed.

Jobs For A Team

Enter a team or an engineer number, or All Jobs For The Branch must be set to 1.

If you enter a team, a list of all job lines currently assigned to this team, irrespective of the job line branch, which satisfy the other selection criteria, will be displayed.

All Jobs For The Branch

Enter one of the following

0 - If an engineer or team number is entered.

1 - If an engineer or team number is not entered.

If this is set to 1, a list of all job lines belonging to the current branch, which satisfy the other selection criteria, will be displayed.

Scheduled PM Or Callout Or Both

Must be 1, 2 or blank:

If 1 is entered, only planned maintenance job lines, assuming they satisfy the other selection criteria, will be displayed.

If 2 is entered, only breakdown job lines, assuming they satisfy the other selection criteria, will be displayed.

If the field is left blank, all job lines, irrespective of whether they are breakdown calls or planned maintenance jobs, will be displayed, assuming they satisfy the other selection criteria.

Contracted Responses Only

Enter one of the following:

0 - All jobs, irrespective of whether they are covered by contract or not, are selected.

1 - Only jobs for pieces of equipment covered by contract, and therefore having a contracted response time, are selected.

Escalation Step

The default is 00. Valid entries are between 00 and 98, or blank.

If set to a specific number, only job lines with this escalation step will be displayed.

If set to blank, any job line with any escalation step will be displayed, depending on the other selection criteria.

Status Range

The status must be between 00 and 09:

00 - Open job lines.

01 - Assigned jobs.

02 - Scheduled jobs.

03 - Despatched jobs.

04 - Work in progress.

05 - Telephone call required.

06 - Awaiting parts.

07 - Credit hold.

08 - Completed, but not documented.

09 - Partial report - assisting engineer.

10 - Not supported in the current system.

All job lines with status which fall within the range, assuming they satisfy the other selection criteria, will be displayed.



Press **Enter** to display the Job Escalation Enquiry Detail screen.

Job Escalation Enquiry Detail Screen



To display this screen press Enter on the Job Escalation Enquiry Initial screen.



Tip: Select **F13=Fold** to expand the single line of detail by a further two lines.

SS852	Demonstration Company	USER BRERETM	26/11/93
	CENTRAL BRANCH		8:01:20
Escalation Enquiry			
Engineer	E0001 JOHN SMITH	Radio Page No.:	
Last Contact	26/11/93 7:45	Location	ON WAY TO JOB 501131
n	Account name	Pcde Model	Flt Cat Job St Target Stp
-	Jones & Crossland (Northe	PRI WA10	ELE CSR 501131 DES 8:00 00
	Unit 5	Qty: 1	Target Date 26/11/93
	Fault Electrical fault	ARCING BEHIND FILTER	Service Period 9311
-	Jones & Crossland (Northe	PRI WA10	NSY WTY 501132 SCH 11:00 03
	Unit 5	W930001	Target Date 26/11/93
	Fault Noisy	SECONDARY DRIVE RATTL	Service Period 9311
+			
1=Job Details			
F3=Exit F5=Refresh F12=Previous F13=Fold/Truncate F21=Text			

Fields:

Engineer Number or Team Number

Selected on the previous screen.

N

Select. Enter 1 to view the job line in more detail.

Account name

Retrieved from the customer file using the account or location codes from the job.

Postcode 1

The first four alphanumeric of the customer's postcode, retrieved from the customer file using the account or location codes from the job.

Model

This is the model code of the piece of equipment on the job.

Fault

This is the fault code entered against this piece of equipment when the job was logged.

Job Category code

This is the job category entered against this piece of equipment when the job was logged.

Job Number

This is the number which has been allocated by the application.

Status

Displayed only, cannot be amended. This is the current status of the job for example, open, allocated, scheduled, despatched, completed and so on.

Target Time

This is the calculated target time for the piece of equipment on the job.

It is calculated by adding the response hours for the call to the original time of contact. This takes into account the working hours in the day, from the service window, and the working days in a period, from the daily calendar file.

If an appointment date and time were entered when the job was logged, these are used instead of the above.

Escalation Step

This is the current escalation step for the piece of equipment on the job.

98 is the step when the call is logged. The call will stay at this until the Report Escalation Before Response Due time is reached (set up in Escalation Parameters maintenance). The call's report step is then updated to the highest step value listed on the escalation parameters maintenance screen. The report steps decrease, as the escalation steps are reached.

Site Address Line 1

Retrieved from the customer file using the account or location codes from the job.

Serial Number Or Quantity

This is the serial number of the piece of equipment on the job; if there is no serial number, the quantity of the model included on the job line is displayed.

Target Date

This is the calculated target date for the piece of equipment on the job.

It is calculated by adding the response hours for the call to the original date and time of contact. This takes into account the working hours in the day, from the service window, and the working days in a period, from the daily calendar file.

If an appointment date and time were entered when the job was logged, these are used instead of the above.

Fault Code: Description 1

Retrieved from the codes file: Parameter type FLTC, or as overwritten at call logging.

Fault Code: Description 2

The first 21 alphanumeric characters of any user defined fault description, entered on the Job Line Detail screen in call logging.

Service Period

This is the service period in which the job was created or the visit was due.



Note: If All Jobs for the Branch was selected on the Initial screen, the engineer number, name, radio page no., last contact date and time and location are not shown; instead, a heading of All Jobs For Branch is displayed.

Functions:

F13

Fold/truncate - for extra detail.

F21

Text for engineer.



Press **Enter** to display the Job Line Detail screen.

Job Line Detail Screen (Option 1)



To display this screen select a job line on the Job Escalation Enquiry screen and press **Enter**.

SS444	Demonstration Company	USER BRERETM	26/11/93
Job Line Detail	CENTRAL BRANCH		13:48:34
Job number....: 501131		Serial number..:	
Job status....: 03=Despatched		Model number...: WA10	
Contract type: *NO No user contract		Configuration..:	
Customer.....: Jones & Crossland (Northern) L		Account/Loc....: C03 001	
Call received: 25/11/93 19:22		Warranty exp...: 16/08/93	
Response time: 12:00 Actual resp.:			
Target date...: 26/11/93 8:00		Travel/Labour Chargeable	
Job cat.....?: CSR Customer service req		Parts Chargeable	
Contact.....: BILL DEAN			
Machine locn.: DEVELOPMENT DEPT : 2 WEST			
Fault.....?: ELE Electrical fault			
Machine up....: 1		Team.....: TM1 Team 1	
Maintenance...:		Eng no.....: E0001	
Appoint. date: 26/11/93 8:00		JOHN SMITH	
Order no.....: 24792811		Job Duration...: 0:30	
Emergency.....: 1		Estim. arrival: 26/11/93 8:00	
		Despatched....: 25/11/93 19:35	
F3=Exit	F6=Contract	F7=Job Story	F12=Previous
F17=Misc. Costs	F14=Peripherals	F15=Hours	F16=Parts Used
	F21=Text	F23=Name and Address	

Fields:

All Fields

For details of each field's functionality, please refer to the Service Call Logging Maintenance section (Job Line Detail screen 2 of 2).

Functions:

F6

Contract and charge matrix.

F7

Job story. Text for the whole job.

F14

Peripherals.

F15

Hours (lists reported labour hours for this job line).

F16

Parts used (lists reported parts for this job line).

F17

Misc. costs (lists reported miscellaneous costs for this job line).

F21

Text for job line.

F23

Name and address.

Branch Workload Enquiry



32/SSS

Use this option to view the projected workload for the next 16 working hours based on the duration of jobs in the system and the available engineers' working hours.

Description

The workload program displays the workload in two-hour time slots, starting from the current time. Only working hours are displayed, as derived from the service window.

The calculation is based on the total job duration of calls, with a target time falling within the two-hour slot, divided by the total available engineer hours for the slot. The result is multiplied by 100, to express the load as a percentage.

Implications

No allowance is made within the loading for travel time. Jobs are included in two-hour slots, based on their target time; no account is taken of job duration which falls outside that two-hour slot.

Branch Workload Enquiry Detail Screen



Select Branch Workload Enquiry.

SS245	Demonstration Company CENTRAL BRANCH				USER BRERETM	9/04/94 22:57:40		
Branch Workload Enquiry								
	8:00 9:59	10:00 11:59	12:00 13:59	14:00 15:59	16:00 18:00	8:00 9:59	10:00 11:59	12:00 13:59
District CG								
F3=Exit F5=Refresh								

Branch Workload Enquiry



Note: All blocks are intended for display in colour.

The purpose of the screen is to display the loading on a district (that is, a team, or group of teams). The two-hour periods show the comparison between the available engineer time and the time already allocated to jobs, with the result expressed as the colour-coded percentage load.

The colour of the block represents the percentage load as follows:

- Red - Flashing >125%
- Red 110 - 125%
- Pink 100 - 109%
- Yellow 90 - 99%
- Green 75 - 89%
- Blue 50 - 74%
- White <50%

Outstanding DRP Order Enquiry



33/SSS

Use this option to enquire on outstanding DRP orders and their associated Service Management jobs.

Only DRP orders which have been raised in association with a Service Management job are visible within this enquiry.

Outstanding DRP Order Enquiry Screen



Take Outstanding DRP Order Enquiry.

SS656	Z1 - Demonstration Company	USER GBJBANB1	25/02/98 15:35:07
Outstanding DRP Order Enquiry			
DRP Order Number.....: _____			
Or	Job Number.....: _____		
Or	Engineer's Stockroom..: _____		
Or	Engineer Number.....?: ? _____		
F3=Exit F4=Prompt			

Fields:

DRP Order Number

Enter the DRP order you wish to enquire on. Leave the other three fields blank.

Leave all four fields blank to see a list of all outstanding DRP orders for the current company and branch.

Job Number

Enter the job which is associated with the DRP order you wish to enquire on. Leave the other three fields blank.

Leave all four fields blank to see a list of all outstanding DRP orders for the current company and branch.

Engineer's Stockroom

Enter the stockroom which is associated with the DRP order you wish to enquire on. Leave the other three fields blank.

Leave all four fields blank to see a list of all outstanding DRP orders for the current company and branch.

Engineer Number

Enter the engineer associated with the DRP order you wish to enquire on. Leave the other three fields blank.

Leave all four fields blank to see a list of all outstanding DRP orders for the current company and branch.



When you have entered your selection, press **Enter**.

If you did not specify an order or job, then you will see the Outstanding Parts Orders Enquiry screen 1.

If you selected an order or a job, then you will see the Outstanding Parts Orders Enquiry screen 2.

Outstanding Parts Orders Enquiry Screen 1



To display this screen do not specify an order or job on the Outstanding DRP Order Enquiry screen and press **Enter**.

This screen lists the outstanding orders for the stockroom, engineer or current company and branch, depending on the selection you made on the Outstanding DRP Order Enquiry screen.

Fields:

N

Selection field. Enter one of the following:

1 - See the job detail for this order. This takes you into the Job Line Detail screen.

2 - See the order detail for this order. This takes you to the Outstanding Parts Orders Enquiry screen 2.



Press **Enter** when you have made your selection. If you enter 2 against an order you will see the Outstanding Parts Orders Enquiry screen 2.

Outstanding Parts Orders Enquiry Screen 2



To display this screen specify an order or job on the Outstanding DRP Order Enquiry screen, and press **Enter**.

Or: Enter 2 against an order on the Outstanding Parts Orders Enquiry screen 1.

All the items for the order are listed, with the item description, quantity ordered and quantity despatched.

Engineer Messages



40/SSS

Use this option to send messages, or review messages sent, between engineers and teams within a service branch. You can send messages to any engineer or team in any branch.

The function allows messages to be entered, stored and retrieved for display, for engineers and teams of engineers.

Description

If you enter an engineer or team you can create a three line (195 character) message, together with the sender's code (for example, engineer number). The message expiry date is calculated by the system: it adds the current date and the Default expiry days for messages, set up on the System Parameters file (see screen 4 of 5).

These engineer and team messages are also displayed in Engineer Work Allocation, before the job list is displayed for the selected engineer or team. However, Branch messages can only be reviewed using this option.

Implications

The message sender needs to be defined on the system as an engineer.

You can use the same engineer or team as both the sender and the recipient.

Engineer Messages Initial Screen



Select Engineer Messages.

```

SS122                Demonstration Company          USER BRERETM          1/12/93
                      CENTRAL BRANCH                10:17:12

Engineer Message Maintenance

Message type to maintain..... 1      1=Engineer
                                         2=Team
                                         3=All

If types 1 or 2:

    Engineer.....?.. E0001      (Leave blank for all)
    Team.....?..           (Leave blank for all)

Leave selection fields blank to list all outstanding messages.

F3=Exit   F4=Prompt   F10=Message entry

```

Fields:

Message Type To Maintain

Enter one of the following:

- 1 - Engineer.
- 2 - Team.
- 3 - All messages.

Engineer

Enter the engineer that the message is for.

Team

Enter the team that the message is for.

Functions:

F10

Display the message entry screen.

Send an Engineer Message Screen (F10)



To display this screen select **F10=Message Entry** from the Engineer Messages Initial screen.

SS121	Demonstration Company CENTRAL BRANCH	USER BRERETM	1/12/93 10:21:11
Send an Engineer Message			
Message from..?..	<u>E0002</u>	PETER JONES	
Expiry date.....	<u>4/12/93</u>		
Message..	<u>An engineer message Peter</u>		
Send to (specify ONE of the following):			
Engineer....?..	<u>E0001</u>	JOHN SMITH	
Team.....?..	<u> </u>		
All engineers..	<u>0</u>	(0=No,1=Yes)	
F3=Exit F4=Prompt F8=Send message F12=Previous			

Fields:

Message From

You must define the originator of a message on the system as an engineer.
Enter an engineer code.

Expiry Date

The message expiry date is system-calculated by adding the current system date and the Default expiry days for messages (set by System Parameters file maintenance, screen 4 of 5).

The displayed date may be changed, if required.

Message

Enter the message detail, in up to three lines of 65 alphanumerics each.

Send To:

Enter one of the following:

Engineer

Enter an engineer to whom the message will be transmitted.

Team

Enter a team code to whom the message will be transmitted.

All Engineers

Enter 1 to transmit the message to all engineers defined to the branch.

Machine Messages



41/SSS

Use this option to provide a facility to store messages for machines, on an individual or generic basis, for later retrieval when a job is logged or despatched.

Description

You can specify a message type which determines whether it will be recorded for a specified model and serial number, a serial number range, a model type, or a model sub-group.

If the model and serial fields are left blank, you can retrieve outstanding messages.

If you enter model or serial information you can create a three line (195 character) message, together with the sender's code (for example,; engineer number). The message expiry date will assume an indefinite default value of 99/99/99, but can be amended to any future date as required.



```

SS125                      Demonstration Company          USER BRERETM          1/12/93
                           CENTRAL BRANCH                11:19:36

Machine Message Maintenance

Message type to maintain..... 3      1=Model / Serial
                                         2=Model / Serial number range
                                         3=Model
                                         4=Model Sub-group

Specify which to list, or leave blank for all:

    Model .....?.. WA10 _____
and/or
    Serial .....?.. _____ to _____

    Division / Model Group / Sub-group....?.. __ / __ / __

Leave selection fields blank to list all outstanding messages.

-----
F3=Exit   F4=Prompt   F10=Message entry

```

5-115

In this case you must leave the model and serial number fields blank.

Model Group Code

If the machine message is for a product division and model group, enter a valid two alphanumeric division code and a valid three alphanumeric model group code; or, prompt for the model group code selection window and enter 1 against the model group code to select it from there.

In this case you must leave the model and serial number fields blank.

Model Sub-Group Code

If the machine message is for a product division, model group and model sub-group, enter a valid two alphanumeric division code, a valid three alphanumeric model group code and a valid three alphanumeric model sub-group code; or, prompt for the model sub-group code selection window and enter 1 against the model group code to select it from there.

In this case you must leave the model and serial number fields blank.

Functions:

F10

Display the message entry screen.

Send A Machine Message Screen (F10)



To display this screen select **F10=Message Entry** on the Send A Machine Message Initial screen.

```

SS124          Demonstration Company          USER BRERETM      1/12/93
                  CENTRAL BRANCH                               11:16:44

Send a Machine Message

Message from.... _____

Expiry date..... 99/99/99

Message.. All model WA10 manufactured after 10/09/93 to be checked for
          incorrect fuse rating:
          F1 may be 5A quick blow   Correct rating 5A delay

Send to:

  Model.....?.. WA10
  and/or
  Serial.....?.. _____ to _____

Or
  Division / Model group / Sub-group...?.. __ / __ / __

F3=Exit  F4=Prompt  F8=Send message  F12=Previous
  
```

Fields:

Message from

Enter up to 10 alphanumerics, to identify the sender by name, by job title or by user defined code.

Machine Message Expiry Date

The default (99/99/99) is for a machine message which will not expire, nor be subject to expiry by the default number of days for message expiry set on the System Parameters maintenance screen 4 of 5.

If the machine message is to expire, enter a valid expiry date (DDMMYY).

Message Detail

Enter a maximum of three 65 character lines, of free form detail.

Send To:

Enter one of the following:

Model

The model code defaults from the Initial screen.

Prompt for the model code selection window if a different code is required, or enter a valid model code of up to 15 alphanumerics.

Serial Number From

The Serial Number From defaults from the Initial screen.

Enter ? and **F4=Prompt** to display the Equipment by Model screen and select a different serial number, if required; or, enter a valid serial number for the model, of up to 15 alphanumerics.



*Note: If the message is for a machine with no serial number, enter the model number and field exit through the serial number field before taking **F8=Send Message**.*

Serial Number To

The Serial Number To may be blank, but if entered, must be greater than the Serial Number From.

Enter ? and **F4=Prompt** to display the Equipment by Model screen and select a valid serial number, if required; or, enter a valid serial number for the model, of up to 15 alphanumerics.

Division Code

If the machine message is for a product division, enter a valid two alphanumeric code, or prompt for the division code selection window and enter 1 against the model group code to select it from there..

Model and serial number fields must be blank.

Model Group Code

If the machine message is for a product division and model group, enter a valid two alphanumeric division code and a valid three alphanumeric model group code; or, prompt for the model group code selection window and enter 1 against the model group code to select it from there.

Model and serial number fields must be blank.

Model Sub-Group Code

If the machine message is for a product division, model group and model sub-group, enter a valid two alphanumeric division code, a valid three alphanumeric model group code and a valid three alphanumeric model sub-group code; or, prompt for the model sub-group code selection window and enter 1 against the model group code to select it from there.

Model and serial number fields must be blank.