

-
-
-
-
-

Chapter 1

Maintenance



Transport Centre



1/TPM

You can maintain a number of control flags per transport centre. These flags condition the processing of transport requirements and loads.

You use this to set up new transport centres and maintain existing centres. Transport centres are delivery depots, where you plan, pick and despatch transport loads.

Maintain Transport Centre Selection Screen

 To display the Maintain Transport Centre Selection screen, select Transport Centre.

You use this screen to select the transport centre you want to maintain.

TP001A	Z1 - Demonstration Company	User SP1	20/02/95 16:20:38
Maintain Transport Centre			
Transport centre?.. <u>TC01</u>			
F3=Exit F4=Prompt			

Fields:

Transport Centre

To add a new transport centre, enter a four character code.

To maintain a transport centre, select, or enter, an existing code.

Planners normally operate within a default transport centre, but they can change to any authorised centre.

 Press **Enter** to display the Transport Centre Detail Screen 1.

Transport Centre Detail Screen 1



To display this screen, on the Maintain Transport Centre Selection Screen, enter a code and press **Enter**.

You use this screen to enter the basic details for the transport centre.

TP001B	Z1 - Demonstration Company	User SP1	20/02/95 16:20:46
--------	----------------------------	----------	----------------------

Maintain Transport Centre

Transport centre..... TC01

Centre name Demonstration Transport Centre

Load number prefix A

Load number range 1 599999

Manual order prefix..... M

Manual order range..... 600000 999999

Default freight payment method?... 01 Pay driver cash

Bill print conversion factor..... 1.00000

Default rating conversion factor . 1.00000

Default capacity on screens ...?... 1 Weight

Add orders immediately to load 0 (0=No,1=Yes)

Allow load to be released before goods ready for loading . 1 (0=No,1=Yes)

Print Bol/Load sheets immediately after load released 1 (0=No,1=Yes)

Bypass confirm load despatch 0 (0=No,1=Yes)

F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous
F13=Stockroom

Fields:

Centre Name

Enter a transport centre name.

Load Number Prefix

Enter a character. This is the load reference prefix and precedes all automatically generated load references.

Load Number Range

Enter the range of numbers to use when automatically generating load numbers. The load numbers increment by 1, starting at the lower limit, up to and including the upper limit. If you reach the upper limit, the system reassigns transport load references from the lower limit.

Manual Order Prefix

Enter a character. This precedes all automatically generated order numbers. You add manual orders using Manual Requirement Creation.

Manual Order Range

Enter the range used to automatically generate manual order numbers.

Default Freight Payment Method

Enter the freight payment method to use as a default for the transport centre. You can define freight payment methods using the Inventory Management descriptions file major type TPPM. The payment methods print on the bill of lading.

Bill Print Conversion Factor

Enter the conversion factor for the weight capacities. Before printing the gross weight of the load on the bill of lading, Transport Planning divides it by this factor.

Default Rating Conversion Factor

Enter the conversion factor for the rating of loads. The system divides the load weight, volume or number of containers by this factor before accessing a rate for a given quantity.

Default Capacity on Screens

Enter one of the following to specify how you define the capacity for orders, drops and loads:

- 1 - Weight
- 2 - Volume
- 3 - Number of containers or packs

You can define capacity types using the Inventory descriptions file major type TPDC.

Add Orders Immediately To Load

Enter one of the following:

- 1 - To add the order to a load with sufficient capacity, the same route, ship date, carrier and vehicle type. If the system cannot find a load with the right carrier, it adds the order to a load with a different carrier.
- 0 - To make the system suggest a suitable load number, but not automatically add the order to the load.

Allow Load To Be Released Before Goods Ready For Loading

Enter one of the following:

- 1 - To allow you to release a load before confirming all of the despatch notes.
- 0 - To not allow early release.

Print Bol/Loadsheets Immediately After Load Released

Enter one of the following:

- 1 - To print load sheets and Bill of Lading documentation when you release loads.
- 0 - To print the documentation in batch via the print loads option.

Bypass Confirm Load Despatch

Enter one of the following:

- 1 - To automatically flag loads, as waiting to be dropped to history, when you print or after you post transport charge payments.
- 0 - To specify you have to confirm despatch.

The confirm load despatch transaction date, and time, stamps the load so you can view whether the load has left the premises.

Functions:

F13

Stockroom. Use this function to allocate and deallocate stockrooms to the transport centre.



To display the Transport Centre Details Screen 2, press **Enter**.



*Note: If you are maintaining a Transport Centre, you can select **F8=Update** to save your changes and return to the Maintain Transport Centre Selection Screen.*

Transport Centre Stockrooms Screen (F13)



To access this screen, on the Transport Centre
Detail Screen 1, select **F13=Stockrooms**.

You use this screen to allocate and deallocate stockrooms to the transport
centre. Transport centres can plan the transport on behalf of multiple sales
companies and/or multiple stockrooms.

TP002	Z1 - Demonstration Company	User SP1	20/02/95 16:22:23
Maintain Transport Centre Stockrooms			
Transport centre TC01 Demonstration Transport Centre			
Sel	Sales company	Stockroom	
-	Z1 Demonstration Company	01 Central Stockroom	
4=Delete			
F3=Exit	F9=Add	F12=Previous	F15=All stockrooms



*Note: You can only use a sales company and
stockroom combination for one transport centre.
This relationship determines where to add the
requirements.*

Fields:

Sel

Enter 4 to delete the sales company and stockroom combination.

Functions:

F9

Add. Use this function to add a sales company and stockroom combination.

F15

All stockrooms. Use this function to assign all Inventory stockrooms within all
sales companies to this transport centre.



To return to the Transport Centre Details Screen
1, select **F3=Exit**.

Transport Centre Stockroom Addition Window (F9)



To display this window, on the Transport Centre Stockroom Screen, select **F9=Add**.

You use this screen to allocate a stockroom to a transport centre.

TP002	Z1 - Demonstration Company	User SP1	24/03/95 16:46:22
Maintain Transport Centre Stockrooms			
Transport centre TC01 Demonstration Transport Centre			
Sel	Sales company	Stockroom	
-	Z1 Demonstration Company	01 Central Stockroom	
Addition			
Sales company Z1 Demonstration Company			
Stockroom ? 02 Northern RDC Stockroom			
F4=Prompt F8=Update F12=Previous			

Fields:

Sales Company

Enter the sales company code.

Stockroom

Enter the stockroom code associated with the allocation and despatch of sales items within the sales company defined.



To add the stockroom, sales company combination select **F8=Update**. Then select **F12=Previous** to return to the Transport Centre Detail Screen 1.

Transport Centre Detail Screen 2

 To display this screen, on the Transport Centre Detail Screen 1, press **Enter**.

You use this screen to enter more advanced transport centre details.

TP001B	Z1 - Demonstration Company	User SP1	20/02/95 16:20:46
Maintain Transport Centre			
Transport centre		TC01 Demonstration Transport Centre	
Default commodity code		?	
Default VAT code		001 17.50 %	
Temperatures		_ _	
Fixed temperature message		_____	
Temperature range message		_____	
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			

Fields:

Default Commodity Code

Enter the commodity code to use as a default when creating pending loads. This prints on the Bills of Lading. You can define commodity codes in the Inventory descriptions file under major type TPCC.

Default VAT Code

Enter the VAT code. You must have defined this to the General Ledger, if you have defined a General Ledger company to the transport company profile, or defined to the Inventory Descriptions file under a major type of VAT.

Temperature

Enter the temperature for the shipment of temperature dependent goods. This is the default for created loads.

If you enter one temperature, the fixed temperature message prints on the bill of lading documentation.

If you enter two temperatures, the temperature range message prints on the bill of lading documentation.

Fixed Temperature Message

Enter the fixed temperature message. This prints on the bill of lading documentation, if you only enter one temperature against a load header.

Temperature Range Message

Enter the temperature range message. This prints on the bill of lading documentation, along with both temperatures, if you enter two temperatures against a load header.



To save the information and return to the Maintain Transport Centre Selection Screen, select **F8=Update**.

Transport Nodes

1... **2...** 2/TPM

You use this option to define nodes for the transport centre currently in use.

A node is a geographical location where one or more routes start or end. This is typically a company distribution centre (DC), but can be a location used by the carrier as a depot, or a location to break down bulk loads.

Transport Node Selection Screen



Select Transport Node.

You use this screen to select the transport node you want to maintain, or enter the code for a new transport node.

TP027A	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		11:10:20
Maintain Transport Nodes			
Transport node.....?.. <u>BHAM</u>			
F3=Exit F4=Prompt			

Fields:

Transport Node

Enter a new or existing transport node or geographical location.



To display the Transport Node Detail Screen,
press **Enter**.

Transport Node Detail Screen

 To display this screen, on the Transport Node Selection Screen, enter a Transport Node and press **Enter**.

Use this screen to enter the details for the transport node.

TP027B

Z1 - Demonstration Company
Demonstration Transport Centre

User SP1

8/03/95
11:10:44

Maintain Transport Nodes

Transport node

..... BHAM

Name

..... Birmingham

County

.....?.. WMID West Midlands

F3=Exit

F4=Prompt

F8=Update

F11=Delete

F12=Previous

Fields:

Name

Enter the name of the transport node.

County

Enter the county or state for the transport node. You can define counties in the Inventory Descriptions file using major type TPCY.

 To add the transport node and return to the previous screen, select **F8=Update**.

Vehicle Types



3/TPM

Use this function to define vehicle types and their associated capacities (gross weight and volume).

When you assign a vehicle type to a load, Transport Planning keeps a check on its current load size, and makes sure that it does not exceed the maximum values assigned here.



Note: If you do not set up a Vehicle Type, Transport Planning cannot check the capacity when assigning loads automatically.

Maintain Vehicle Types Selection Screen

 Select Vehicle Type.

Use this screen to enter the code of the vehicle type that you wish to maintain or create.

TP012A	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		11:15:50
Maintain Vehicle Types			
Vehicle type?.. <u>16I</u>			
F3=Exit F4=Prompt			

Fields:

Vehicle Type

Enter a code for a new or existing type of vehicle.

 To display the Vehicle Type Detail Screen, press **Enter**.

Vehicle Type Detail Screen



To display this screen, on the Vehicle Type Selection Screen, enter a code and press **Enter**.

Use this screen to enter or amend the details for the selected vehicle type. Transport Planning uses the capacities you enter when you build a load and if you exceed the capacities, issues an overridable warning.

TP012B	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		11:16:21
Maintain Vehicle Types			
Vehicle type 16T			
Description 16 Tonne Rigid			
Maximum weight capacity ..		10500.0	
Maximum volume capacity ..		12000.0	
F3=Exit F8=Update F11=Delete F12=Previous			

Fields:

Description

Enter a description for the vehicle type.

Weight Capacity

Enter the maximum gross weight capacity for the vehicle type.

Volume Capacity

Enter the maximum volume capacity for the vehicle type.



To save the information and return to the previous screen, select **F8=Update**.

Carrier Rate

1... **2...** 4/TPM

Use this function to maintain the tables used to automatically rate loads, or calculate carrier freight charges.

You should set up a rate code for each set of charges applied to a group of carriers, an individual carrier, or an individual route covered by the carrier. You assign the rates to the carrier using the Carrier Maintenance option. The rate code and description should clearly describe when to apply these charges.

Once you have rated a load, you can transfer the charge to the General Ledger (via AFI) as an accrued cost (for more information, see Advanced Financial Integrator Product Information). Also, you use the calculated load charge as the basis, when you match the carrier's invoice. (See Processing for details on authorising carrier payments.)

Carrier Rate Selection Screen



Select Carrier Rate.

Use this screen to enter the carrier rate selection details.

TP015A	Maintain carrier rates	Date: 8/03/95 Time: 11:16:47
Maintain Carrier Rates		
Rate method?.. <u>01</u>		
Rate code?.. <u>C01STD</u>		
Effective date?.. <u>8/03/95</u>		
F3=Exit F4=Prompt		

Fields:

Rate Method

Enter one of the following:

01 - To calculate charges, based on the loads gross weight, volume or number of containers, using a rating table.

02 - To calculate charges for each drop, based on the gross weight, volume or number of containers, using a rating table.

03 - To calculate charges using a fixed rate, based on the gross weight, volume or number of containers dropped into each area.

04 - To calculate charges, based on the gross weight, volume or number of containers for each area, using a rating table.

Rate Code

Enter a code to identify this rate.

Date From

Enter the date from which the rating information is effective. You can set up multiple dates, so you can add new rates before they come into effect.



To display the Carrier Rate Details Screen, press **Enter**.

Carrier Rate Details Screen (Option 1 and 2)



To display this screen, on the Carrier Rate Selection Screen, enter a Rate Method of 01 or 02 and press **Enter**.

Use this screen to enter the information required to rate loads by:

- Total gross capacity - if rate method is 01.
- By drop capacity - if rate method is 02.

TP015B	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		11:17:08
Maintain Carrier Rates			
Rate method	01 Load and rate table		
Rate code	C01STD		
Effective date	8/03/95		
Description	BMZ Standard Rate		
Capacity type	Weight		
VAT code	001		
Drop charge rate	3.00		
Minimum drop charge	10.00		
Maximum drop charge	100.00		
Surcharge %	2.00		
Surcharge value	.00		
Minimum load charge	25.00		
Number of free drops	1		
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F13=Charge structure F14=Volume F15=Containers F16=Weight			

Fields:

Description

Enter the description for the rating information. For example, you could enter the carrier and route to which this applies.

Capacity Type

If you are defining a new rate table, enter the default capacity. To set it to volume, select **F14=Volume**, to set it to containers, select **F15=Containers**, or to set it to weight, select **F16=Weight**.

If you are maintaining a rate table, this field is for information only.

VAT Code

Enter the VAT code used to calculate the VAT on load charges. The system applies the VAT when you transfer the invoice to Accounts Payable.

Drop Charge Rate

Enter the fixed charge for each drop on a load.

Minimum Drop Charge

Enter the minimum charge for each drop on a load. You do not need this for Rate Method 01.

Maximum Drop Charge

Enter the maximum charge for each drop on a load. You do not need this for Rate Method 01.

Surcharge %

Enter a percentage to apply to load or area charges to accommodate unforeseen extras, for example, government fuel tax charges.

Surcharge Value

Enter a value to apply to load or area charges to accommodate unforeseen extras, for example, government fuel tax charges.



Note: You can enter either a surcharge percentage or value, but not both.

Minimum Load Charge

Enter the minimum charge for a load.

Number Of Free Drops

Enter the number of free drops when calculating load charges.

Functions:

F13

Charge structures. Use this function to set up the charge structures.

F14

Volume. Use this function to set the capacity type to volume.

F15

Containers. Use this function to set the capacity type to number of containers.

F16

Weight. Use this function to set the capacity type to weight.



Note: You can only set the capacity type, when you are defining a new rate method, code and effectivity date combination.



To save the information and return to the previous screen, select **F8=Update**.

Carrier Rates Charge Structures Window (F13)

 To display this window, on the Carrier Rates Detail Screen, select **F13=Charge Structure**.

 OR, on the Carrier Rates Area Detail Screen, enter 5 alongside an area.

Use this screen to set up and amend charge structures for the rate code.

TP015B	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		11:17:08
Maintain Carrier Rates			
Rate method	01 Load and rate table		
Rate code	C01STD		
Effective date	8/03/95		
Description	Charge Structures		
Capacity type	Conversion factor	1.00000	
VAT code	Sel	Level break	Rate Flat
	-	1.0	10.00 0
Drop charge rate	-	100.0	8.00 0
Minimum drop charge ..	-	200.0	7.00 0
Maximum drop charge ..	-	500.0	6.00 0
Surcharge %			
Surcharge value			
Minimum load charge ..			
Number of free drops ..			
		Bottom	
1=Select		4=Delete	
F8=Update		F9=Add F12=Previous	
F3=Exit	F4=Prompt	F8=Update	F11=Delete
F13=Charge structure	F14=Volume	F15=Containers	F16=Weight

Fields:

Sel

Selection field. Enter one of the following:

1 - To select the break for amendment.

4 - To delete the break details.

Conversion Factor

Enter the conversion factor for the rating of loads. Transport Planning divides the capacity by this factor before accessing a rate for a given quantity.

Functions:

F9

Add. Use this function to add new charge structure details.

 To return to the previous screen, select **F8=Update**.

Carrier Rates Level Break Details Window (F9)



To display this window, on the Carrier Rates Charge Structures Window, select **F9=Add**.

Use this window to add a level break to the charge structure.

```

TP015B                Z1 - Demonstration Company        User SP1                8/03/95
                        Demonstration Transport Centre    11:17:08

Maintain Carrier Rates

Rate method ..... 01 Load and rate table
Rate code ..... C01STD
Effective date ..... 8/03/95
Description .....
Capacity type .....
VAT code .....

Drop charge rate ....
Minimum drop charge ..
Maximum drop charge ..

Surcharge % .....
Surcharge value .....

Minimum load charge ..
Number of free drops .. 1
                        F

Charge Structures
Conversion factor ..... 1.00000

Sel      Level break      Rate      Flat
-         1.0              10.00      0
-         100.0             8.00      0
-         200.0             7.00      0
-         500.0             6.00      0

Level Break Details
Gross weight ..... 1000
Rate ..... 5.5
Flat Rate ..... 0 1=Yes, 0=No

F12=Previous
F3=Exit      F4=Prompt      F8=Update      F11=Delete      F12=Previous
F13=Charge structure  F14=Volume      F15=Containers F16=Weight

```

Fields:

Gross Capacity

Enter the gross capacity (in weight, volume or number of containers).

Rate

Enter the charge rate associated with a particular capacity.

Flat Rate

Enter one of the following:

- 0 - If the rate is per unit of weight, volume or number of containers.
1 - If the rate is an absolute value for this range.



Note: If you define a flat rate, it must be between the minimum and maximum drop charges.



To add the details and return to the previous window, press **Enter**.

Carrier Rate Area Details Screen (Option 3 and 4)



To display this screen, on the Carrier Rate Selection Screen, enter a Rate Method of 03 or 04 and press **Enter**.

Use this screen to maintain the information required to rate loads by capacities dropped into each area. Transport Planning calculates charges based on the gross weight, volume or number of containers dropped into each area using a fixed rate (option 03) or a capacity table (option 04).

```

TP015D          Z1 - Demonstration Company      User SP1      8/03/95
                Demonstration Transport Centre    11:19:41

Maintain Carrier Rates

Rate method ..... 03 Area
Rate code ..... C03STD
Effective date ..... 8/03/95
VAT code .....?.. 001
Rating conversion factor..... 1.00000
Description ..... Standard Rate by Area

```

Sel	Area	Weight rate Drop maximum	Area minimum Surcharge value	Drop minimum Surcharge %
-	A1	3.0 250.00	100.00 25.00	10.00 .00
-	A2	5.0 500.00	150.00 .00	15.00 5.00

```

1=Select  4=Delete
F3=Exit   F4=Prompt  F8=Update  F9=Add    F11=Delete
F12=Previous

```

Fields:

Sel

Selection field. Enter one of the following:

- 1 - To select the area for amendment.
- 4 - To delete the area details.
- 5 - To enter charge structures.



Note: This is only available if the rate method is 04 - Area and Rate Table.

VAT Code

Enter the VAT code used to calculate VAT on load charges. The system applies this when you transfer the invoice to Accounts Payable.

Conversion Factor

Enter the conversion factor. Transport Planning divides the capacity by this factor before accessing a rate for a given quantity.

Description

Enter a description for the rating information. For example, you could enter the carrier and route to which this applies.

Functions:

F9

Add. Use this function to add area rate details.

F14

Volume. Use this function to set the capacity type to volume.

F15

Containers. Use this function to set the capacity type to number of containers.

F16

Weight. Use this function to set the capacity type to weight.



Note: You can only set the capacity type when you are defining a new rate method, code and effectivity date combination.



To save the information, select **F8=Update**.

Maintain Area Rate Window (F9)



To display this window, on the Carrier Rate Area Details Screen, select **F9=Add**.

Use this window to add and maintain Area Rate details.

TP015D Z1 - Demonstration Company User SP1 8/03/95
 Demonstration Transport Centre 11:19:41

Maintain Carrier Rates

Rate method 03 Area
Rate code C03STD
Effective date 8/03/95
VAT code?.. 001
Rating conversion factor. 1.00000
Description Standard Rate by Area

Sel Area

- A1

- A2

Maintain Area Rate

Area?.. A3
 Area 3 - Up to 275 Miles

Weight rate 6.0
Area minimum 200.00
Drop minimum 20.00
Drop maximum 600.00
Surcharge value00
Surcharge % 5.00

1=Select 4=De
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous

F4=Prompt F8=Update F9=Add F11=Delete

Fields:

Area

Enter the area code for the rating information. You cannot amend this for existing details.

Weight/Volume/Container Rate

This only displays for Option 03 rate methods.

Enter the rate for each unit of weight, volume or container.

Area Minimum

Enter the minimum charge for the area.

Drop Minimum

Enter the minimum charge for each drop on a load.

Drop Maximum

Enter the maximum charge for each drop on a load.

Surcharge Value

Enter a value to apply to load or area charges, to accommodate unforeseen extras; for example, government fuel tax charges.

Surcharge Percentage

Enter a percentage to apply to load or area charges, to accommodate unforeseen extras; for example, government fuel tax charges.



Note: You can enter either a surcharge percentage, or value, but not both.



To add the details and return to the previous screen, select **F8=Update**.

Carrier Maintenance



5/TPM

Use this function to enter the attributes for all the carriers used to transport the goods.



Note: You must define all carriers, whether they are internal or external.

Maintain Carriers Selection Screen



Select Carrier.

Use this screen to enter the code for the carrier you want to maintain or create.

TP020A	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		11:24:51
Maintain Carriers			
Carrier.....?.. <u>CARRIER1</u>			
F3=Exit F4=Prompt			

Fields:

Carrier

Enter a reference code for the carrier.



Note: You must define the carrier to each transport centre used by the carrier.



To display the Maintain Carriers Details Screen, press **Enter**.

Maintain Carriers Detail Screen



To display the Maintain Carriers Details Screen, enter a carrier and press **Enter** on the Maintain Carriers Selection Screen.

Use this screen to maintain, or enter, the carrier details including contact information.

TP020B	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		11:25:14
Maintain Carriers			
Carrier	CARRIER1		
Name	BMZ Distribution Services		
Address	UNIT 2		
	MATFORD INDUSTRIAL ESTATE		
	SKETCHLEY WAY		
	HINKLEY		
	LE1 5EU		
Carrier type	0003	Parcel Service	
Contact name	John Smith		
Phone number	0965 1234567		
FAX number	0965 5678998		
Rating required	1 (0=No,1=Yes)		
Rate method	01	Load and rate table	
Rate code	C01STD		
Payables account	GS01		
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			
F13=Routes F21=Text			

Fields:

Name

Enter the carrier name. This prints on the bill of lading.

Address

Enter the carrier address. This prints on the bill of lading.

Carrier Type

Enter the carrier type code. You can maintain carrier types on the Inventory descriptions file under a major type of TPCT. This is a memo only field.

Contact name

Enter the name of the contact at the carriers.

Phone Number

Enter the carrier telephone number.

Fax Number

Enter the carrier FAX number.

Rating Required

Enter one of the following:

1 - To automatically calculate transport charges for the carrier.

0 - To not calculate the transport charges.

Rate Method

Enter the method of automatic rating associated with a particular rate code:

01 - Load and rate table. To calculate charges, based on the loads gross weight, volume or number of containers, using a rating table.

02 - Drop and rate table. To calculate charges, based on each drops gross weight, volume or number of containers, using a rating table.

03 - Fixed rate per area. To calculate charges, based on the gross weight, volume or number of containers, dropped into each area.

04 - Area and rate table. To calculate charges, based on the gross weight, volume or number of containers, for each area using a capacity table.

Rate Code

Enter the rate code for this carrier. You can override this by specifying a different rate code for a particular route, on the carrier route screen.

Payable Account

If you are doing automatic rating, enter an Accounts Payable supplier code for the carrier.



Note: If you have Accounts Payable attached, you must have defined the supplier to Accounts Payable.

Functions:

F13

Routes. Use this function to define the routes for which you can use this carrier.

F21

Text. Use this function to enter internal text for the carriers.

F23

Language Descriptions. Use this function to enter and maintain the descriptions for different languages.



To save the details and return to the selection screen, select **F8=Update**.

Restrict Routes Addition Window (F9)



To display this window, on the Restrict Carriers to Routes Window, select **F9=Add**.

OR, On the Restrict Carriers to Routes Window, select a route, with 1 - Amend.

Use this window to add and maintain the routes you can use this carrier for.

TP020B	Z1 - Demonstration Company Demonstration Transport Centre	User SPI	8/03/95 11:25:14
Maintain Carriers			
Carrier CARRIER1			
Restrict Carriers To Routes			
Sel	Route	Description	Rate method Rate code
-	BHAM	Birmingham Route	01 C01 STD
Addition			
Route.....?.. CAMBS Cambridge Route			
Rate method....?.. 01 Load and rate table			
Rate code.....?.. C01STD Carrier 01 Standard			
F4=Prompt F8=Update F12=Previous			
1=Select 4=Delete			
F5=Refresh F8=Update F9=Add F12=Previous			
F13=Routes F21=Text			

Fields:

Route

Enter the route you want to use this carrier for. If you are maintaining routes, this field is for information only.

Rate Method

Enter the method of rating this route for this carrier:

- 01 - Load and rate table.
- 02 - Drop and rate table.
- 03 - Fixed rate per area.
- 04 - Area and rate table.

Rate Code

Enter the rate code to use for this route and carrier combination.



To save the details and return to the Restrict Carriers To Routes Window, select **F8=Update**.

Text Window (F21)



To display this window, on the Maintain Carriers Detail Screen, select **F21=Text**.

Use this screen to enter the text for the carrier.



Note: This text is for the planners only, and is not printed on any documentation.

TP020B

Z1 - Demonstration Company

User SP1

8/03/95

Demonstration Transport Centre

11:26:37

Maintain Carriers

Carrier

CARRIER1

Name

BMZ Distribution Services

Address

UNIT 2

MATFORD INDUSTRIAL ESTATE

SKETCHLEY WAY

HINKLEY

Carrier type

LE1

5EU

Contact name

0003

Parc

Phone number

John Smith

FAX number

0965 12345

Rating required

0965 56789

Rate method

1

(0=No.1

Rate code

01

Load

Payables account

C01STD

GS01

F3=Exit

F4=Prompt

F8=

F13=Routes

F21=Text

Carrier text

Lin Internal Text

1 Pick up goods before 12 noon.

2

3

4

5

6

Position to

Insert

after

Delete

from

F5=Refresh

F8=Update

F12=Previous

Fields:

Text

Enter any text you wish to have associated with the carrier.

Position To

Enter the line to position the cursor to.

Insert

Enter the number of the lines to insert.

After

Enter the line number you want the inserted lines to follow.

Delete

Enter the number of the line to start the deletion from.

From

Enter the number of lines to delete.



To save the text and return to the previous screen, select **F8=Update**.

Multi-Lingual Descriptions Maintenance Text Window (F23)



To display this window, on the Maintain Carriers Detail Screen, select **F23=Language Descriptions**.

Use this screen to enter the text for multi-lingual documentation. You use this to enter alternative descriptions for different language codes. When a user, with that language code associated to the user profile, uses the processing function, the description displays in that language.

[illegible]

Fields:

Language

Enter the language code.

Description

Enter the description.



To save the text and return to the previous screen, select **F8=Update**.

Routes



6/TPM

Use this function to define the journeys undertaken by the carriers (internal or external) between two geographical locations. You must define all routes to the application.



Note: Before you define routes, you must define the nodes representing the origins and destinations (for more information, refer to Transport Nodes).

Maintain Routes Selection Screen



Select Routes

Use this screen to enter the route that you want to maintain or create.

TP023A	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		11:27:32
Maintain Routes			
Route.....?.. <u>BHAM</u>			
F3=Exit F4=Prompt			

Fields:

Route

Enter the route. This is the journey between two geographical locations (known as transport nodes). You assign a customer delivery point a particular drop sequence along a route. You can amend this when you build the load.



Note: For a master load, define the route codes for the sub-loads, to the transport centre where you ship the master load from.



To display the Maintain Routes Detail Screen, enter a route and press **Enter**.

Maintain Routes Detail Screen



To display this screen, on the Maintain Routes Selection Screen, enter a route and press **Enter**.

Use this screen to enter the details for the selected route.

TP023B	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		11:27:39
Maintain Routes			
Route.....	BHAM		
Description.....	Birmingham Route		
Default carrier.....?	OWN	Demonstration Fleet	
Default vehicle type.....?	16T	16 Tonne Rigid	
Origin.....?	TC01	Transport Centre No 1	
Destination.....?	BHAM	Birmingham	
Bill of lading required.....	0	(0=No, 1=Yes)	
Bill of lading format.....?			
Number of copies.....	1		
Default ship time.....	8:00		
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			

Fields:

Description

Enter a description for the route.

Default Carrier

Enter the default carrier for this route.

Default Vehicle Type

Enter the default type of vehicle for this route. Transport Planning uses vehicle types to check that you do not exceed the defined gross weight and volume when building loads.

Origin

Enter the origin or start point for the route. You must define the origins as transport nodes. The origins print on the bill of lading.

Destination

Enter the destination or end point for the route. You must define the destinations as transport nodes. The destinations print on the bill of lading.

Bill Of Lading Required

Enter one of the following:

0 - If you only need a load sheet.

1 - If you require a bill of lading as well as a load sheet.

Bill Of Lading Format Code

Enter one of the following:

01 - One document per load. The capacity totals are from the load header and the despatch notes are associated with the load.

02 - One document per drop/delivery point on route. The capacity totals are per drop/delivery point and the despatch notes are associated with drop/delivery point.

03 - One document per load. The capacity totals are from the load header with one totals line per drop. The despatch notes for each drop/delivery point.

04 - One document per load. The capacity totals are per area and for the load. The despatch notes are associated with the load.

You use the Inventory descriptions file, major type of TPBL, to support and maintain these formats.

Number Of Copies

Enter the number of copies of the bill of lading documentation you require.



Note: The bill of lading information you assign to the route is the default when you create loads. You can override this using the Maintain Loads function.

Ship Time

Enter the default ship time assigned to the route. This field is for information only.



To save the details, and return to the Maintain Routes Selection Screen, select **F8=Update**.

Areas

1... **2...** 7/TPM

Use this function to define the areas or zones which are used to group load drops. You can then rate loads and split load documentation by area (Rating Methods 03 and 04). You can assign a rating area to a customer on the Customer Delivery Profile.

Maintain Areas Screen



Select Area

Use this screen to enter the details for the area you want to maintain or create.

```

TP026B                Z1 - Demonstration Company        User SP1          8/03/95
                    Demonstration Transport Centre      11:28:06

Maintain Areas

Area..... A1

Name..... Area 1 - Up to 50 Miles


```

Fields:

Area

Enter the area you want to maintain or create.

Name

Enter a description of the area.



*Note: To display this field, enter an Area and then press **Enter**.*

Functions:

F11

Delete. Use this function to delete the area.



Note: You cannot delete the area if it is defined to a delivery profile.



To save the details, select **F8=Update**. Then select **F3=Exit** to return to the Menu.

Delivery Profile Maintenance



8/TPM

Use this function to define profile details for each delivery point. You must set up a delivery profile for each customer delivery point, or distribution centre, that you want to consider whilst planning transport from this transport centre.

Maintain Delivery Profiles Selection Screen



Select Delivery Profile.

Use this screen to enter the sales company and customer combination for which you want to maintain the delivery profile.

TP024A	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		11:28:19
Maintain Delivery Profiles			
Sales company.....?.. <u>Z1</u> Demonstration Company			
Customer.....?.. <u>GC01</u> <u>000</u>			
F3=Exit F4=Prompt			

Fields:

Sales Company

Enter the sales order processing company.

Customer




Enter the customer, as defined to Accounts Receivable, and the customer delivery point.



Note: You must enter a sales company to prompt on the associated customers, as a transport centre can plan transport on behalf of multiple sales companies.



To display the Maintain Delivery Profiles Detail Screen, enter the details and then press **Enter**.



Enter one of the following:

0 - If the goods for this customer can be included on a load with other customers goods.

1 - To only include goods for this customer delivery point on the load.

Confirm Delivery Time Slot

Enter one of the following:

0 - If you do not need to confirm a delivery time.

1 - To highlight, during the build load function, the customer name and delivery point with a flashing asterisk. This shows that you must confirm with the customer a delivery time slot.

Deliveries Allowed

Enter one of the following for each day of the week:

0 - If you cannot deliver on this day.

1 - If the customer allows deliveries on this day.



Note: The appropriate days are highlighted if delivery time slots exist.

Functions:

F11

Delete. Use this function to delete the delivery profile (providing there are no outstanding orders or load drops for this delivery profile).

F13

Delivery time Slots. Use this function to enter delivery time slot details.

F21

Text. Use this function to enter text using the standard text window.



To save the information and return to the Maintain Delivery Profiles Selection Screen, select **F8=Update**.

Delivery Time Slots Window (F13)

-  To display this window, on the Maintain Delivery Profiles Details Screen, make sure the cursor is on a day which allows deliveries, and select **F13=Delivery Time Slots**.

Use this screen to enter the delivery times allowed for the selected day.

TP024B	Z1 - Demonstration Company Demonstration Transport Centre	User SP1	8/03/95 11:28:42
Maintain Delivery Profiles			
Sales company..... Z1 Demonstration Company			
Customer..... GC01 000 Reeves Chemist's 31 Lenton Boulevard Lenton			
Default planning parameters:			
Route?.. YORKS1		Yorkshire Route 1	
Drop?.. 010		Delivery Time Slots	
Carrier?.. CARRIER1		Day..... Monday	
Area?.. A2		Time slot 1..... 10:00 12:00	
Customer exclusive loads ... 0 (0=No		Time slot 2..... 14:00 17:30	
Confirm delivery time slot . 0 (0=No		Time slot 3..... 0:00 0:00	
Deliveries allowed: Mon Tue Wed Thu F		Time slot 4..... 0:00 0:00	
1 1 1 1		F8=Update F12=Previous	
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous		F13=Delivery time slots F21=Text	

Fields:

Time Slot N

Where N = 1 to 4.

Enter the time slots between which deliveries are accepted by the customer.

-  To save the information and return to the previous screen, select **F8=Update**.

Item Transport Details



9/TPM

Use this function to enter item details in addition to the Inventory item definition. These are used to calculate the capacity requirements. You must define all items to the application in order to assess the capacities. Otherwise the item is ignored when an order is passed into Transport Planning and recorded on the serious error report.

Maintain Item Transport Details Selection Screen



Select Item Transport Detail.

Use this screen to enter the selection criteria for the item you want to maintain.

TP048A	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		11:30:27
Maintain Item Transport Details			
Sales company.....?.. <u>Z1</u> Demonstration Company			
Item.....?.. <u>5001</u>			
F3=Exit F4=Prompt			

Fields:

Sales Company

Enter the Sales Order Processing/Inventory Management company associated with the processing of orders and stocking of the item.

Item Code

Enter the reference code for the item.



Note: You must have defined the item codes for the specified Sales/ Inventory company.



To display the Maintain Item Transport Details Screen, press **Enter**.

Maintain Item Transport Details Screen



To display the Maintain Item Transport Details Screen, press **Enter**.

Use this screen to enter the weight, volume and container details for the item.

TP048B	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		11:31:04
Maintain Item Transport Details			
Sales company..... Z1 Demonstration Company			
Item..... 5001 Suncream Factor 4 225ml			
Net weight per iss. unit .2250			
Volume per issue unit... .3000			
Item tare weight:			
Per issue unit..... .0			
OR			
Net weight percentage. 2.00			
Quantity per container.. 240.00			
Container tare weight... .0			
Container volume..... .0			
F3=Exit F8=Update F11=Delete F12=Previous			

Fields:

Net Weight Per Iss. Unit

Enter the net weight for an issue unit of the item, this is the weight of the item per selling unit. This is used to calculate the weight capacities associated with transport requirements for this item. The default is from the Item/stockroom profile.

Volume Per Issue Unit.

Enter the volume for an issue unit of the item. This is used to calculate the volume capacities associated with transport requirements for this item.

Item Tare Weight

Enter the item tare weight, per issue unit. This is used to calculate the weight of any inner pack or shrink wrapping associated with the item.

Or enter the net weight percentage. This is the tare weight expressed as a percentage of the net weight and is used to calculate the weight of any inner pack or shrink wrapping associated with the item.



Note: You can enter tare weight per issue unit or tare weight percentage but not both.

Quantity Per Container

Enter the quantity of the item per default container (pallet, case, drum). This is used to calculate the number of containers required.

Container Tare Weight

Enter the tare weight of the empty container. This is used to calculate the weight of empty containers.

Container Volume

Enter the volume for an empty container.



Note: The volume and weight are assumed to be cumulative for the issue unit and the container. If the container is a box, and therefore the item does not take up any extra space, set the issue volume to zero and the container volume to the volume of the box.



To save the information, and return to the Maintain Item Details Selection Screen, select **F8=Update**.

Sample Calculation

If you set up the following details for an item:

Net weight per issue unit = 5.00

Net volume per issue unit = 3.00

Item tare weight per issue unit = 0.25

Container tare weight = 2.00

Container volume = 3.00

From an order line quantity of 10 issue units, the transport requirements calculated are:

Net weight = $10 \times 5.00 = 50.00$

Net volume = $10 \times 3.00 = 30.00$

Item tare weight = $10 \times 0.25 = 2.50$

Number of containers = $10/10.00 = 1.00$

Container tare weight = $1 \times 2.00 = 2.00$

Container volume = $1 \times 3.00 = 3.00$

Total volume = Net volume + container volume = **33.00**

Total tare weight = Item tare weight + container tare weight = 4.50

Gross weight = Net weight + total tare weight = **54.50**

Carrier Enquiry



25/TPM

You use this enquiry to select and enquire on carrier codes and associated information. You must have defined all carriers, whether internal or external, to the application.

Carrier Selection Screen



Select Carrier Enquiry.

Use this screen to select the carrier to enquire on.

TP220A	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		12:17:12
Carrier Enquiry			
Carrier?.. <u>CARRIER1</u>			
F3=Exit F4=Prompt			

Fields:

Carrier

Enter the internal or external carrier that you want to view the details for.



Press **Enter** to display the detail screen.

Carrier Enquiry Details Screen

 To display this screen, on the Carrier Enquiry Selection Screen, enter a Carrier and press **Enter**.

This screen displays the contact and rating details for the selected carrier.

TP220B	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		12:17:21
Carrier Enquiry			
Carrier	CARRIER1		
Name	BMZ Distribution Services		
Address	UNIT 2		
	MATFORD INDUSTRIAL ESTATE		
	SKETCHLEY WAY		
	HINKLEY		
	LE1	5EU	
Carrier type	0003 Parcel Service		
Contact name	John Smith		
Phone number	0965 1234567		
FAX number	0965 5678998		
Rating required ...	1		
Rate method	01 Load and rate table		
Rate code	C01STD		
Payables account ..	GS01		
F3=Exit F12=Previous F13=Routes F21=Text			

Functions:

F13

Routes. Use this function to display the routes the carrier can use.

F21

Text. Use this function to display the internal text for the carrier. This is used for planning purposes.



*Note: If routes and text exist, **F13=Routes** or **F21=Text**, respectively, are highlighted.*



To leave the enquiry, select **F3=Exit**.

Carrier Route Restriction Window (F13)

 To display this window, on the Carrier Enquiry Details Screen, select **F13=Routes**.

This window displays the routes that the carrier is restricted to. If no routes display, you can use the carrier for all routes for the transport company. The default rate method and code apply to all routes for this carrier.

TP220B	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		12:17:21
Carrier Enquiry			
Carrier CARRIER1			
Nam	Carrier Route Restriction		
Add			
	Route	Rate method	Rate code
	BHAM	01	C01STD
	CAMBS	01	C01STD
Car			
Con			
Pho			
FAX			
Rat			
Rat			
Rat			
Pay			
	Bottom		
F12=Previous			
F3=Exit F12=Previous F13=Routes F21=Text			

 To return to the previous screen, select **F12=Previous**.

Carrier Text Window (F21)

 To display this window, on the Carrier Enquiry Details Screen, select **F21=Text**.

This window shows the internal text for the carrier.



Note: This text is for the planners information only, and does not print on any documentation.

TP220B	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		12:17:21
Carrier Enquiry			
Carrier CARRIER1			
Name BMZ Distribution Services			
Address UNIT 2			
MATFORD INDUSTRIAL ESTATE			
SKETCHLEY WAY			
HINKLEY			
Carrier type LE1 5EU			
Contact name 0003 Parcel S			
John Smith			
Phone number 0965 1234567			
FAX number 0965 5678998			
Rating required ... 1			
Rate method 01 Load and r			
Rate code C01STD			
Payables account .. GS01			
Carrier text			
Lin Internal Text			
1 Pick up goods before 12 noon.			
2			
3			
4			
5			
6			
Position to ____			
F3=Exit		F12=Previous	
F13		F5=Refresh F12=Previous	

Fields:

Position To

Enter the line number you wish to display.

 To return to the previous screen, select **F12=Previous**.

Delivery Profiles Enquiry



28/TPM

Use this enquiry to display the defined delivery profiles. You must define all customer delivery points, including those which represent distribution centres.

Delivery Profile Enquiry Selection Screen

 Select Delivery Profile Enquiry.

Use this screen to enter the sales company and customer for which you want to display the delivery profile.

TP224A	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		12:26:59
Delivery Profile Enquiry			
Sales company.....?.. <u>Z1</u> Demonstration Company			
Customer.....?.. <u>GC01</u> <u>000</u>			
F3=Exit F4=Prompt			

Fields:

Sales Company

Enter the Sales Order Processing company.

Customer

Enter the customer and delivery sequence for the delivery point.

 Press **Enter** to display the detail screen.

Delivery Profile Enquiry Detail Screen



To display this screen, on the Delivery Profile Enquiry Selection Screen, enter a sales company and customer and press **Enter**.

This screen displays the delivery profile details including the route details and days that you can deliver to the customer.

TP224B	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		12:27:26
Delivery Profile Enquiry			
Sales company..... Z1 Demonstration Company			
Customer..... GC01 000 Reeves Chemist's			
31 Lenton Boulevard			
Lenton			
Default planning parameters:			
Route..... YORKS1 Yorkshire Route 1			
Drop..... 010			
Carrier..... CARRIER1 BMZ Distribution Services			
Area..... A2 Area 2 - Up to 150 Miles			
Customer exclusive loads.... 0 (0=No,1=Yes)			
Confirm delivery time slot.. 0 (0=No,1=Yes)			
Deliveries allowed: Mon Tue Wed Thu Fri Sat Sun			
1 1 1 1 0 0 (0=No,1=Yes)			
F3=Exit F12=Previous F13=Delivery time slots F21=Text			

Functions:

F13

Delivery time slots. Use this function to display the times you can deliver to this customer.

F21

Text. Use this function to display the internal customer text which contains details to assist the transport planner.



To leave the enquiry, select **F3=Exit**.

Enquire On Delivery Time Slots Window (F13)



To display this window, on the Delivery Profiles Enquiry Details Screen, select **F13=Delivery Time Slots**.

This window displays the time slots you can deliver to the specified customer delivery point.

TP224B

Z1 - Demonstration Company

User SP1

8/03/95

Demonstration Transport Centre

12:27:26

Delivery Profile Enquiry

Sales company..... Z1 Demonstration Company

Customer..... GC01 000 Reeves Chemist's

31 Lenton Boulevard

Lenton

Default planning parameters:

Route..... YORKS1 Yorkshire Route 1

Drop..... 010

Carrier..... CARRIER1

Area..... A2

Customer exclusive loads.... 0 (0=No.

Confirm delivery time slot.. 0 (0=No.

Deliveries allowed: Mon Tue Wed Thu F

1 1 1

F3=Exit F12=Previous F13=DeT

Enquire on delivery time slots

Delivery Time Slots

Day..... Monday

Time slot 1..... 10:00 12:00

Time slot 2..... 14:00 17:30

Time slot 3.....

Time slot 4.....

F12=Previous



To return to the previous screen, select **F12=Previous**.

Customer Text Window (F21)



To display this window, on the Delivery Profiles Enquiry Details Screen, select **F21=Text**.

This window displays the internal customer text. This text is only used for the planner's information, and is not printed on any documentation.

TP224B	Z1 - Demonstration Company	User SP1	8/03/95
	Demonstration Transport Centre		12:27:26
Delivery Profile Enquiry			
Sales company..... Z1 Demonstration Company			
Customer..... GC01 000 Reeves Chemist's			
31 Lenton Boulevard			
Lenton			
Default planning parameters:			
Route..... YORK			
Drop..... 010			
Carrier..... CARR			
Area..... A2			
Customer exclusive loads.... 0 (0			
Confirm delivery time slot.. 0 (0			
Deliveries allowed: Mon Tue Wed T			
1 1			
F3=Exit F12=Previous F13			

Customer Text

Lin	
1	Afternoon deliveries preferred.
2	
3	
4	
5	
6	

Position to ____

F5=Refresh F12=Previous



To return to the previous screen, select **F12=Previous**.