

-
-
-
-
-

Chapter 4

Reports



Bills Of Lading

 **1/TPR**

 **2/TPR**

Bills of Lading provide a formal document detailing the load contents, according to the bill of lading format code specified on the load header. You normally only produce Bills of Lading for selected external carriers.



Note: Load sheets provide a drivers manifest and list all drops for each load. You can also use load sheets to marshall goods and despatch notes onto their appropriate transport loads prior to despatch.

When you print the master load documentation, Transport Planning prints sub-load numbers and totals as drops (as well as any customer drops) and automatically prints the documentation for unprinted sub-loads

If the load requires automatic or manual rating, Transport Planning updates the load status to awaiting rating. If you do not want rating but do require confirm despatch, Transport Planning updates the load as awaiting confirm despatch. If you do not want rating and confirm despatch, Transport Planning updates the load status so that you can drop the load to history, This means producing the bill completes the processing of the load.

You can either print bills of lading or reprint already printed sheets.

Print Bills Of Lading Selection Screen



To display this screen select either Print Bills Of Lading or Reprint Bills Of Lading.



Note: The screen name is Print Bills Of Lading or Reprint Bills Of Lading, depending on the option selected.

Use this screen to select the Bills of Lading (BoLs) you want to print.

TP810

Z1 - Demonstration Company
Demonstration Transport Centre

User SP1

9/03/95
15:08:11

Print bills of lading

Ship date..... 9/03/95

Route.....?.. _____

OR

Carrier.....?.. _____

OR

Origin.....?.. _____

Destination.....?.. _____

OR

Load number..... _____

Print load sheets..... 1 (0=No.1=Yes)

Load sheet sequence... 1 (1=Ascending 2=Descending)

F3=Exit

F4=Prompt

F8=Submit

F16=Released Loads

Fields:

Ship Date

Enter the ship date for the loads. This defaults to today's date plus the planner's time fence days for planning.

Route

Enter the route for which you want to print BoLs.

Carrier

Or, enter the carrier for which you want to print BoLs.

Origin

Or, enter the start point for which you want to print BoLs.

Destination

If you entered the origin, enter the destination or end point for which you want to print BoLs.

Load Number

Or, enter a particular load reference for which you want to print the BoLs.

Print/Reprint Load Sheets

Enter one of the following:

0 - Not to reprint/print the load sheets.

1 - To reprint/print the load sheets.

Load Sheets Sequence

Enter one of the following:

1 - Ascending. To print load sheets in ascending drop sequence within route.

2 - Descending. To print load sheets in descending drop sequence within the route.

Functions:

F16

Released loads. Use this function to display loads headers that conform to the selection criteria, on the Select Load Detail Screen.



Note: For the reprint option, this only displays load headers already printed and the document clearly displays Reprint.



Note: If you have printed a load, then reset it to pending for amendment and subsequently released it again, use the print option (not reprint).



To print or reprint the Bills Of Lading, select **F8=Submit**.

Load Sheets

1... 3/TPR
2...

1... 4/TPR
2...

Load sheets provide a drivers manifest and list all drops for each load. You can also use load sheets to marshall goods and despatch notes onto their appropriate transport loads prior to despatch.



Note: Bills of lading are a more formal document detailing the load contents and are generally produced for selected external carriers only.

You can print drops in descending or ascending sequence for the route.

When you print the master load documentation, Transport Planning prints sub-load numbers and totals as drops (as well as any customer drops) and automatically prints the documentation for unprinted sub-loads

If you do not require Bill of Lading documentation, Transport Planning updates the load as follows:

- If the load requires automatic or manual rating, Transport Planning updates the load status as printed, that is awaiting rating.
- If rating is not applicable and you require confirm despatch, Transport Planning updates the load status as rated, that is awaiting confirm despatch.
- If rating and confirm despatch are not applicable, Transport Planning updates the load status such that you can drop it to history, that is the production of the load sheet completes the processing of the load.

The load sheet serves three major purposes:

- As a marshalling document for all despatch notes included on the load sheet, particularly if the notes are from more than one stockroom.
- As an aid for loading the vehicle in the best sequence for dropping.
- As an action and confirmation list for the driver.

You can print load sheets or reprint already printed sheets.

Print Load Sheets Screen



To display this screen select either Print Load Sheets or Reprint Load Sheets.



Note: The screen name is Print Loads Sheets or Reprint Load Sheets, depending on the option selected.

Use this screen to select the Load Sheets you want to print.

TP820	Z1 - Demonstration Company Demonstration Transport Centre	User SP1	9/03/95 15:08:53
-------	--	----------	---------------------

Print Load Sheets

Ship date 9/03/95

Route?.. _____

OR

Carrier?.. _____

OR

Origin?.. _____

Destination ..?.. _____

OR

Load number _____

Load sheet sequence. 1 (1=Ascending,2=Descending)

F3=Exit F4=Prompt F8=Submit F16=Released Loads

Fields:

Ship Date

Enter the ship date for the loads. This defaults to today's date plus the planner's time fence days for planning.

Route

Enter the route for which you want to print load sheets.

Carrier

Or, enter the carrier for which you want to print load sheets.

Origin

Or, enter the start point for which you want to print load sheets.

Destination

If you entered the origin, enter the destination or end point for which you want to print load sheets.

Load Number

Or, enter a particular load reference for which you want to print the load sheets.

Load Sheets Sequence

Enter one of the following:

- 1 - Ascending. To print load sheets in ascending drop sequence within route.
- 2 - Descending. To print load sheets in descending drop sequence within the route.

Functions:

F16

Released loads. Use this function to display loads headers that conform to the selection criteria, on the Select Load Detail Screen.



Note: For the reprint option, this only displays load headers already printed and the document clearly displays Reprint.



Note: If you have printed a load, then reset it to pending for amendment and subsequently released it again, use the print option (not reprint).



To print or reprint the load sheets, select **F8=Submit**.

Outstanding Orders Report



13/TPR

The outstanding orders report provides you with details of all order requirements not yet assigned to loads, with capacity totals per route and date. The report is sequenced by route/drop within required ship date and provides details of capacity requirements.

Use this report in conjunction with the build loads function.

Outstanding Orders Report Screen



To display this screen, select the Outstanding Orders Report option.

Use this screen to enter the desired ship date and route selections for the Outstanding Orders Report.

TP800

Z1 - Demonstration Company
Demonstration Transport Centre

User SP1

9/03/95
15:12:27

Outstanding Orders Report

	From	To
Ship date	0/00/00	9/03/95
Route	?	

F3=Exit F4=Prompt F8=Submit

Fields:

Ship Date

Enter the range of ship dates for which you want to review orders. The To date defaults to today's date plus the planner's time fence days for planning and is matched against the order line despatch date.

If you do not specify a To date, then all outstanding orders on or after the From date are selected.

Route

Enter the route range for which to review orders.

To select details for all routes, leave both the From and To fields blank.

If you specify the From route and leave the To route blank, then all details are selected with route codes matching, or greater than, the From route.



To submit the report, select **F8=Submit**.

Load Status Report



14/TPR

The load status report provides summary information for the total capacity requirements of outstanding orders, together with a view of current loads. The report is sequenced by route or drop within required ship date and provides a direct comparison between outstanding requirements and current loads applicable to those requirements, that is for the same route and ship date.

Use this report, in conjunction with the outstanding orders report and the build loads function, to assess and action over or under capacity commitments to loads, prior to assigning further requirements.

For example, for all routes where there is enough commitment to justify a load, and not enough to overload it, the planner build these loads immediately. Otherwise, the planner uses the outstanding orders report for under and over committed routes to determine which orders to reassign during the build loads function.

Load Status Report Screen

 To display this screen, select the Load Status Report option.

Use this screen to enter the ship date and route selection criteria for the Load Status Report.

TP805

Z1 - Demonstration Company
Demonstration Transport Centre

User SP1

9/03/95
15:12:46

Load Status Report

	From	To
Ship date.....	9/03/95	0/00/00
Route.....?..		

F3=Exit F4=Prompt F8=Submit

Fields:

Ship Date

Enter the range of ship dates for which you want to review loads.

If you do not specify a To date, then all outstanding orders on or after the From date are selected.

The To date defaults to today's date plus the planner's time fence days for planning and is matched against the load ship date.

Route

Enter the route range for which to review orders.

To select details for all routes, leave both the From and To fields blank.

If you specify the From route and leave the To route blank, then all details are selected with route codes matching, or greater than, the From route.

 To submit the report, select **F8=Submit**.

Load Details Report



15/TPR

The load details report displays details of all order requirements currently assigned to loads. The report is sequenced by route/drop within required ship date and provides details of capacity requirements.

Use this report in conjunction with the load status report and maintain loads function to assess and action over and under capacity commitments to loads.

Load Details Report Screen

 To display this screen, select the Load Details Reports option.

Use this screen to enter the ship date and route selection criteria for the Load Details Report.

TP830

Z1 - Demonstration Company
Demonstration Transport Centre

User SP1

9/03/95
15:13:05

Load Details Report

	From	To
Ship date	9/03/95	0/00/00
Route	?	

F3=Exit F4=Prompt F8=Submit

Fields:

Ship Date

Enter the range of ship dates for which to display orders.

If you do not specify a To date, then all outstanding orders on or after the From date are selected.

The To date defaults to today's date plus the planner's time fence days for planning and is matched against the load ship date.

Route

Enter the route range for which to review orders.

To select details for all routes, leave both the From and To fields blank.

If you specify the From route and leave the To route blank, then all details are selected with route codes matching, or greater than, the From route.

 To submit the report, select **F8=Submit**.