

-
-
-
-
-

Chapter 5

Utilities



Company Profile Maintenance



1/TPU

Use Company Profile Maintenance to enter and maintain the reference data that controls the processing of transport order requirements for a particular company.

When you create a Transport Planning Company, the company must already exist in Inventory Management.

Maintain Company Profile Selection Screen



To display this screen, select the Company Profile Maintenance option.

Use this screen to enter the transport company you want to maintain or create.

TP900A	User SP1	8/03/95 11:45:58
Maintain Company Profile		
Company code?.. <u>Z1</u>		
F3=Exit F4=Prompt		

Fields:

Company Code

To create a new company, enter a code using two alphanumeric characters.



Note: This company must already exist in Inventory Management.

To maintain an existing transport company, select the required company.



To display the Maintain Company Profile Address Screen, press **Enter**.

Maintain Company Profile Address Screen



To display this screen, on the Maintain Company Profile Selection Screen, select a company and press **Enter**.

Use this screen to enter the address details for the selected company.

TP900B	User SP1	8/03/95 11:46:42
Maintain Company Profile		
Company code	Z1	
Company name	Demonstration Company	
Address	Unit 5, Rennes Boulevard	
	Magna Park	
	Lutterworth	
	Leics	
Post code	_____	
Container decimals	1 (0-2)	
Weight decimals	1 (0-3)	
Volume decimals	1 (0-3)	
Load numbers per centre	1 (0=No,1=Yes)	
Load number prefix	A	
Load number range	1 9999	
F3=Exit F8=Update F11=Delete F12=Previous		

Fields:

Company Name

Enter the name for the transport company.

Address

Enter the address for the transport company.

Post Code

Enter the post code for the transport company.

Transport Container Decimals

Enter the number of significant decimal places, (0, 1 or 2) for transport containers. Transport Planning uses this setting to calculate and display container capacities.

Weight Decimals

Enter the number of significant decimal places, (0, 1, 2 or 3) for transport weights. Transport Planning uses this setting to calculate and display weight capacities.

Volume Decimals

Enter the number of significant decimal places, (0, 1, 2 or 3) for transport volumes. Transport Planning uses this setting to calculate and display volume capacities.

Load Numbers Per Centre

Enter one of the following:

0 - No. To generate load references with a single alphanumeric prefix and incrementing number range, that appear throughout the system. Load references are unique within the transport company.

1 - Yes. To generate load references with an alphanumeric prefix and incrementing numeric range for the transport centre. Load references are unique within the transport centre only.

Load Number Prefix

Enter the load reference prefix to precede all automatically generated load references.

Load Number Range

Enter the range for the numeric portion of the transport load number reference.

Transport Planning increments all automatically generated load numbers from the lower value. If the load numbers reach the upper limit, Transport Planning reassigns transport load references from the lower limit.



To display the Maintain Company Profile Details Screen, press **Enter**.

Maintain Company Profile Details Screen



To display this screen, on the Maintain Company Profile Address Screen, press **Enter**.

Use this screen to enter the default sales and accounting details.

TP900B	User SP1	8/03/95 11:46:42
Maintain Company Profile		
Company code Z1 Demonstration Company		
Order planning level 2 (1=Order,2=Lines)		
Initial creation of transport requirements ...?.. 1		
Default sales company?.. Z1		
General ledger company Z1		
Default VAT code?.. 001		
Transport requirement leadtime 0		
Accounts Payable posting method 2 (1=Single,2=Multiple)		
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous		

Fields:

Order Planning Level

Enter one of the following:

- 1 - Order. To use the stockroom associated with the order header for the retrieval of transport planning information.
- 2 - Lines. To use the stockroom associated with each order line for the retrieval of transport planning information. In line level planning, you can process a particular sales order via a number of different transport centres.

Initial Creation Of Transport Requirements

Enter the point at which you initially create transport requirements. You define the point of creation to the Inventory management descriptions file under a major type TPIC. The default points are:

- 1 - Sales order creation.
- 2 - Sales order allocation.
- 3 - Pick note creation.
- 4 - Commit stock.
- 5 - Confirm pick.
- 6 - Confirm despatch of pick note.



Note: Transport Planning does not currently support options 4 and 5.

Default Sales Company

Enter the Sales or Inventory company associated with any descriptions file entries.

General Ledger Company

Enter the General Ledger company associated with the transport company. If you enter a company code, Transport Planning assumes General Ledger is attached. You must define all VAT codes and General Ledger account codes to the ledger.

Default VAT Code

Enter the normal VAT rate charged by carriers for transporting goods.

If General Ledger is attached, you must define this code in General Ledger. Otherwise you must define the VAT code to the Inventory Management descriptions file under major type VAT.

Transport Requirement Lead Time

Enter the number of days forward from the current date up to which new sales order lines are transferred into Transport Planning (based on their due date). This avoids the transport planner being overwhelmed by requirements which they have no need to consider yet.



Note: A change in lead time will not take effect until you stop and restart the Transport Planning background subsystems.

Accounts Payable Posting Method

This determines what invoices are transferred to the Accounts Payable invoice log, when you authorise a payment for multiple loads on a single carrier invoice. Enter one of the following:

- 1 - Single. To transfer a single invoice.
- 2 - Multiple. To transfer an invoice for each load on the carrier's invoice.



To save the date and return to the menu, select **F8=Update**.

Planner Profile Maintenance

1... **2/TPU**

Use this option to specify the authorisation level of a specified planner for transport order requirements.

You must set up a profile for every planner who uses Transport Planning. You set up the profile for the planner's user ID.

You can also define the planner's default transport centre. Planners normally operate within a default transport centre but they can change to any centre within which they are authorised to process details.

You can authorise each user ID to one or more transport centres.

Maintain Transport Planners Selection Screen

 To display this screen, select the Planner Profile option.

Use this screen to select the transport company and user profile you want to maintain.

TP903A

User SP1

8/03/95
11:48:30

Maintain Transport Planners

Company code?.. Z1

User profile?.. SP1

F3=Exit

F4=Prompt

Fields:

Company Code

Enter an existing transport company.

User Profile

Enter the user ID.

 Press **Enter** to display the Maintain Transport Planners Detail Screen.

Maintain Transport Planners Detail Screen



To display this screen, enter the company and user ID and press Enter on the Maintain Transport Planners Selection Screen.

Use this screen to specify the default transport centre and levels of authority for the selected planner.

TP903B	User SP1	8/03/95 11:48:40
Maintain Transport Planners		
Company code	Z1	Demonstration Company
User profile	SP1	Work Station User
Default centre	?.. TC01	Demonstration Transport Centre
Planning time fence days ..	0	
Release load	1 (0=No, 1=Yes)	
Override capacity errors ..	1 (0=No, 1=Yes)	
Authorise payments	1 (0=No, 1=Yes)	
Authorise adjustments	1 (0=No, 1=Yes)	
F3=Exit	F4=Prompt	F8=Update
F13=Transport centres		F11=Delete F12=Previous

Fields:

Default Centre

Enter the transport centre which is the default for this planner. This is the transport centre the planner normally uses to plan, marshal and despatch loads.



Tip: You can authorise the planner to transport centres by selecting **F13=Transport Centres**.

Planning Time Fence Days

Enter the number of days to use as the default planning time fence. This determines the planned ship date the planner uses when reviewing order requirements and load details. The planned ship date is today's date plus this figure.

Release Load

Enter one of the following:

- 0 - If the planner cannot release loads.
- 1 - If the planner can release loads.

Override Capacity Errors

Enter one of the following:

0 - If the planner cannot override capacity errors when assigning transport requirements.

1 - If the planner can override capacity errors.

Authorise Payments

Enter one of the following:

0 - If the planner cannot match carrier payments against calculated charges for loads.

1 - If the planner can match carrier payments.

Authorise Adjustments

Enter one of the following:

0 - If the planner cannot authorise adjustments to carrier payments.

1 - If the planner can authorise adjustments.

Functions:

F13

Transport centres. Use this function to authorise the planner to transport centres.



Select **F8=Update** to save the entered information.

Authorise Planners To Transport Centres Screen (F13)



To display this screen, select **F13=Transport Centres** on the Maintain Transport Planners Detail Screen.

Use this screen to select the transport centres that the planner can use.



Tip: Select **F15** to authorise the planner to all centres.

TP904	User SP1	8/03/95 11:49:08
Authorise Planners To Transport Centres		
Company code Z1		Demonstration Company
User profile SP1		Work Station User
Sel	Transport centre	Name
- *	TC01	Demonstration Transport Centre
1=Select 4=Delete		
F3=Exit F12=Previous F15=All centres		

Fields:

Sel

Selection field. Enter one of the following:

1 - Select. To authorise the planner to the selected transport centre.

4 - Delete. To remove the planners authorisation from the selected transport centre.

Functions:

F15

All centres. Use this function to authorise the planner to all transport centres defined to the transport company.



Select **F12=Previous** to return to the Maintain Transport Planners Detail Screen.

Start / End Background Tasks

1... 10/TPU
2...

1... 11/TPU
2...

Transport Planning creates transport requirements via a set of background jobs that run in a Transport Planning subsystem.

When you start the subsystem the following jobs become active:

- Requirements monitor.
- Creation of requirements.
- Amendment of requirements (including order cancellations).
- Creation of pick requirements from sales order requirements.
- Creation of sales order requirements from pick requirements (via short despatch).



To start the background jobs, select the Start Background Tasks option



To end the background jobs, select the End Background Tasks option

Create Requirements



15/TPU

This batch job transfers order requirements into Transport Planning when the order line due date falls on or inside the time fence horizon, that is today's date plus the transport requirement lead time, defined on the company profile.

Use this to avoid passing order lines scheduled for delivery in the future which do not yet require planning of transport. You only need to start this batch job when you have set the transport requirement lead time to a value other than the default. You should schedule, with Machine Manager, to run this batch job automatically, typically on a daily overnight run.

This option considers order requirements for all transport centres within the transport company currently being used.



To run this batch job, select the Create Requirements option. Then select **F8=Submit** to submit the batch job.

Update Load History



20/TPU

Use this option to delete cancelled loads, and, delete and drop to history completed loads.



Note: You must have exclusive use of the company.

Depending on how you configured the transport centre, loads may be complete after any of the following process steps.

- Printing documentation - loads sheets/bill of lading.
- Confirm despatch.
- Authorisation of payment details.

This option deletes the following information and creates history details:

- Load headers
- Load drops
- Drop orders
- Order line details
- Load charge details
- Load text.

Route period history details are updated for the carrier/vehicle type combination for both completed and cancelled loads.

This option only processes loads if you have completed all associated AFI postings. That is you have posted all charge/payment details (if applicable) for completed loads, and cancelled the postings of all charge and/or payment details (if applicable) for cancelled loads.

Update Load History Selection Screen



To display this screen, select Update Load History.

Use this screen to select the company and transport centre you want to update.

TP967	User SP1	9/03/95 15:15:55
Update Load History		
Company?.. <u>Z1</u>		
Transport centre?.. <u>IC01</u>		
F3=Exit F4=Prompt F8=Update		

Fields:

Company

Enter the transport company.

Transport Centre

Enter the transport centre.



Select **F8=Update** to delete all cancelled loads, and delete and drop to history all completed loads.

Load Purge



21/TPU

Use this option to remove load history details from the system on a week stamp basis. Also, you can optionally delete payment and route period history details.

The following history details are deleted:

- Load headers
- Load drops
- Drop orders
- Order line details
- Load charge/payment details (optional)
- Route period history details (optional).

Purge Load History Details Screen



To display this screen, select the Load Purge option.

Use this screen to select the details for which you want to purge the historical details.

TP965	User SP1	9/03/95 15:16:40
Purge Load History Details		
Company?.. <u>Z1</u>		
Transport centre?.. <u>TC01</u>		
Week number from <u>9401</u>		
Week number to <u>9412</u>		
Purge charge history <u>0</u> (0=No, 1=Yes)		
Purge route/period details <u>0</u> (0=No, 1=Yes)		
F3=Exit F4=Prompt F8=Update		

Fields:

Company

Enter the transport company.

Transport Centre

Enter the transport centre.

Week Number From

Enter the week number from which to remove historical data.

Week Number To

Enter the week number up to which to remove historic data.

Purge Charge History

Enter one of the following:

0 - To retain charge data on the system

1 - To remove historic charge data from the system

Purge Route/Period Details

Enter one of the following:

0 - To retain the historic route/period date.

1 - To remove the historic route/period data.



Select **F8=Update** to start the batch job to purge the selected data.

Remove Audit Transaction Data



22/TPU

All master and transaction file data is audited according to standards, that is record images are written to separate audit files for all record additions, changes and deletions. These records are:

- After image for additions.
- Before and after image for changes.
- Before image for deletions.

Although all files are audited, those files directly associated with the processing of loads normally increase in size relatively quickly.

You can use this option to clear the audit files associated with the following load data:

- Load headers
- Load drops
- Drop orders
- Order line details
- Load charge/payment details.

This deletes, by default, all the audit data except for that created in the last two weeks.



Note: Before running this option, you must print the report of the required audit information.

Remove Audit Transaction Data Screen



To display this screen, select the Remove Audit Transaction Data option.

Use this screen to specify the date before which you want to remove audit details.

TP950	Z1 - Demonstration Company	User SP1	9/03/95 15:17:25
Remove Audit Transaction Data			
Date before which audit details are to be removed... <u>22/02/95</u>			
F3=Exit F8=Submit			

Fields:

Audit Removal Date

Enter the date in DDMMYY format.



Select **F8=Submit** to submit the batch job that removes all records created before the date and re-organise the audit files.

En Masse Route Transfer



23/TPU

Use this option to globally change a route across multiple loads. You can replace all references of a particular route with a revised route or you can revise a drop on a route to a new drop on the same route or a different route.

You can change load history details as well as the live data.

This option changes the following:

- Delivery profiles
- Carrier routes
- Load headers
- Load drops
- Drop orders
- Load charges
- Route history (optional)
- Load history (optional).



Warning: This option updates all occurrences of the route or drop and can therefore take a long time to run.



Note: You must stop the Transport Planning background processes while you run this option.

Global Route Change Screen



To display this screen, select the En-masse Route Transfer option.

Use this screen to specify which route or drop you want to change.



Warning: This option updates all occurrences of the route or drop and can therefore take a long time to run.

TP970	User SP1	9/03/95 15:17:47
Global Route Change		
Company?.. <u>Z1</u>		
Transport centre?.. <u>TC01</u>		
Original route?.. <u>YORKS1</u>		
Original drop <u>010</u>		
Revised route?.. <u>YORKS1</u>		
Revised drop <u>040</u>		
Update load history <u>1</u> (0=No, 1=Yes)		
This job will update ALL occurrences of the route and drop (including details on history files if selected). It may therefore take a long time to run, and will require exclusive use of Transport Planning. The background processors must be stopped while this job is running.		
PLEASE ENSURE THAT YOUR D.P. DEPARTMENT ARE INFORMED		
F3=Exit F4=Prompt F8=Update		

Fields:

Company

Enter the transport company.

Transport Centre

Enter the transport centre for which the route transfer is to take place.

Original Route

Enter the existing route code, all occurrences of which you want to replace with the revised route.

Original Drop

Enter the existing drop, all occurrences of which you want to replace with the revised drop.

Revised Route

Enter the revised route code. You must have defined this route to Transport Planning.

Revised Drop

If you entered an original drop, enter the revised drop.

Update Load History

Enter one of the following:

0 - If you do not want to change load history details.

1 - If you want to change the load history files.



Select **F8=Update** to transfer the load details.

Copy Item Transport Details



24/TPU

Use this option to copy item transport profiles across a number of different transport centres.

You can copy the details for a particular sales company processed by the centre, or for all sales companies processed by the centre.

You can restrict the items copied by range and you can copy them into a number of centres, by range.



Note: If you target a range of transport centres, only those centres you are authorised to are copied.



Note: All sales companies processed for the copy must already be processed by the targeted transport centres, that is sales company/stockroom definitions must be predefined to the target centres.

Copy Item Transport Details Screen



To display this screen, select the Copy Item Transport Details option.

Use this screen to select the transport details you want to copy.

TP974	User SP1	9/03/95 15:21:28
Copy Item Transport Details		
Company code?.. <u>Z1</u>		
Transport centre?.. <u>IC01</u>		
Copy the following details (leave Sales company blank if all details are to be copied) :-		
Sales company?.. <u>Z1</u>		
Item (from) <u>5001</u>		
Item (to) <u>5035</u>		
Into the following Transport Centres :-		
Transport centre (from) .?.. ____		
Transport centre (to) ...?.. ____		
F3=Exit F4=Prompt F8=Update		

Fields:

Company Code

Enter the transport company code from which you want to copy the item details.

Transport Centre

Enter the transport centre from which you want to copy the item details.

Sales Company

If you want to copy items for a single sales company, enter a sales company attached to the entered transport centre.

Item (From)

Enter the item from which you want to copy the details. You must have defined the item to Transport Planning within the entered transport centre, and, if you entered a sales company, sales company.

Item (To)

Enter the item code to which you want to copy details. You must have defined the item to Transport Planning within the entered transport centre, and, if you entered a sales company, sales company.

Transport Centre (From)

Enter the transport centre from which you want to copy item details. You must have defined the transport centre to the Copy From transport company.

Transport Centre (To)

Enter the transport centre to which you want to copy details. You must have defined the transport centre to the Copy From transport company.

If you leave this field blank, the transport centre (from) is the only transport centre into which data is copied.



Select **F8=Submit** to start the copy process.

Serious Error Report



30/TPU

Use this option to report and, optionally, delete serious errors logged to the error file.

A number of error conditions can occur during the planning processing cycle, and these may require manual intervention to process complete, associated loads.

These error conditions are trapped to ensure that any data problems found by the background transport requirements and amendment processes are noted. The error codes are as follows:

01 - Sales order not found. The sales order can no longer be found in Sales Order Processing when you create or amend the transport requirements.

02 - Pick note header not found. The pick note can no longer be found in Sales Order Processing when you create or amend transport requirements for the pick note.

03 - Item record not found. The inventory item master record cannot be found when you calculate transport requirements for the item, that is weights (gross, net and tare) and volumes.

04 - Item/stockroom record not found. The inventory item/stockroom profile record cannot be found when you calculate transport requirements for the item, that is weights (gross, net and tare) and volumes.

05 - Route specified not found. The default route defined to a delivery profile cannot be found when you calculate transport requirements for an order.

06 - Time out for requirements update. This error condition arises if a time out occurs when you are retrieving a locked sales order record. It is important that you finish creating order requirements before processing amendment requests. Under these conditions a sales order will be locked for the whole of the requirements creation, before processing an amendment request. If the amendment request finds the sales order locked it waits and retries the order for five minutes, before issuing a serious error and bypassing the order amendment request.

07 - Details changed after AFI posting. If a load is set back to a pending release state after rating/payment information has already been posted by AFI, a serious error is issued. This could arise if you have released and rated a load and then set back to a pending state, because of changes in the transport requirements.

08 - Details changed after manual override. Transport Planning automatically maintains planned and actual capacities (weights, volumes and numbers of containers) until a manual override takes place that maintains actual capacities in isolation, (via Build or Maintain Loads Order Amendment). If a manual override has taken place and a request is made to amend associated order transport requirements, only planned capacities are amended and a serious error is issued.

09 - Global route change warning. Issued as part of a global route change request for each carrier/route combination affected.

10 - Possible capacity problems. As part of the conversion of sales order transport requirements to pick note transport requirements (and the reverse process, for example, for pick note cancellations), weight and/or volume capacity errors can arise for vehicle types associated with assigned loads. If this occurs a serious error is issued.

11 - Item transport profile not found. The transport item profile record cannot be found when you calculate the transport requirements for the item, that is, weights (gross, net and tare) and volumes.



Note: This report details all errors logged for all defined transport planning companies.

Serious Errors Report Submission Screen



To display this screen, select the Serious Error Report option.

Use this screen to enter the selection criteria for the Serious Error Report.

```

TP498A                                     User SP1                               9/03/95
                                           15:22:04

Serious Errors Report

Print report . . . . . 1 (1=Yes, 0=No)
Clear serious error file . . . . 0 (1=Yes, 0=No)

F3=Exit      F8=Submit

```

Fields:

Print Report

Enter one of the following:

- 0 - If you do not want to print the serious error report.
1 - To print the serious error report.

Clear Serious Error File

Enter one of the following:

- 0 - If you do not want to clear the serious error file of data after printing the serious error report.
- 1 - To clear the serious error file after printing the serious error report.



Note: This operates across all transport companies. We strongly advise you print the report before you clear the serious error file.



Select **F8=Submit** to start the batch job.