

-
-
-
-
-

Chapter 3

Utilities



Company Profile Maintenance



1/VSU

The company profile maintenance allows you to define a variety of parameters at company level which determine the running of the Vendor Scheduling application. The company details must be set up prior to any other aspect of the system.

You can enter descriptions and lengths for the three time periods you can set up on a schedule. The standard time spans are held as the standard default but may be overridden when maintaining contracts.

You can also specify override time spans which will override all time periods set in contracts, and plan schedules accordingly.

Maintain Profile Records Screen



Select Company Profile Maintenance from the menu to display the Maintain Profile Records screen.

This screen allows you to select the company that you want to maintain records for.

```
VS010          Vendor scheduling company profile      User GBJBAPH2  30/11/95
                                                    11:29:08

Maintain profile records
Sel  Company
-    3H Distribution V3 -> Financials

1=Select
F3=Exit

05-03  SF  MW  KS  IM  II  KENB20A  PET087S1
```

Fields:

Sel

Select. Enter 1 against the required company.



Press **Enter** to display the first Company Profile Maintenance screen.

Company Profile Maintenance Screen 1



Press **Enter** on the Maintain Profile Records screen to display the first Company Profile Maintenance screen.

This screen allows you to define the significant changes and the horizons to be used as defaults for the vendor scheduling system.

VS010		Vendor scheduling company profile		User	GBJBAPH2	7/09/95
						13:59:25
Company profile maintenance						
Company code :		DH	Company name..... ARROWHEAD SYSTEMS LIMITED			
Authority in days			Standard	Override		
FABRICATION	FAB		---	---		
MATERIAL	MAT		---	---		
FORECAST	FRC		---	---		
Override horizon		0 (0/1)				
F3=Exit F12=Previous						
00-02		SF	MW	KS	IM	II KENB20A PET150S1

Fields:

Authority

Enter a name to represent each time period for all your Vendor Schedules. The time periods are designed to split up the schedule so that orders on a schedule can be classified by a period. For example, time periods can be called:

FABRICATION

MATERIAL

FORECAST

Abbreviation

Enter a three character abbreviation to represent the time periods.

Standard

Enter the time, in days, that you want this time period to last. All demand on a schedule falling into this time span is classified as belonging to this period. (Period one, two or three).

This field is mandatory.

Override

Enter the number of days you want this override time period to last. All demand on a schedule falling into this override time span is classified as belonging to this period. (Period one, two or three).

When the override horizon is set to 1, this field is mandatory.

Override Horizon

Enter one of the following:

0 - to leave standard item periods as they are.

1 - to override standard item periods. Allocate them the same time spans you entered in the Override fields.

The next time you run Vendor Sourcing a window is displayed with the override time spans, informing you that all sourced schedules will adhere to those overrides irrespective of what has been set up for them in the contracts.



Select **Enter** to display the second Company Profile Maintenance screen.

Company Profile Maintenance Screen 2



Select **Enter** on the first Company Profile Maintenance screen to display the second Company Profile Maintenance screen.

This screen allows you to define the print time buckets and contract numbers for the Vendor company.

```
VS010      Vendor scheduling company profile      User GBJBAPH2      7/09/95
                                                13:59:50

Company profile maintenance

Company code : DH   Company name..... ARROWHEAD SYSTEMS LIMITED

Password required on contract authorization. 0 (0/1)   Password..
Password for altering contract accumulated values.....

Schedule print time buckets
FABRICATION ..... 1 (1=Days, 2=Weeks)
MATERIAL ..... 1 (1=Days, 2=Weeks)
FORECAST ..... 2 (2=Weeks, 3=Periods)

Last contract number used ..... 000000

Default contract number initial letter..... _

Allow entry of manual contract number..... 1 (0/1)

-----
F3=Exit F12=Previous

07-47  SF  MW  KS  IM  II  KENB20A  PET158S1
```

Fields:

Password Required On Contract Auth

Use this field to set up a password for contract authorisation. Enter one of the following:

- 0 - No. A password is required.
- 1 - Yes. A password is not required.

Password

When the Password Required flag is set to 1, a password must be entered. This field does not display the password as you enter it.

Password For Altering Contract Accumulated Values

Enter the password required in order to change the contract accumulated values.

Time Buckets

Enter the time bucket with which the schedule order amounts are accumulated when the schedules are printed. Enter one of the following:

- 1 - Unit of time = Days
- 2 - Unit of time = Weeks
- 3 - Unit of time = Periods.



Note: Time periods are only accumulated in days but the time buckets for printing purposes may be different.

Last Contract Number

The contract number is sequentially increased each time a contract is raised. The default is the last contract number used. When maintaining a company for the first time, the default is 0.

Default Contract Number Initial Letter

This is the letter which will prefix any system generated contract number. This field is mandatory.

Allow Entry Of Manual Contract Number

Enter one of the following:

0 - to prevent the use of manual contract numbers.

1 - to allow the use of manual contract numbers. This is the default.



Press **Enter** to display the third Company Profile Maintenance screen.

Company Profile Maintenance Screen 3



Press **Enter** on the second Company Profile Maintenance screen to display the third Company Profile Maintenance screen.

This screen allows you to enter more information to the Vendor company details.

VS010	Vendor scheduling company profile	User GBJBAPH2	1/11/95 12:02:10
Company profile maintenance			
Company code : DH Company name..... ARROWHEAD SYSTEMS LIMITED			
Default planner code..... █			
More than 1 contract per purchase order @ (0/1)			
Default purchase order generation level 3 3=One per delivery 4=One per requirement			
Allow contract values to be exceeded .. @ (0/1)			
F3=Exit F8=Update F12=Previous			
10-42	SF	MW	KS IM II KENB20A PET087S2

Fields:

Default Planner Code

Enter the Default Planner Code which will be used in Schedule Maintenance.

More Than One Contract Per Purchase Order

This flag indicates if the system is allowed to generate multiple contracts on the same purchase order. Enter one of the following:

- 0 - To disallow multiple contracts.
- 1 - To allow more than one contract per purchase order.

Default Purchase Order Generation Level

This field is used for items that have no associated contract. Enter one of the following:

- 3 - Purchase orders are generated for each delivery.
- 4 - Purchase orders are generated for each requirement.

Allow Contract Values To Be Exceeded

Enter one of the following:

- 0 - Contract values can not be exceeded. This field will default to 0.
- 1 - Contract values can be exceeded.



Select **F8=Update** to confirm the details on the Company Profile Maintenance screens and display the Maintain Profile Records screen.


Schedule Purge

2/VSU

This option allows you to remove old schedules to enable you to maintain your system. When you specify a date, all schedules created before that date are purged.



Select Schedule Purge to display the Schedule Purge Screen.



The screenshot shows a terminal window with the following text:

```
VS074      Distribution V3 -> V3 Financials      User GJBAPH2      7/09/95
Schedule purge
Delete schedules created before.... █
F3=Exit  F8=Submit
05-38    SF      MW      KS      IM      II  KENB20A  PET158S1
```

Fields:

Delete Schedules Created Before

Enter a valid date. All schedules created before this date are deleted.



Select **F8=Submit** to submit the delete request to the job queue.