

-
-
-
-
-

Chapter 1

Company Parameters Maintenance



Company Profile File



1/WOP

Use this option to set up and maintain the fields that control how Workshop Management works for a specific company. This is where you make many key decisions about how you operate Workshop Management. You mainly use this option when you install the system.



Note: You must have exclusive use of Workshop Management to use this option.

A company is completely self-contained within the module. It may be sub-divided into branches, but these branches all operate under the controlling parameters defined for the company.

The company profile is where you decide which other modules (the ledgers, Sales Order Processing, Inventory Management, and so on) integrate with Workshop Management.

If you do integrate other modules, then you can use:

- Inventory to check the engineer's stock.
- SOP to price parts.
- Technical Reporting to automatically send information to update Inventory stock movements, and to generate invoices.

Company Profile Maintenance Selection Screen



To display this screen, select Company Profile File (Maintenance).

Use this screen to either enter a new company code, or select the company you want to maintain.

SS006	JBA Demonstration Company	USER BRERETM	24/06/93 14:53:52
-------	---------------------------	--------------	----------------------

Company Profile Maintenance

1 Company name	Code
<u>1</u> Demonstration Company	ZM

Enter company code to maintain.. __

1=Select company
F3=Exit

Fields:

1

Selection field. Enter 1 against the company to maintain.

Enter Company Code to Maintain

If you are setting up a new company, enter a two character company code. You can also enter an existing company, so you do not have to scroll through the list of companies.



Select a company using the selection field, to automatically display the Company Profile Maintenance Screen 1, or

Select a company, by entering the code, then press **Enter** to display the Company Profile Maintenance Screen 1.

Company Profile Maintenance Screen 1



To display this screen, select a company, on the Company Profile Maintenance Selection screen.

Use this screen to enter the basic details, such as job and invoice numbers, for the selected company.

SS006	JBA Demonstration Company	USER BRERETM	8/03/94 13:52:45
Company Profile Maintenance			
Company Code	ZM	Company Name	<u>Demonstration Company</u>
Last Job Number			<u>0501221</u>
Last Invoice Number			<u>500676</u>
Last Credit Note Number			<u>900022</u>
Last Contract Number			<u>0000125</u>
New Contract Number at Renewal ?		(1=Yes/0=No)	<u>1</u>
Validate Post Codes ?		(1/0)	<u>0</u>
Use geocode/UK post code rules for team assignment		(1/2)	<u>2</u>
Manual Engineer Allocation across Branch ?		(1/0)	<u>1</u>
Assign by Territory (1) or Alternative (0) Engineer			<u>0</u>
Hard Copy Job Audit Log Required ?		(1/0)	<u>1</u>
Accounting Period			<u>03</u>
Accounting Year			<u>94</u>
F3=Exit F12=Previous			

Fields:

Company Name

For a multi-company environment, the name defaults from Application Manager. Use the Maintain Company Parameters option in Application Manager to set up the company name.

For a stand-alone installation, enter up to 30 alphanumeric characters.

Last Job Number

Enter the first job number. When the system assigns the next job number, this field increments by 1, so the field always shows the last job number used. Once you start using Workshop Management, do not change this number.

Last Invoice Number

Enter the first invoice number. When the system assigns the next invoice number, this field increments by 1, so the field always shows the last invoice number used. Once you start using Workshop Management, do not change this number.

Last Credit Note Number

Enter the first credit note number. When the system assigns the next credit note number, this field increments by 1, so the field always shows the last credit note number used. Once you start using Workshop Management, do not change this number.



Tip: When you post invoices and credits from System 21 applications into the General Ledger, or elsewhere, the system attaches a prefix to show where the invoice or credit originated.

The prefixes for Workshop Management are I for invoices, and C for credits. Therefore you should avoid using I and C as prefixes in other modules.

Last Contract Number

Enter the first contract number. When the system assigns the next contract number, this field increments by 1, so the field always shows the last contract number used. Once you start using Workshop Management, do not change this number.

New Contract Number at Renewal

Enter one of the following:

- 0 - To use the existing contract number when you renew the contract.
- 1 - To assign a new contract number when you renew the contract.

Validate Post Codes

Enter one of the following:

- 0 - To stop the system validating the post code fields. You can then use the post code fields for any geocode you devise.
- 1 - To make the system check that the post code fields conform to the UK postcode format standards. The system transfers the postcode from the module you set it up in (Accounts Receivable), and highlights it here if the post code format is not correct.

Use Geocode / UK Post Code Rules For Team Assignment

To define how the system matches the teams, enter one of the following:

- 1 - Geocode. Workshop Management first looks for a complete geocode match between customer and team. If it finds no match, it makes successive tests, reducing the customer's geocode by one character each time, the final test being for a match on just the first character of the customer's geocode.
- 2 - UK Postcode. Workshop Management first looks for a complete postcode match between customer and team. If it finds no match, it makes successive tests, reducing the customer's postcode by one character each time. If the postcode starts with two alpha characters, the final test is for a match on the first two characters of the customer's postcode. Workshop Management does not test on the first character, so, for example, it never reduces BR for Bristol to B for Birmingham.

If there is no match, Workshop Management assigns the job to a default team *DF, authorised to service anything. You can assign the actual team to work on the job during call logging, or in Work Control.

Manual Engineer Allocation Across Branch

Enter one of the following:

0 - To manually assign only engineers based at the branch of the piece of equipment.

1 - Within Job Management, you can manually assign an engineer from any branch to a job.

Assign By Territory Or Alternative Engineer

Enter one of the following:

0 - To assign another engineer from the engineer's alternative engineers list.

1 - To assign another engineer from the same territory.

If automatic assignment finds that the selected engineer is not available, it uses the value in this field.

Hard Copy Job Audit Log Required

Enter one of the following:

0 - If you do not require an audit report of all changes to jobs.

1 - If you require an audit report that prints every job added, deleted or modified.

Accounting Period

Enter the posting period for all invoice generating routines in Workshop Management. The system makes Accounts Receivable postings to the Accounts Receivable open period, if it is later than the period indicated here.

You must manually reset this at each period end.

Accounting Year

Enter the posting year for all invoice generating routines in Workshop Management. The system makes Accounts Receivable postings to the Accounts Receivable open period / year, if it is later than the year indicated here.

You must manually reset this at each year end.



To display the Company Profile Maintenance Screen 2, press **Enter**.

Company Profile Maintenance Screen 2



To display this screen, press **Enter**, on the Company Profile Maintenance Screen 1.

Use this screen to enter the relationships with the other modules, and to set up General Ledger accounts.

You set up General Ledger accounts on the transactions posted to the General Ledger from the generation of contract and job invoices. If you use Advanced Financial Integrator, establish the accounts in AFI.

W0006	GB Demonstration Company	USER GBJBANB1	9/04/98 14:57:18
Company Profile Maintenance			
Company Code	Z1	Company Name	Z1 - Demonstration Company
Sales & General Ledgers Active	1 (1=Yes/0=No)		
Inventory Active	1 (1/0)		
S.O.P. Active	1 (1/0)		
Currency Rate Code ?	PERQ		
General Ledger Account Codes:			
Sales Ledger Control	411100		
VAT Control	445700		
Service Sales	702000		
Deferred Income	4860130		
Default Labour Rate Price List Code	PL1		
Default Scheduled Service Visit Profile	2PA		
No. of Service Periods to be Loaded	012		
Minimum No. of Loaded Service Periods	003		
F3=Exit F4=Prompt F12=Previous			

Fields:

Sales & General Ledgers Active

Enter one of the following:

- 0 - To use Workshop Management as a stand-alone application.
- 1 - To integrate Workshop Management with General Ledger and Accounts Receivable.

Inventory Active

Enter one of the following:

- 0 - To use Workshop Management as a stand-alone application.
- 1 - To integrate Workshop Management with Inventory Management.

SOP Active

Enter one of the following:

- 0 - To use Workshop Management as a stand-alone application.
- 1 - To integrate Workshop Management with Sales Order Processing.

Currency Rate Code

Enter a currency rate set up in the General Ledger.

The currency rate converts contract, or job, invoice values from the customer's prime currency to the customer's base currency. You can overwrite this default value at both customer and sundry invoice / credit note levels.



Note: The field only displays if Accounts Receivable operates as a multi-currency ledger.

If you are adding a new company, this field defaults to the currency rate set up on the Accounts Receivable company profile.

Sales Ledger Control

Only use this field if you are not using AFI.

Enter the GL debtors control account used for posting sales revenue.

VAT Control

Only use this field if you are not using AFI.

Enter the GL VAT output account used for posting sales revenue.

Service Sales

Only use this field if you are not using AFI.

Enter the GL sales account used for posting sales revenue.

Deferred Income

Only use this field if you are not using AFI.

Enter the GL account for posting deferred revenue from service contracts invoiced in advance.

Default Labour Rate Price List Code

Enter a price list.

Job pricing uses the default price list when calculating labour charges. The system uses this company default only if it finds no price list for the model concerned.

Default Scheduled Service Visit Profile

Enter a schedule visit profile.

Contract maintenance and renewal use the default profile, when you generate a maintenance visit schedule, if the equipment has no profile defined for the contract, the model or the model group.

A visit profile generates scheduled service visits for each piece of equipment on a contract. The system looks for the relevant profile according to the following hierarchy:

1. Use the SVP on the contract header.
2. If there is none, use the model file SVP.
3. If there is none, use the model group file SVP.
4. If there is none, use the company profile SVP.

5. If there is none, generate no visits.

Otherwise, the system generates visits using the first SVP code found, when you select option 8 on the Equipment screen.

No Of Service Periods To Be Loaded

Enter the maximum number of service periods for which you generate scheduled maintenance visits. The scheduled visit profile (SVP) for a contract lasting for more than a year should include a repeat indicator (*RP), otherwise the system only generates visits for the first year of the contract.

As an example, if you define monthly service periods, set the No Of Service Periods To Be Loaded field to 24, with an SVP for four visits a year, plus *RP, this generates eight visits.

You must run the Load PM Jobs option to convert these new visits to actual jobs.

Minimum No Of Loaded Service Periods

Use this at period end, to limit the extension of scheduled service visit generation.

When you run the Period End Routines option, you extend the schedule of planned service visits. You also specify a period in the Start Next Profile Load From field on the Contract Equipment Maintenance Visits Screen.

When Period End Routines generates further scheduled visits, these are for the minimum number of periods entered here, ahead of the Start Next Profile Load From date.

You must run Load PM Jobs to convert these new visits to actual jobs. You can limit planned maintenance jobs to one machine only, or cover all machines on the site due for maintenance in the same period.



Press **Enter**. If you have specified control accounts, and you use extension codes in your General Ledger chart of accounts, then an extension code window displays for each account. Select the correct extension codes. Press **Enter** on each extension code window, to display the Company Profile Maintenance Screen 3.

If you have not entered any control accounts, press **Enter**, to display the Company Profile Maintenance Screen 3.

Company Profile Maintenance Screen 3



To display this screen, on the Company Profile Maintenance Screen 2, press **Enter**.

Use this screen to enter the job defaults for the company.

W0006	GB Demonstration Company	USER GBJBANB1	9/04/98 14:58:39
Company Profile Maintenance			
Company Code	Z1	Company Name	Z1 - Demonstration Company
One Machine per PM Job		<u>0</u> (1=Yes/0=No)	
Apportion Travel Time across Job Categories		<u>0</u> (1/0)	
Revenue Analysis Period Based on		<u>0</u>	
Visit Date (1) or Invoice Date (0)		<u>0</u> (1/0)	
Break Times Entry in Technical Reporting Required		<u>0</u>	
Technical Reporting by Times (1) or Hours (0)		<u>0</u> (1/0)	
Engineers Diary Active		<u>1</u> (1/0)	
Mileage to be Charged By:			
Standard Mileage Value		<u>1</u> (1/0)	
Mileage Zones		<u>0</u> (1/0)	
Actual Miles Driven		<u>0</u> (1/0)	
F3=Exit F12=Previous			

Fields:

One Machine Per PM Job

Enter one of the following:

0 - To list all the items due for service in the same period on one job number.

1 - To generate a separate job number for each service item, using the Load Planned Maintenance Jobs option.

To allow more than one machine on a job, see Codes/Parameter File Maintenance.

Apportion Travel Time

Enter one of the following:

0 - To accrue the travel time to the first job category entered.

1 - To split the travel time across the job categories, in proportion to the labour time booked for each job category.

Revenue Analysis By Visit/Invoice Date

Enter one of the following:

0 - To base the revenue and cost analysis on the date you invoiced the visit.

1 - To base the revenue and cost analysis on the date of the engineer's visit.

Break Times Entry

This is for future development.

Technical Reporting In Hours/Minutes

Enter 0. You can report in hours and minutes not by clock time.

Engineers Diary Active

This field is for future development. Enter 1 to display the Reserved Time Buffer fields on the next screen, but these too are for future development.

You can access an engineer diary for non-job activities and job appointments by selecting **F10=Diary** from the Work Control Selection Screen.

Mileage To Be Charged By



Note: Only set one of the mileage fields to 1.

Standard Mileage Value

Enter one of the following:

0 - To not charge mileage by standard mileage value.

1 - To charge mileage by standard mileage value. The Charge Standard Mileage Value field on a Customer's Additional Service Details defaults to 1.



Note: If you have set the Zone Code Mandatory field to 1 in System Parameters Maintenance, Screen 1, this field should be 0 - No.

Mileage Charged By Zone

Enter one of the following:

0 - To not charge mileage by zone.

1 - To charge mileage by zone. The Charge Mileage Zones field on a Customer's Additional Service Details defaults to 1.



Note: If you have set the Zone Code Mandatory field to 1 on System Parameters Maintenance Screen 1, this field should be 1 - Yes.

Mileage Charged By Distance Driven

Enter one of the following:

0 - To not charge mileage by distance driven.

1 - To charge mileage by distance driven. You enter the actual distance driven at technical reporting.



Note: If you set the Zone Code Mandatory field to 1 on System Parameters Maintenance Screen 1, this field should be 0 - No.



To display the Company Profile Maintenance Screen 4, press **Enter**.

Company Profile Maintenance Screen 4



To display this screen, on the Company Profile Maintenance Screen 3, press **Enter**.

The service window start and finish times show the standard working hours per day. Engineer scheduling and the calculation of target response dates and times use these times.

W0006	GB Demonstration Company	USER GBJBANB1	9/04/98 14:59:31
Company Profile Maintenance			
Time interval:	0:30	(HH:MM)	
Service window - Start:	8:00 a	(HH:MM a/p/n)	
Service window - Finish:	5:30 p		
Display diary from:	8:00 a	(defaults to system time)	
Reserved time buffer:			
Day	From	To	
Mon	8:00 a	5:30 p	
Tue	8:00 a	5:30 p	
Wed	8:00 a	5:30 p	
Thu	8:00 a	5:30 p	
Fri	8:00 a	5:30 p	
Sat	0:00 a	0:00 a	
Sun	0:00 a	0:00 a	
Display reserve time as available time (0=No, 1=Yes) 0			
F3=Exit F12=Previous			

Fields:

Time Interval

This field is for future development.

Service Window - Start

Enter the opening time using the 12 hour clock and a for morning, p for afternoon, n for noon and blank for midnight.

Service Window - Finish

Enter the closing time using the 12 hour clock and a for morning, p for afternoon, n for noon and blank for midnight.

When logging a call, the system calculates the response time, and the target time, using the service window. It is only effective on the days defined as working days in the Codes/Parameter Maintenance option (major type DAYT). You must have set up working days in the Daily Calendar File Maintenance option.



Note: Any other fields displayed are for future development.



To display the Company Profile Maintenance Screen 5, press **Enter**.

Company Profile Maintenance Screen 5



To display this screen, on the Company Profile Maintenance Screen 4, press **Enter**.

Use this screen to enter the defaults for the workshop jobs.

W0006	GB Demonstration Company	USER GBJBANB1	9/04/98 15:00:08
Company Profile Maintenance			
Workshop mode (0) OR BOTH Service and Workshop (1)..... 1			
Calculate Warranty from Installation date () or Purchase date (1): -			
Default Accessory list code.....?			
Credit call processing - special status () or message only (1)... -			
Technician return stock - status determination by technician (1)... 0			
Technician return stock - received as available () or frozen (1)... 0			
Prefix for Job estimates..... E			
Next available estimate number..... 1			
Prefix for Job quotations..... Q			
Next available quotation number..... 1			
F3=Exit F4=Prompt F8=Update F12=Previous			

Fields:

Workshop Mode Or Both Service And Workshop

Enter one of the following:

- 0 - To use this company only as a workshop company.
- 1 - To use this company as both a workshop and service company.

Calculate Warranty

Enter one of the following:

- Blank - To calculate the warranty from the installation date.
- 1 - To calculate the warranty from the purchase date.

Default Accessory List Code

Enter the default accessory list for this company. You can change this when you create a job.

Credit Call Processing

Enter one of the following:

- Blank - To automatically set a call status to 07, if a customer is on credit stop within Accounts Receivable.
- 1 - To display a message during job creation if a customer is on credit stop within Accounts Receivable.

Technician Return Stock

Status Determination By Technician

Enter one of the following:

- 0 - To automatically determine the stock status of returned goods.
- 1 - To allow the technician to determine the stock status of returned goods.

Received As Available Or Frozen



Note: This field is only relevant if you have set the previous field to 0.

Enter one of the following:

- 0 - To receive returned stock as available, this is the default.
- 1 - To receive returned stock as frozen.

Prefix For Job Estimates

Enter a letter to use as the prefix to differentiate estimates from real invoices. This cannot be I, which Invoices use, or C which Credit Notes use.

Next Available Estimate Number

Enter the first estimate number. When the system assigns the next estimate number, this field increments by 1, so the field always shows the last estimate number used. Once you start using Workshop Management, do not change this number.

Prefix For Job Quotations

Enter a letter to use as the prefix to differentiate quotations from real invoices. This cannot be I, which Invoices use, or C which Credit Notes use.

Next Available Quotation Number

Enter the first quotation number. When the system assigns the next quotation number, this field increments by 1, so the field always shows the last quotation number used. Once you start using Workshop Management, do not change this number.



To save any entries you have made, select **F8=Update**.

Codes/Parameter File Maintenance



2/WOP

Use this option to set up many codes used widely throughout the system to assist in data entry, validation and analysis.



Tip: The difference between this option and the Codes/Parameter Maintenance option in the Utilities area is that this does not include system supplied parameters.

You can change a user code to a system code by adding * to the beginning of the description.

Codes/Parameter Selection Screen



To display this screen, select Codes/Parameter File (Maintenance).

Any parameter consists of the parameter type, the four-character code itself, and parameter IDs. Parameter IDs are the codes defined to that parameter.



Tip: The parameter type corresponds to the Major Type parameter in other modules, and the parameter ID to the Minor Type.

W0378	Z1 - GB Demonstration Company	USER GBJBANB1	9/04/98
	CENTRAL WORKSHOP		15:03:41
Codes/Parameter Maintenance			
Parameter Type	_____	Enter PTDS to define new type	
Parameter I.D.	_____		
1	Type	Description	
-	CCAL	Customer Calendar Codes	
-	CCRC	Contract Cancellation Reason	
-	CHGT	Miscellaneous Charge Types	
-	CLMT	Warranty Claim Type	
-	CODC	Condition Code	
-	COLM	COLLECTION METHOD	
-	CONC	IRIS Condition Code	
-	CONF	Configuration code	
-	CORA	Corrective actions	
-	CRDR	Credit Assessment Reason Codes	+
1=Select			
F3=Exit F4=Code Selection			

Fields:

Parameter Type

To enter or amend a parameter type, enter PTDS.

Parameter ID

To maintain a parameter ID, enter the ID. You must also enter a parameter type.

1

Selection field. Enter 1 against a parameter type to display a list of existing parameter IDs.



Warning: Do not amend or delete any of the supplied parameter types unless advised to do so by your agent, you may get unpredictable results.



Enter a parameter type and ID, then press **Enter** to display the Codes/Parameter Maintenance Screen.

Codes/Parameter Maintenance Screen



To display this screen, select the parameter type and press **Enter** on the Codes/Parameter Maintenance Selection Screen.

Use this screen to define the format of parameter IDs.

```

W0378          Z1 - GB Demonstration Company   USER GBJBANB1   9/04/98
                  CENTRAL WORKSHOP              15:05:44

Codes/Parameter Maintenance

Parm Type      PTDS
Parm I.D       DAYT          AMENDMENT

Description (Maximum) Size....: 30
I.D. Size....: 1 & Format....: C (C=Character/N=Numeric)

Description.: Day Type          Max size 30

Value required....: -      Value Description
(1=yes)           Value Type Description

Character 1 req?...: 1 (1=yes/0=no) Description Deferred Rev. Acct. daw (1/0)?
Character 2 req?...: 1 (1=yes/0=no) Description Workinc daw (1/0)?
Character 3 req?...: 1 (1=yes/0=no) Description Shift Profile

F3=Exit F11=Delete F12=Previous
  
```

Fields:

Description (Maximum) Size

Enter a value, between 1 and 30, to define how long the description of the parameter IDs can be.

ID Size

Enter a value, between 1 and 4, to define the length of the parameter IDs of this parameter type.

Format

Enter one of the following:

C - If the parameter ID must be characters only.

N - If the parameter ID must be numeric.

Description

Enter a parameter type description of up to 30 characters.

If you start the description with the character *, you can only maintain this parameter type from the Utilities option. You can use this as a security measure.

Value Required

Enter one of the following:

Blank - If parameter IDs for this type do not require a value.

1 - If you must enter a value (either an absolute value or a percentage) when maintaining parameter IDs of this parameter type.

Value Description

This field is only relevant if you entered 1 in the Value Required field. Enter the text to display on the Parameter ID Maintenance screen next to the field where you enter the value.

Value Type Description

This field is only relevant if you entered 1 in the Value Required field. Enter the text to display on the Parameter ID Maintenance screen next to the field where you enter P for percentage or V for value.

Character N Req

Enter one of the following:

0 - If you require no field.

1 - If you require a single numeric field when maintaining parameter IDs of this parameter type.

Workshop Management holds these entries under the system maintained parameter types, PMC1, PMC2, PMC3.

Character N Description

If you entered 1 in the Character N Req field, this description indicates how the system uses the character flag.

The system stores these entries under the parameter types, PMC1, PMC2, PMC3.

Allow Blanks

Enter one of the following:

0 - To force entry of 1 or 0 in the Character 1 or Character 2 fields when you maintain the parameter IDs.

1 - To allow blank entries in the Character 1 or Character 2 fields when you maintain the parameter IDs.



Tip: The rule does not apply to entries or blanks in the (2 character) Character 3 field.



Warning: Do not amend or delete any of the supplied parameter type definitions unless specifically advised to do so by your agent, as unpredictable results may occur.



Press **Enter** to display the Existing Parameter IDs screen.

Existing Parameter IDs Screen

 To display this screen, select a parameter on the Codes/Parameter Maintenance Screen.

Use this screen to select the parameter you want to maintain.

SS608	Demonstration Company	USER BRERETM	18/08/93 13:26:09
Parameter Code Selection			
Parameter Type DAYT Day type			
1	Code	Description	
—	B	Bank holiday	
—	C	Closed	
—	S	Saturday/Sunday	
—	W	Working day	
Enter selection or required code _			
1=Select			
F3=Exit F12=Previous			

Fields:

1

Enter 1 against a parameter code to display the detail screen.



Note: You should not create more than 10 parameter IDs for parameter type DAYT.



Tip: If you set up more than 10, call logging ignores from the 11th code. As the Working Days code is often W, and therefore at the end of the list of codes, the system ignores this code, which leads to unpredictable results.



Select a parameter ID to display the Parameter ID Maintenance screen.

Parameter ID Maintenance Screen

 To display the Parameter ID Maintenance screen, select a parameter code from the Existing Parameter IDs screen.

Use this screen to enter the details for the selected parameter type.

SS008	Demonstration Company	USER BRERETM	18/08/93 13:26:33
Codes File Maintenance			
Parm Type	DAYT	Day type	
Parm I.D	B	AMENDMENT	
Description.: <u>Bank holiday</u>		Max size	30
Deferred rev. a/c day (1/0)?	<u>1</u>		
Working day (1/0)?	<u>0</u>		
F3=Exit F11=Delete F12=Previous			

Fields:

Description

Enter the parameter ID description.

Value or Percentage Code

Enter one of the following:

P - Percentage.

V - Value.

Actual Percentage or Value Figures

Enter the required value, either a percentage or absolute value.

Value Field(s)

The system only displays these fields if you specify extra values and characters for the parameter type.

Enter the required values. The system stores these under parameter types PMC1, PMC2 or PMC3.

 To save any entries, press **Enter**.

Calendar File Control



3/WOP

Use this option to define the number of service periods per year and set the current period and year at system set-up time.



Note: You must have exclusive use of the company.

A service period is a specific number of days, defined by a start and end date.

You can enter between 1 and 99 service periods per calendar year, but typically they are a week, 4 weeks, or a month long.



Tip: You must set up the current service period and year when you install Workshop Management. Thereafter, when you run the Period End Routines it automatically increments the period (and year, when necessary).

Calendar Control Maintenance Screen



To display this screen, select Calendar File
Control (Maintenance).

Use this screen to define the basic details for the current year.

SS003	Demonstration Company CENTRAL BRANCH	USER BRERETM	9/09/93 16:31:32
Calendar Control Maintenance			
Current Year	93		
Current Week	34		
Current Period	34		
No. of Weeks This Year	52		
No. of Weeks Last Year	52		
No. of Periods This Year	52		
F3=Exit F11=Delete			

Fields:

Current Year

Enter the current year as two digits in the range 00 to 99.

Current Week

Enter the week number in the range 01 to 53.

Current Period

Enter the current period number, in the range 01 to 99.

No. Of Weeks This Year

Enter the number of weeks. This must be a value of either 52 or 53.

No. Of Weeks Last Year

Enter the number of weeks in last year. The value entered must be 52 or 53.

No. of Periods This Year

Enter the number of periods in this (current) year as 2 digits in the range 01 to 99.



To update, press **Enter**.



Tip: Once set up, these fields are system-maintained.

Daily Calendar File Maintenance



4/WOP

Use this option to define and maintain a calendar of service and accounting periods.

You use this option, when you install Workshop Management, to define the calendar for current, previous and future years.



Note: You must create an extra dummy year, one year previous to the first year actually required in the system. This is so you can define service and accounting years, or both, which span two calendar years. The Rebuild Period End Dates File option does not create period end date records for the first year defined on the daily calendar file.

Use this option after installation to define all future years.



Note: You must have exclusive use of the company to do this.

Implications

Workshop Management uses service periods to control the scheduling of planned maintenance jobs and to monitor all jobs processed.

Workshop Management uses accounting periods to control the postings to Accounts Receivable and the General Ledger, from job and contract invoicing. This is particularly in relation to apportioning deferred revenue from contract invoices.



Note: The calendar file data is essential, without it, you cannot create contracts, process jobs, or raise invoices.

Daily Calendar Maintenance Screen



To display this screen, select the Daily Calendar File Maintenance option.

Use this screen to enter the calendar you want to maintain or create.

Fields:

Year

Enter the year to add or update.

If you are installing Workshop Management for the first time, create a dummy year, one year previous to the first calendar year required.

Make sure that you set up the calendar far enough into the future, so you can generate scheduled visits.



To display the Set Up Period End Dates Screen, press **Enter**.

Set Up Period End Dates Screen



To display this screen, on the Daily Calendar Maintenance Screen, enter the appropriate year and press **Enter**.

For each month, you classify the day type for each day, such as Bank Holiday, Saturday, Sunday, or working day. You define the day types in the Codes/Parameter File Maintenance option under DAYT. In addition, to show the end of service and accounting periods, mark the relevant dates E.

```

SS969          Z1 - C&T TEST COMPANY          USER GBJBAJKG    6/03/96
                  BIRMINGHAM BRANCH              14:44:02
Daily Calendar Maintenance

Year: 96
1st Service period - end date: 31/01/96
1st Account period - end date: 31/01/96

          1          2          3
        1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1
January
DAY TYPE  W W W W W W W W W W W W W W W W W W W W W W W W W W W W
SERVICE PD  - - - - - - - - - - - - - - - - - - - - - - - E
ACCOUNT PD  - - - - - - - - - - - - - - - - - - - - - - - E

F3=Exit  F4=Prompt  F8=Update  F12=Previous
ROLL KEYS=Change month

06-37  SF  MW  KS  IM  II  KENB20A  PED129S1
  
```

Fields:

1st Service Period End Date

Enter the date of the first service period end.

1st Account Period End Date

Enter the date of the first accounting period end.

Day Type

Enter a day type against each day of the month. You set up day type codes in the codes/parameter file under parameter ID DAYT. The codes define working days and non-working days.

Service Pd

Enter E under the last day of a service period. You can have more than one service period end in a calendar month.

You must enter an E for the date specified as the 1st Service Period End Date.

Account Pd

Enter E under the date which is the last day of an accounting period. You can set more than one accounting period end in a calendar month.

You must enter an E for the dates specified as the 1st Account Period End Date.



Note: The service period and the accounting period end dates could be in a previous calendar year. You must identify the dates in the previous year, with an E, in both the Service Pd and Accounting Pd fields. To do this, you must enter a dummy year, for the year before the first calendar year you require.

The Period End Rebuild option does not generate period end dates for the first calendar year entered on the Daily Calendar file.



Tip: To see the different months, page up and down.



When you have entered all months, select **F8=Update** to update.



Note: After making changes you must run the Rebuild Period End Dates File option. This makes sure that the period end dates on the system accurately reflect the daily calendar detail. You should check the period dates after the rebuild, using the Period End Dates Enquiry.

Branch File Maintenance



5/WOP

Use this option to set up each service branch operating within a company. Use this option when you are setting up your system to define all branches, and as necessary to add new branches.



Note: You must have exclusive use of the company to do this.

A branch is a sub-division of a company, and is an organisational unit which controls its own service operations, but shares certain data with other branches.

Implications

You must define at least one branch for each company, otherwise you cannot access the system. You must also authorise at least one user to a branch before you can access the branch.

When using the system, you are always signed on to a particular branch. You can authorise yourself to access one or more branches. If you have access to more than one branch, you can switch between them within the same session. The branch to which you sign on determines the data you are able to access, and the ownership of the data you create.

Branch Maintenance Selection Screen



To display this screen, select the Branch File Maintenance option.

Use this screen to select the branch you want to maintain or define.

SS010	Demonstration Company	USER BRERETM	9/09/93
	CENTRAL BRANCH		16:32:06
Branch Maintenance			
Branch Code	<u>CI</u>		
F3=Exit F4=Prompt			

Fields:

Branch Code

Enter a new branch code using up to two alphanumeric characters, or select an existing branch.



To display the Branch Maintenance Detail Screen, press **Enter**.

Branch Maintenance Detail Screen



To display this screen, enter a branch on the Branch Maintenance Selection screen, then press **Enter**.

Use this screen to enter the branch workshop details.

W0010	Z1 - UK Demonstration Company	USER GBJBANB4	20/01/98
	CENTRAL WORKSHOP		15:31:57
Branch Maintenance			
Branch Code.....?	CW		
Branch Name.....	CENTRAL WORKSHOP		
Address.....			
Post Code.....			
Telephone.....			
Mileage Travel Rate..	00	Average Travel Time...	00:00
Calendar Code.....?			
Branch stockroom.....?	WE		
Default transfer to Stockroom?	WQ		
Job Audit Log Queue.....		Error Message Queue...	
Default Account number.....?	CW	Default site number...	000
Default Collection method....?	CI	CUSTOMER TRANSPORT	
F3=Exit F4=Prompt F8=Update F12=Previous F14=Location maint.			

Fields:

Branch Name

Enter the name of the branch, using up to 35 alphanumeric characters.

Address

Enter the branch address.

Post Code

Enter the branch postcode using the official postcode format.

Telephone

Enter the branch telephone number. You can use up to 15 alphanumeric characters.

Mileage Travel Rate

This is a memo field only, the Charge Per Mile/Km field in the customer's additional service details gives the rate.

Average Travel Time

Enter the default travel time, in hh:mm format, for use in call scheduling calculations. This is a flat figure Workshop Management uses as the travel time to schedule between jobs.

Calendar Code

This is a memo only field. Leave this field blank to use the standard system calendar.

Branch Stockroom

Enter the default stockroom for this branch. This is the stockroom used when you receive or transfer stock.

Default Transfer To Stockroom

Enter the default stockroom to which you transfer all despatches from the workshop.

Job Audit Log Queue

Enter the output queue to direct the job audit log report to audit list of job maintenance activities. If you leave this field blank, the system uses the queue specified in Application Manager.

Error Message Queue

This field only displays if remote communications are active (see System Parameters Maintenance Screen 4).

Enter the user or queue identity to receive the reports on validation and transmission errors arising from remote communications.

Default Account Number

Enter the account number to use when transferring items to stock.

Default Site Number

Enter the site number to use when transferring items to stock.

Default Collection Method

Enter the default collection methods for this branch.

Functions:

F14

Location Maint. Use this function to maintain all location codes for a workshop.



To save any changes you have made, select
F8=Update.

Location Code Maintenance Window (F14)

 To display this window, on the Branch Maintenance Details Screen, select **F14=Location Maint.**

Use this window to enter all the valid locations for the selected workshop.

W0095		Z1 - Demonstration Company		USER GBJBATD0		1/12/97	
		CENTRAL BRANCH		UPDATE		15:18:36	
Location Code Maintenance							
Branch Code.... CT		CENTRAL BRANCH					
Location	Location	Location	Location	Location	Location	Location	Location
<u>LOCN1</u>	<u>LOCN11</u>	<u>LOCN24</u>	<u>LOCN37</u>	<u>LOCN50</u>	<u>LOCN63</u>	<u>LOCN76</u>	
<u>ALOCN3</u>	<u>LOCN12</u>	<u>LOCN25</u>	<u>LOCN38</u>	<u>LOCN51</u>	<u>LOCN64</u>	<u>LOCN77</u>	
<u>CTBOOK</u>	<u>LOCN13</u>	<u>LOCN26</u>	<u>LOCN39</u>	<u>LOCN52</u>	<u>LOCN65</u>	<u>LOCN78</u>	
<u>LOCN01</u>	<u>LOCN14</u>	<u>LOCN27</u>	<u>LOCN40</u>	<u>LOCN53</u>	<u>LOCN66</u>	<u>LOCN79</u>	
<u>LOCN02</u>	<u>LOCN15</u>	<u>LOCN28</u>	<u>LOCN41</u>	<u>LOCN54</u>	<u>LOCN67</u>	<u>LOCN80</u>	
<u>LOCN03</u>	<u>LOCN16</u>	<u>LOCN29</u>	<u>LOCN42</u>	<u>LOCN55</u>	<u>LOCN68</u>	<u>LOCN81</u>	
<u>LOCN04</u>	<u>LOCN17</u>	<u>LOCN30</u>	<u>LOCN43</u>	<u>LOCN56</u>	<u>LOCN69</u>	<u>LOCN82</u>	
<u>LOCN05</u>	<u>LOCN18</u>	<u>LOCN31</u>	<u>LOCN44</u>	<u>LOCN57</u>	<u>LOCN70</u>	<u>LOCN83</u>	
<u>LOCN06</u>	<u>LOCN19</u>	<u>LOCN32</u>	<u>LOCN45</u>	<u>LOCN58</u>	<u>LOCN71</u>	<u>LOCN84</u>	
<u>LOCN07</u>	<u>LOCN20</u>	<u>LOCN33</u>	<u>LOCN46</u>	<u>LOCN59</u>	<u>LOCN72</u>	<u>LOCN85</u>	
<u>LOCN08</u>	<u>LOCN21</u>	<u>LOCN34</u>	<u>LOCN47</u>	<u>LOCN60</u>	<u>LOCN73</u>	<u>LOCN86</u>	
<u>LOCN09</u>	<u>LOCN22</u>	<u>LOCN35</u>	<u>LOCN48</u>	<u>LOCN61</u>	<u>LOCN74</u>	<u>LOCN87</u>	
<u>LOCN10</u>	<u>LOCN23</u>	<u>LOCN36</u>	<u>LOCN49</u>	<u>LOCN62</u>	<u>LOCN75</u>	<u>LOCN88</u>	
F8=Update F12=Previous							

Fields:

Location

Enter all the locations that this workshop can use.

When you are adding a new workshop, all the location fields are blank.

 To save the details and return to the previous screen, select **F8=Update.**

User/Branch Authorities



6/WOP

Use this option to maintain the record of the branches each user can use, and to authorise users to branches.



Tip: To authorise yourself to all branches for a company, enter a special branch code of *A, instead of specifying each branch individually.

Authority Maintenance Screen



To display this screen, select the User/Branch Authorities Maintenance option.

Use this screen to select the user and branches you want to authorise the user for.

SS005	Demonstration Company CENTRAL BRANCH	USER BRERETM	9/04/94 11:33:35
Authority Maintenance			
User ID.....	BRERETM		
Branch Code....?	__		
F3=Exit F4=Prompt			

Fields:

User ID

Enter a user ID.

Branch Code

If you want to authorise this user to a particular branch, then enter the branch code and press **Enter**. The Branch Marker field displays on the screen.

If you want to see a list of all branches to which this user ID can access, then leave this field blank and press **Enter**. The Branch Selection screen is displayed.

If you want to authorise this user to all branches, then enter *A and press **Enter**. The Default Branch Code field is displayed.

Branch Marker



*Note: This field only displays if you enter a user ID and a branch code other than *A in the Branch Code field.*

A user can only have one branch marker.

Enter one of the following:

0 - This is not the branch that this user is in when they sign on to Workshop Management.

1 - This is the branch that this user is in when they sign on to Workshop Management.

Default Branch Code



*Note: This field only displays if you entered a user ID and the branch code *A.*

Every time a user logs on and starts using Workshop Management the system has to find out which branch they want to use. Normally this means selecting from a list, but if you enter a branch here, then the system automatically assigns this branch each time a user logs on.

Enter an existing branch.



Press **Enter**. If you entered a user and a branch, or a user and the *A code, then the system updates the information.

If you entered a user but left the branch blank, the Branch Selection Screen is displayed.

Branch Selection Screen

-  To display this screen, on the Authority Maintenance Screen, enter a user ID and leave the Branch Code field blank, then press **Enter**.

This screen displays all the branches the user can access.

SS005	Demonstration Company	USER BRERETM	9/04/94
	CENTRAL BRANCH		11:33:44
Branch Selection			
User ID BRERETM			
1	Code Branch Name	Marker	
-	BR BIRMINGHAM BRANCH	0	
-	BT 'BRUM' TRAINING BRANCH	1	
-	CW CHORLEYWOOD BRANCH	0	
Enter a selection or a Branch Code ____			
1=select			
F3=Exit F12=Previous			

Fields:

1

Select. Enter 1 against a branch to maintain the branch marker. If you authorise a user to all branches, to maintain the Default Branch Code, select it with 1.

Branch Marker

Enter one of the following:

0 - If this is not the branch the user accesses when they sign on to Workshop Management.

1 - If this is the branch the user accesses when they sign on to Workshop Management.

Each user can only have one branch set to 1. To change the marker, set each marker to 0 before setting the new marker to 1.

Enter A Selection Or A Branch Code

Enter the branch you wish to maintain, instead of selecting from the list.

-  Press **Enter**. The Authority Maintenance Screen displays with the Branch Marker or Default Branch Code field showing.

Escalation Parameters



7/WOP

Job escalation is how Workshop Management alerts users to outstanding jobs approaching their contracted response time.

The way you set up this option controls the way in which job escalation operates for each Workshop Management branch. You do not have to use job escalation in Workshop Management, and you can implement it at any time.

You use this option to set the branch response time used at call logging. You can define it either by division and model group, or as a default for any division and model group combination not set up. The system uses the default only if there is no match at a higher level in the response time hierarchy.



Note: You must have exclusive use of the company to do this.



Note: Escalation takes place only if you select the Start Job Escalation option.

You must define the following fields for each workshop branch, and optionally for each model group serviced within the branch:

- Escalation Time Fence. This is the number of hours or minutes before the target response time that a job starts to escalate, for example, 4 hours.
- Escalation Step Interval. This is the number of hours or minutes between each escalation level, or step; for example, 30 minutes.
- Report PM Jobs. You can exclude planned or scheduled maintenance jobs from the routine which sends escalation messages to defined users, so it alerts users to breakdown or call-out jobs only.
- Report Contracted Responses Only. This only sends escalation messages for pieces of equipment covered by contract to defined users.
- Default Response Time. This is the response time to use as a branch default.
- Users to Receive Messages. You define a list of user IDs who receive warning messages as jobs reach certain escalation levels.

Implications

Escalation is an optional facility in the system. If you do not require this, you do not need to define the escalation parameters.

The system assumes a seven day working week. If you work less than this, the system still escalates Monday's jobs on Sunday, not on the preceding Friday.

Escalation Control Maintenance Selection Screen



To display this screen, select Escalation Parameters (Maintenance).

Use this screen to enter the division and model group for which you want to create escalation control.

SS850	Demonstration Company CENTRAL BRANCH	GBJBAMXB	30/06/95 17:48:35
Escalation Control Maintenance			
Division.....?. ____			
Model Group.....?. ____			
Leave both fields blank to create the Default Branch Response Time.			
F3=Exit F4=Prompt			

Fields:

Division

Enter an existing division.

Model Group

Enter an existing model group.



Note: To set up the branch default response time, leave the division and model group fields blank.



Note: You should set up a default response time for each branch. The branch default time sets the call response time for equipment in a division and model group, if there is no match at a higher level in the response time hierarchy.



To display the Escalation Control Maintenance Detail Screen, press **Enter**.

Escalation Control Maintenance Detail Screen



To display this screen, enter the division and model group on the Escalation Control Maintenance Selection Screen and press **Enter**.

Use this screen to define how you escalate jobs.

SS850	Demonstration Company CENTRAL BRANCH	BRERETM	9/04/94 13:43:58
Escalation Control Maintenance			
Division.....	10		
Model Group.....	100	Report PM Jobs ?	0 (0=No,1=Yes)
Report Contracted Responses Only (0/1)			0
Report Escalation Before Response Due (HH:MM)			4:00
Reporting Interval For Escalation (HH:MM)			1:00
Default Branch Response Time (HHH:MM)			8:00
Reports to be sent to :-			
Report Step	User ID	Screen	
00	QSECOFR	2	
01	SUPRVSF	2	
02	OPERATR	1	
00		-	
00		-	
00		-	
			+
F3=Exit F8=Update F11=Delete F12=Previous			

Fields:

Report PM Jobs

Enter one of the following:

0 - No. To exclude planned maintenance jobs from the messages sent when jobs reach the designated escalation step.

1 - Yes. To include planned maintenance jobs in the messages sent when jobs reach the designated escalation step.

Report Contracted Responses Only

Enter one of the following:

0 - For all jobs to send messages to the appropriate users.

1 - If only jobs for pieces of equipment covered by contract, send messages when they reach the designated escalation steps.

Report Escalation

Enter the amount of time before the target time that a job starts to escalate. This should be in hh:mm format, between 00:15 and 99:45, with the minutes being a multiple of 15.

Reporting Interval for Escalation

Enter the amount of time between escalation steps. This should be in hh:mm format, between 00:15 and 99:45, with the minutes being a multiple of 15.

Default Branch Response Time (hhh:mm)

Enter the default branch response time.

Workshop Management calculates a job's target date and time by adding the response hours to the date and time when you first logged the job. It adjusts the date to allow for working hours and days and finds the response hours in:

1. Special serial numbers.
2. Contract equipment or lines.
3. Contract header.
4. Contract type (including *NO).
5. Default branch response time.



Note: You can alter the response times defined in a contract, by a percentage in the 3-D matrix.

Report Step

Enter a step in the range 00 to 98. The step 00 is when the job reaches, or passes, its target date and time. 98 is when you log the call.

The call stays at 98 until you reach the Report Escalation Before Response Due time. The call's report step then moves to the highest step value listed on this screen; for example, if you have defined steps 00, 05, 07, 10 and 98, the call moves to step 10. As you reach escalation, the call moves through each defined step to 00.

User ID

Enter a user ID.

Screen Message

Enter one of the following:

- 0 - To issue no message when the job reaches this step.
- 1 - To send a message to this user's message queue.
- 2 - To send a message to this user in break mode.



Note: If the job reaches step 00 and you want a break message, the system sends the message on the first occasion. At any following escalation cycle, there is no message for that job.

The message includes the sender, the date and time sent, the job number, the escalation step reached, the target date and time, engineer number, customer, model and serial number, and the time to target (hh:mm).



To save any changes you have made, select **F8=Update**.

Rebuild Of Period End Date File



8/WOP

This option rebuilds all service and accounting period end dates for a company, and you should use it after you make changes in the Daily Calendar Maintenance option.

A service period is a specific number of days, defined by a start and end date. The system holds an end date for each service period.

An accounting period is a specific number of days, defined by a start and end date. The system holds an end date for each accounting period.

The option sends a batch job which deletes all existing period end dates for a company. It rebuilds them for both workshop and accounting periods, using the details from the Daily Calendar Maintenance option (where you specify the period end markers).



Note: You must have exclusive use of Workshop Management to do this.



Tip: You must run this option after making any changes in the Daily Calendar Maintenance option, since the system uses the period end dates extensively.

You should use the Period End Dates Enquiry option after the rebuild, to check that the period end dates are as you expect.



To rebuild the period end dates, select Rebuild Of Period End Date File. Then select **F8=Submit** to start the batch job running.

System Parameters File



9/WOP

Use this option to maintain the fields which control the system for a specific company.



Note: This option is an extension to the Company Profile File Maintenance option. It is not a parameter file in the same sense as the Codes/Parameter File Maintenance option in Workshop Management, or the Descriptions option in Inventory Management.

You use this option when you set up the system, but infrequently thereafter.



Note: You must have exclusive use of Workshop Management to do this.

You can sub-divide a company into branches, but these branches all operate under the controlling system parameters defined for the company.

*(which you can overwrite at site address level)
for Mileage To Be Charged By Mileage Zones.*

Allow Service Cover on Pending Contracts

Enter one of the following:

0 - To prevent calls on a pending contract. You must change a field on the contract header before you can send an engineer.

1 - To allow calls on a pending contract. If the customer calls with a problem, you can send an engineer, just as if the contract were active.

No Of Repeat Calls In Sequence = Specialist Call

When the number of repeat calls for the same machine reaches the number defined here, the system uses the default job category, defined for a specialist call, on the call logging screen.

% To Shorten Response On Specialist Call

Enter the percentage to reduce a response time by, when call logging recognises a specialist call.

Minimum Number Of Calls Between Emergency Calls

Enter the number of consecutive calls a customer must log before you log an emergency call. Use this to prevent customers abusing the emergency service.

This emergency indicator is on the call logging screen. When the job is an emergency, the system sets the target date and time to the system date and time - that is, now.

Allow New Job At Technical Reporting

Enter one of the following:

0 - You cannot create a new job when technical reporting within the Engineer Work Allocation option.

1 - When you go into technical reporting for a job (by entering 99 against a job in the Work Control option) the New Job Required field displays. Enter 1 there to enter a new job for an existing or new machine at the same customer's site.

The current system does not use the rest of the fields.



To display the System Parameters Maintenance Screen 2, press **Enter**.

System Parameters Maintenance Screen 2



To display this screen, press **Enter** on the System Parameters Maintenance Screen 1.

Use this screen to enter the job system parameters.

SS011	Demonstration Company	USER BRERETM	9/09/93 17:04:59
System Parameters Maintenance			Screen 2 of 5
Print Job Documentation (1/0).....		0	
Minutes In Between Job Documentation.....		0	
Download Call Information to PC (1/0).....		0	
Minutes In Between PC Download.....		0	
Check Kits Before Assigning Engineer (1/0).....		0	
Print Engineers Name on Service Invoice (1/0).....		0	
Technical Report Text Mandatory for T&M Calls (1/0).....		0	
Engineer Resupply - Send to Home (1/0).....		0	
Maximum Calls Displayed on Engineer Work Queue.....		10	
Maximum Customer Importance - Customer Invoice Level.....		4	
Customer Ref. Mandatory on Call Reporting if VAT free (1/0)		0	
Small Invoice Value.....			.00
F3=Exit F12=Previous			

Fields:

Check Kits Before Assigning Engineer

Enter one of the following:

0 - If you make no check for van stock kit.

1 - When assigning a job to an engineer, Workshop Management checks to determine if the kit item number, set up on the model, is present in the engineer's stock room. If it is not present, the system enters a reason code for non-allocation on the call logging screen.

To use this function, you must be using Inventory Management.

Maximum Customer Importance Customer Invoice Level

You set up a customer's importance in the Customer Additional Service Details option, and the 3-D matrix uses this to help determine response times.

Enter the setting which indicates the most important of your customers. It is best to enter either 1 or 4.



Note: The current system does not use the rest of the fields on this screen.



To display the System Parameters Maintenance Screen 3, press **Enter**.

System Parameters Maintenance Screen 3



To display this screen, on the System Parameters Maintenance Screen 2, press **Enter**.

Use this screen to enter system parameters, including those defining how you handle estimates.

SS011	Demonstration Company	USER BRERETM	9/09/93 17:06:17 Screen 3 of 5
System Parameters Maintenance			
Estimates Allowed for Billing (1/0).....			1
Maximum Number of Estimates Allowed to Bill.....			11
Estimates Allowed for Reconciliation (1/0).....			0
No. of Days Prior to Invoice Date to Trigger Estimate.....			20
No. of Days Allowed for Return of Meter Card.....			10
Actual Reading Validation Parameters:			
% Within Estimate Reading Allowed.....			20
Multiple of Minimum Copies Allowed.....			2
Copy Price Conversion Factor (Pence to Pound).....			100
Item Types to be Invoiced:			
	Type	Description	Abbreviation
1.	1	Major	MAJ
2.	2	Minor	MIN
3.	3	Consume	CON
4.	4	Supplies	SUP
F3=Exit F4=Prompt F12=Previous			

Fields:

Estimates Allowed For Billing

Enter one of the following:

0 - To allow only actual readings when pricing meterage contracts.

1 - To allow estimated readings when pricing meterage contracts.

The system uses this in the contract header, but you can change it.

Maximum Number Of Estimates Allowed To Bill

Enter the default number of estimates allowed, in the contract header. This is a number in the range 1 - 999.

The system only uses this field, if you set the Estimates Allowed For Billing field to 1.

Estimates Allowed For Reconciliation

Enter one of the following:

0 - To allow only actual meter values in the reconciliation calculation. This is the recommended setting.

1 - To allow estimates in the reconciliation calculation.

Reconciliation is a type of meter billing where there is a review of usage. You can then raise an invoice for a meter count higher than the minimum agreed in the

contract; or, you can send a credit where the meter count is below the estimate and bill, but greater than the minimum.

No Of Days Prior To Invoice Date To Trigger Estimate

Enter the maximum number of days before the invoice date that the system generates estimated readings.

For example, if you set your invoice date as 31st May, and enter 20 here. Workshop Management produces estimates on the 11th May, so customers receive their estimates and can return their own readings.

No Of Days Allowed For Return Of Meter Card

Enter the number of days before the invoice date that customers must return their meter cards in order to enter them in time for invoicing.

% Within Estimate Reading Allowed

You could enter gross errors for meter readings. Enter a percentage. If a reading falls outside this percentage of the estimate, the system registers the reading as an error.

Multiple Of Minimum Copies Allowed

Enter the number you can multiply the minimum number of copies allowed by. The system uses this value to check for errors in meter readings. The minimum value is the value you assign to the machine in the conditions set up for the contract line.

Copy Price Conversion Factor (Pence To Pound)

Enter the factor the system uses to convert the copy price back to the main currency unit.

You can set up copy prices in contract conditions as pence or cents per copy, rather than as decimals of the main currency unit. For example, if you enter 100 here, then the system moves the decimal point two points to the left, and 0.25 becomes 0.0025.

Item Types To Be Invoiced

Once you have set the following fields, you can only amend them by editing the file SSP04.

Type Code

Enter the four item types to invoice.

Item Types To Be Invoiced: Description

Enter the descriptions of the four item types to invoice.

Item Types To Be Invoiced: Abbreviation

Enter an abbreviation for the four item types to invoice.



To display the System Parameters Maintenance Screen 4, press **Enter**.

System Parameters Maintenance Screen 4



To display this screen, on the System Parameters Maintenance Screen 3, press **Enter**.

Use this screen to set up the System Parameters for call logging.

SS011	Demonstration Company	USER BRERETM	26/10/93 14:03:03
System Parameters Maintenance			Screen 4 of 5
More than one machine allowed on a breakdown call.....			0
More than one breakdown call allowed at one time.....			0
Position cursor during call logging.....			2
Credit control by branch.....			0
Default expiry days for messages.....			3
Default invoice start date to first of the month.....			0
Technical Report generated if receptionist completes call..			1
Number of days between calls to generate repeat call.....			___
Automatic Call Assignment active (1/0).....			1
Remote Communications active (1/0).....			1
Default Re-Transmission flag (1/0)			1
F3=Exit F12=Previous			

Fields:

More Than One Machine Allowed On A Breakdown Call

Enter one of the following:

0 - If you can only log one machine on a job number.

1 - If you can log additional machines for the site on one job number, after you have updated the call for the first machine.

To allow more than one machine on a planned maintenance job, set the One Machine Per PM Job flag, on the Company Profile Maintenance Screen 4.

More Than One Breakdown Call Allowed At One Time

Enter one of the following:

0 - If you can have only one incomplete job for a machine. This is not the right setting if you deal with large machines, which might have more than one repair logged.

1 - If you can log more than one job for a machine, even if the other jobs are open or in progress.

Position Cursor During Call Logging

Enter one of the following to set the position of the cursor when you access Call Logging:

1 - On the Account Number field.

2 - On Contract Number field.

3 - On Customer Order Number field.

Credit Control By Branch

Enter one of the following:

0 - To display all jobs for the company in Credit Call Maintenance.

1 - To display, for jobs set to bad credit status, only the jobs for the user's branch, in Credit Call Maintenance.

Default Expiry Days For Message

Enter the default length of time the engineer messages remain in the system.



Note: The system does not use this for machine messages, which take a default date of 99/99/99, which is an indefinite expiry date.

Default Invoice Start Date To First Of The Month

Enter one of the following:

0 - To specify that any new contract you enter assumes an invoice start date the same as the contract start date.

1 - To specify that any new contract you enter, assumes an invoice start date of the first of the month following the contract start date. The system includes any days not invoiced on that invoice. For example, if a contract starts on 8th August, and you send the first invoice on 30th September, it includes the charge for 8th - 31st August.



Tip: You can change the invoice start date within Contract Maintenance.

Technical Report Generated If Receptionist Completes Call

Enter one of the following:

0 - If you do not want a technical report record if the call receptionist solves the problem over the telephone.

1 - If you do want a technical report record if the call receptionist solves the problem over the telephone.

Number Of Days Between Calls To Generate Repeat Call

This field is for future development.

Automatic Call Assignment Active

Enter one of the following:

0 - If you do not want to use automatic call assignment. The system does not display the System Parameters Maintenance Screen 5 - and removes any previous settings on that screen. Select **F8=Update** to update displays on this screen.

1 - If you do want automatic call assignment available for the company. The system displays the System Parameters Maintenance Screen 5, so you can set up the company's automatic call assignment parameters.



Tip: You can also limit the ACA operation by settings on the model, job category and engineer.

Remote Communications Active

Enter one of the following:

0 - If engineers do not use remote communications to transmit job details or messages.

1 - So that with the Workshop subsystem active, incoming and outgoing sleeper programs monitor when engineers log on, so that the system can transmit job and message details, or receive technical report details.

Default Re-Transmission Flag



Tip: If you set the Remote Communications Active field to off, then set this field to 9 to switch off the re-transmit field on the call logging screen.

Enter one of the following:

Blank - You must enter 0 or 1 on the Field Logging screen.

0 - To allow transmission of a job, but not re-transmission of any call logging changes.

1 - To automatically retransmit to the engineer, whenever you see a problem on an incoming transaction.

You can change these defaults on the Call Logging Screen.



Enter 1 in the Automatic Call Assignment field, and press **Enter** to display the System Parameters Maintenance Screen 5.

Or enter 1 in the Automatic Call Assignment Field, and select **F8=Update** to save the changes.

System Parameters Maintenance Screen 5



To display this screen, press **Enter** on the System Parameters Maintenance Screen 4.



Note: This screen only displays if you set the Automatic Call Assignment Active field to 1 on System Parameters Maintenance Screen 4.

Use this screen to define how you use Automatic Call Assignment (ACA).

SS011	Demonstration Company	USER BRERETM	26/10/93
			14:03:11
System Parameters Maintenance			Screen 5 of 5
Time within which calls are automatically assigned.....: <u>8</u>			
Assign CM calls only to maintenance-only engineers (0/1)...: <u>1</u>			
Assign repeat calls only to original engineers (0/1).....: <u>1</u>			
Assign calls only to preferred engineer for machine (0/1)..: <u>1</u>			
Assign calls only to engineers carrying kit (0/1).....: <u>0</u>			
Permitted % increase in response time.....: <u>10.00</u>			
Permitted appointed call overlap time (minutes).....: <u>15</u>			
Engineer workload threshold (hours).....: <u>0</u>			
Automatic Call Assignment sleeper wait time (minutes).....: <u>3</u>			
Maximum calls to assign between waits.....: <u>10</u>			
F3=Exit F8=Update F12=Previous			

Fields:

Time Within Which Calls Are Automatically Assigned

Enter the number of hours, before call target time, that Automatic Call Assignment picks up an unassigned call and allocates it to a team or preferred engineer. This prevents the system allocating visits too far in advance.

Assign CM Calls Only To Maintenance-Only Engineers

CM is short for contracted maintenance; it is not a job category, nor a scheduled visit profile code.

Enter one of the following:

0 - To allocate calls to any engineer within the team.

1 - To only assign system-generated calls (planned visits) to those engineers assigned to contract maintenance.

Assign Repeat Calls Only To Original Engineers

Enter one of the following:

0 - To assign any call identified as a repeat call to any engineer within the team.

1 - To assign any call identified as a repeat call to the engineer who made the original visit.

Assign Calls Only To Preferred Engineer For Machine

Enter one of the following:

0 - To assign calls to any engineer within the team.

1 - To assign calls to the engineer defined on the installation, or, if there are none defined, to the team.

Assign Calls Only To Engineers Carrying Kit

Enter one of the following:

0 - The system does not check whether the engineer is carrying the kit item for the equipment.

1 - The system checks the engineer's van stock (defined for that engineer), to see if the engineer is carrying the kit item for the equipment.

Permitted % Increase In Response Time

Enter the percentage that calls must exceed their target time by, to still be scheduled by Automatic Call Assignment.

Above this figure, ACA does not allocate the call and adds the appropriate reason code (parameter type ETAR) to the job.

Permitted Appointed Call Overlap Time

Enter the amount of time, in minutes, by which appointments can overlap.

Engineer Workload Threshold

Not used in the current system.

Automatic Call Assignment Sleeper Wait Time

Enter the number of minutes the ACA procedure (which runs in the background) waits before it runs again.

Maximum Calls To Assign Between Waits

Enter the maximum number of calls ACA attempts to schedule for an engineer each time it runs. Use this field to avoid overloading an engineer.



Select **F8=Update** to save the information.

Working Days Calendar File Maintenance



10/WOP

Use this option to provide alternative calendars to the system's daily calendar. The alternative working calendars define working days, Saturdays, Sundays, public holidays and shut downs, for future use at branch and customer levels.

You set up calendar codes and descriptions via the Codes/Parameter File Maintenance option, under parameter type CCAL.

Implications

Workshop Management holds details of a company's calendar day types on the same file as its customers' calendar data.

Company period end dates, set up on a separate file apply to its customers' calendars. The system uses these for service and accounting period ends.

There is no functionality associated with the customer records on the calendar file in the current system. You can only use customer calendars for memo purposes.

Working Days Calendar Maintenance Selection Screen



Select Working Days Calendar File Maintenance.

Use this screen to select the calendar you want to maintain or create.

W0082	Z1 - GB Demonstration Company	USER GBJBANB1	9/04/98
	CENTRAL WORKSHOP		16:08:08
Working Days Calendar Maint.		UPDATE	
Calendar code.....	01	Calendar Code	
Year to maintain..... 00			
Base upon calendar code...?..		(Enter based-on code and year to	
and year..... 00		copy existing details if required)	
n Year	n Year	n Year	n Year
- 95			
1=Amend, 4=Delete			
F3=Exit F4=Prompt F8=Update F12=Previous			

Fields:

Calendar Code

Enter an existing calendar code and press **Enter**. This displays the following fields:

Base Upon Existing Calendar Code

Enter one of the following:

0 - Do not base the calendar on an existing calendar.

1 - To base the calendar on an existing calendar.

Base Upon Calendar Code

Enter an existing calendar to copy.



To display the Working Days Calendar
Maintenance Detail Screen, press **Enter**.

Working Days Calendar Maintenance Detail Screen



To display this screen, select a calendar code and year on the Working Days Calendar Maintenance Selection Screen.

Use this screen to define the working and non-working days.

SS082	Demonstration Company	USER BRERETM	26/10/93
	CENTRAL BRANCH		14:23:14
Working Days Calendar Maint.		ADDITION	
Calendar code.....	C01	Customer Group	999
Year to maintain.....	93		
	1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1		
January	B S S C C C C S S W W W W W S S W W W W W S S W W W W S S		
February	W W W W W S S W W W W W S S W W W W W S S W W W W S S		
March	W W W W W S S W W W W W S S W W W W W S S W W W W S S		
April	W W S S C C C C B S S B C C C C S S W W W W W S S W W W W W		
	+		
F3=Exit F4=Prompt F8=Update F12=Previous			

Fields:

Day Types

Enter day types for each day of the month.



Tip: You can page down to display the other months in the year.



Select **F8=Update** to save any changes you have made.

Action Code



11/WOP

Use this function to define the actions required. You enter the information required to process the action whenever the application uses that action.



Note: The actions are branch specific, therefore you must enter a set of actions for each branch.

Action Maintenance Selection Screen



To display this screen, select the Action Code option.

Use this screen to select the action you want to maintain or create.

Fields:

Action Code

Enter an action code using two numeric characters.



Select an action code to display the Action Maintenance Details Screen 1.

Action Maintenance Details Screen 1



To display this screen, on the Action Maintenance Selection Screen, select an action.

Use this screen to enter the default values for the action.

W0008	Z1 - UK Demonstration Company	USER GBJBANB4	22/04/98 14:47:14
Action Maintenance		ADDITION	
Action code..... 01 WORKSHOP PICKUP REQUIRED			
Default Action value. ? . _			
Subsequent Action value ? . _			
Batch Number prefix _			
Despatching Action. (0/1/2) . 0 0=No, 1=External, 2=Internal			
Action not allowed with cust stock. (0/1) . 0			
Default Despatch Method ? . _			
Stock Movement type _			
1=Receipt			
2=Issue			
3=Transfer Out			
4=Transfer In			
5=One Shot Transfer			
Blank=No Movement			
F3=Exit F4=Prompt F12=Previous			

Fields:

Default Action Value

Select the default value for the action.



Note: You can only enter the default value against one action. For example, you cannot have two actions with the default value 01 - Collection Required.

Subsequent Action Value

Enter the action to carry out after the first action.

Batch Number Prefix

Enter a batch number prefix. If you enter a value, whenever you assign this action to a job, the system assigns a batch number as well as a job number.

If you do not want to assign a batch number to this action, leave this field blank.

Despatching Action

Enter one of the following:

- 0 - If you do not despatch the job after this action.
- 1 - If this action is external despatch.
- 2 - If this action is internal despatch.

Action Not Allowed with Customer Stock

Enter one of the following:

- 0 - If you can use this action on customer owned stock.
- 1 - If you cannot use this action on customer owned stock.

Default Despatch Method

If this action is a despatching action, select the default despatch method. You can overwrite this default when you enter this action against a job.

Stock Movement Type

Enter the type of stock movement that this action must perform.

Leave the field blank if there is no stock movement.



To display the Action Maintenance Details
Screen 2, press **Enter**.

Action Maintenance Details Screen 2



To display this screen, on the Action Maintenance Details Screen 1, press **Enter**.

Use this screen to enter further defaults for the selected action.

W0008	Z1 - UK Demonstration Company	USER 6BJBANB4	22/04/98 14:48:22
Action Maintenance		ADDITION	
Action code..... 01 WORKSHOP PICKUP REQUIRED			
Model transformation suffix			
Reason code required. (0/1) . 0			
No. of days if progress chasing required. . . 0			
Text type if documentation required . . ? .			
RMA number required (0/1) . 0			
Account number override allowed . . (0/1) . 0			
Account Default ? .			
Account Sequence.			
Stockroom entry allowed ? .			
Set Status(1=Hold(06),2=Reles(00),0=No chg) 0			
Location code update. (0/1) . 0			
Location code value ? .			
Program to call			
F3=Exit F4=Prompt F8=Update F12=Previous F14=Invalid Actions			

Fields:

Model Transformation Suffix

Enter the value to add to the item number whenever you enter this action for the item. If you enter a value, the Workflow application performs the stock movements for this action and item combination. The default is blank.

Reason Code Required

Enter one of the following:

- 0 - If you do not require a reason code when a user enters this action for a job.
- 1 - If you do require a reason code, when a user enters this action for a job.

No. Of Days If Progress Chasing Required

Enter the number of days this action can take, before the Progress Chasing function monitors any job assigned this action.

Text Type If Documentation Required

Select the type of documentation required for this action. Leave this field blank if you do not want any documentation.

RMA Number Required

Enter one of the following:

- 0 - If the user does not need to enter an RMA number when they use this action for a job.

1 - If the user must enter an RMA number when they use this action for a job.

Account Number Override Allowed

Enter one of the following:

0 - To prevent users from overriding the account, when they enter this action.

1 - If users can override the account and sequence when they enter this action.

Account Default

If you set the Account Number Override Allowed to 1, enter the account number to use when entering this action.

Account Sequence

If you set the Account Number Override Allowed to 1, enter the account sequence to use when entering this action.

Stockroom Entry Allowed

Enter the stockroom to send the job to. This must be an Inventory stockroom.

Set Status

Enter one of the following:

0 - If this action does not change the status.

1 - If this action sets the status to 06 - Hold.

2 - If this action sets the status to 00 - Release.

Location Code Update

Enter one of the following:

0 - If this action does not update the location.

1 - If this action updates the location to the location in the Location Code Value field.

Location Code Value

If you set the Location Code Update field to 1, enter the location for the job once this action is complete.

Program To Call

Enter the program that this action calls, if there is an action change for any job assigned this action code.

Functions:

F14

Invalid action. Use this function to define the actions that you cannot use with this action.



To save the information, select **F8=Update**.

Action/Invalid Action Relationship Screen (F14)



To display this window, on the Action Maintenance Details Screen 2, select **F14=Invalid Actions**.

Use this screen to define all the actions you cannot use with the selected action.

W0004	Z1 - Demonstration Company CENTRAL BRANCH	User: GBJBATD0	1/12/97 16:18:42
Action/Invalid Action Relationship Table			
Action.....: AL Despatch to 3rd Party			
Invalid Action.....?: █			
S	Action	Description	
-	AV	Confirm Internal Despatch	
4=Delete			
F3=Exit F4=Prompt F8=Update F12=Previous			
7-27	SP	MW	KS CL IM DM II MARVIN KB PKH318S1

Fields:

Invalid Action

Enter the action to add to the list of invalid actions.

S

Select. Enter 4 alongside the action to delete from the list of invalid actions.



To save the changes and return to the previous screen, select **F8=Update**.

Invalid Status/Action Code



12/WOP

Use this function to identify the actions that you cannot use with the specified job status.



Note: If you do not define any invalid actions for a status, the Workshop Management presumes that all actions are valid.

These relationships are branch specific, therefore you must define them for each branch.

Invalid Status/Action Relationship Screen



To display this screen, select the Invalid Status/Action Code option.

Use this screen to define the actions that you cannot assign to jobs with the specified status.

```

W0005          Z1 - Demonstration Company      User: GBJBATD0      1/12/97
                CENTRAL BRANCH                  16:20:21
Invalid Status/Action Relationship Table

Status.....: 05      05=Telephone

Action.....?: ☐

Sel Action   Description
-    AU      Confirm Internal Despatch

4=Delete
F3=Exit  F4=Prompt  F8=Update  F12=Previous

7-26      ☒ SR      MW      KS      ☒ CL      IM  DM  II      MARVIN      KB      PKH318S1
  
```

Fields:

Status

Enter the status you want to define invalid actions for and press **Enter**. This displays the following fields:

Action

Enter the action that you do not want to allow for this status.

Sel

Select. Enter 4 alongside the action you want to delete from the list of invalid actions.



To save the changes, select **F8=Update**. Then to return to the menu, select **F3=Exit**.

Standard Text



13/WOP

Use this function to enter text against specified document types. This text is printed on the documents specified.

Standard Text Entry Selection Screen



To display this screen, select the Standard Text option.

Use this screen to select the text type you want to define or maintain.

Fields:

Text Type

Select the required text type.



To display the Free Format Text Screen, select a text type.

Free Format Text Screen



To display this screen, on the Standard Text Entry Selection Screen, select a text type.

Use this screen to enter the text you want to print on the specified document type.

Line	Text	Qty	Part No/	Disc%	Unit Price	Net Price
1	VAT		Description		Action	
2	&UQTY46	&PART46			&RATE46	&LVAL46
3	&VATC46	&PDES00			&BPRD00	
4	&UQTYIT	&RECT46				&VALUIT
5	VAT	VARIOUS				
6	&LBRTIM	&RECT46			&RATE46	&VALURT
7	VAT	VARIOUS				
8		&RECT46				&VALURT
9						&VALNET
10				&#NTEXT		

For the attention of
Print this text on 0/00/00

Body Text for Est/Qte (SSP46)

F4=Prompt F8=Update F11=Delete F12=Previous

4-69 **SP** MW KS **CL** IM DM II MARVIN KB PKH318S1

Fields:

For The Attention Of

Enter the initials of the person this document is for.

Print This Text On

Enter the date on which you want to print this text.

Text

Enter the text you want to print on the document.



Note: You can enter fields that you want to print on the documentation. For example, %DATE%, to print the date, &ADD110 to print the first line of the address.



To save the details, select **F8=Update**.

Codes/Parameters File Enquiry

1... 21/WOP
2...

Use this enquiry to view the parameter code details.

Codes/Parameter File Enquiry Screen 1



To display this screen, select the Codes/Parameter File (Enquiry) option.

Use this screen to select the parameter type and ID you want to maintain.

SS508	Z1 - C&T TEST COMPANY BIRMINGHAM BRANCH	USER GBJBAJG	26/04/96 13:20:18
Codes/Parameter File Enquiry			
Parameter Type ___			
Parameter I.D. ___			
Type	Description		
DAYS	* Day Descriptions		
DAYT	Day type		
DISC	Discount reasons		
EGRD	Engineer job grades		
EQST	Equipment Status		
ERRC	* Remote Comms Error Codes		
ETAR	* ACA Errors & Job Sub-Status		
FLTC	Faults		
GLPR	Global Price Increase Code		
GLTX	* G/L Deferred Rev.-Trans.Text		+
F3=Exit F4=Code Selection			
06-20	82	MW	KS IM II KENB20A PED129S1

Fields:

Parameter Type

Select a parameter type.

To see the details of one particular parameter ID, enter that ID in the field below and press **Enter**.



*Note: Parameter Type descriptions starting with * are system required codes; access to these codes for maintenance is restricted.*

Parameter ID

Enter the parameter ID whose details you wish to see.

If you enter a parameter ID then you must also enter the relevant parameter type.



Enter a parameter type and select **F4=Code Selection** to display the Parameter Code Selection Screen.

Parameter Code Selection Screen

-  To display this screen, select a parameter type on the Codes/Parameter File Enquiry Screen 1 and select **F4=Code Selection**.

SS608	Demonstration Company	USER BRERETM	14/12/93
	CENTRAL BRANCH		11:38:44
Parameter Code Selection			
Parameter Type	DAYT Day Type		
1	Code	Description	
-	B	Bank holiday	
-	C	Closed	
-	S	Saturday/Sunday	
<u>1</u>	W	Working day	
1=Select			
F3=Exit F12=Previous			

Fields:

1

Enter 1 against the parameter ID whose details you want to display.

-  Select a parameter ID and press **Enter** to see the Codes/Parameter File Enquiry Screen 2.

Codes/Parameter File Enquiry Screen 2



To display this screen, select a parameter code on the Parameter Code Selection screen.

This screen displays the set-up details for this parameter ID.

SS508	Demonstration Company	USER BRERETM	14/12/93
	CENTRAL BRANCH		11:38:59
Codes/Parameter File Enquiry			
Parm Type	DAYT	Day Type	
Parm I.D	W		
Description.:	Working day	Max size	30
Deferred Rev. Acct. day (1/0)?	1		
Working day (1/0)?	1		
F3=Exit F12=Previous			

For more details of these fields, see the Codes/Parameter File Maintenance Section.



Select **F3=Exit** to return to the menu.

Daily Calendar File Enquiry



22/WOP

Use this option to enquire on the definition of working and non-working days and on service and accounting period end dates.

Daily Calendar File Enquiry Selection Screen



To display this screen, select the Daily Calendar
File Enquiry option.

Use this screen to select the calendar for which you want to see the details.

SS969	Demonstration Company CENTRAL BRANCH	USER BRERETM	14/12/93 11:39:16
-------	---	--------------	----------------------

Daily Calendar File Enquiry

Year: 93

F3=Exit

Fields:

Year

Enter the year you want to enquire on.



Select a year and press **Enter** to display the
Daily Calendar File Enquiry Screen 1.

Daily Calendar File Enquiry Screen 1

 To display this screen, select a year on the Daily Calendar File Enquiry Selection Screen.

SS969	Demonstration Company CENTRAL BRANCH	USER BRERETM	14/12/93 11:39:24
Daily Calendar File Enquiry			
Year: 93			
1st Service period - end date: 15/01/93			
1st Account period - end date: 29/01/93			
1 2 3			
April 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1			
DAY TYPE W W S S W W W W B S S B W W W W S S W W W W S S W W W W			
SERVICE PD E E E E E			
ACCOUNT PD E			
F3=Exit F12=Previous			
ROLL KEYS=Change month			

This screen displays, for the calendar year selected:

- Month
- Day type
- Service and Account Period end dates.

For more details of these fields, see the Daily Calendar File Maintenance Section.

 Tip: To display other calendar months, page up and down.

 Select **F3=Exit** to return to the menu.

Branch File Enquiry



23/WOP

Use this option to enquire on the details of any workshop branch within a company.

Branch File Enquiry Detail Screen

-  Select Branch File Enquiry, then select the branch, to display the Branch File Enquiry Detail Screen.

```

SS510          Z1 - Demonstration Company          USER GBJBATD0      1/12/97
                                                16:23:41

Branch Enquiry

Branch Code..... CT
Branch Name..... CENTRAL BRANCH
Branch Address..... CENTRAL HOUSE
                   MAIN STREET
                   NEWTOWN
                   MONTGOMERYSHIRE

Post Code..... NT01 1PC
Telephone..... 01925 710820
Mileage Travel Rate..... .50 Ave Travel Time. 30
Calendar Code..... ED Education
Branch Stockroom..... BA Workshop Branch (0/1). 1
Default Transfer To Stockroom. FG
Job Audit Log Queue..... PRT01 Error Message Queue... DFT
Default Account Number..... MJB001 Default Site Number... 000
Default Collection Method..... RB Go round the back

F3=Exit F12=Previous F14=Location Enquiry

1-1  SP MW KS CL IM DM II MARVIN KB PKH318S1
  
```

This screen includes the following details for the selected branch:

- Name and address
- Travel rate and time
- Stockroom details
- Default account number
- Default site number
- Default collection method.

For more details of these fields, see the Branch File Maintenance section.

Functions:

F14

Location Enquiry. Use this function to display all the locations for the branch.

-  Select **F3=Exit** to return to the menu.

Location Code Enquiry Screen (F14)



To display this screen, on the Branch File Enquiry Detail Screen, select **F14=Location Enquiry**.

W0595		Z1 - Demonstration Company		USER GBJBATD0		1/12/97	
		CENTRAL BRANCH				16:24:09	
Location Code Enquiry							
Branch Code.... CT		CENTRAL BRANCH					
Location	Location	Location	Location	Location	Location	Location	
ALOCN1	LOCN11	LOCN24	LOCN37	LOCN50	LOCN63	LOCN76	
ALOCN3	LOCN12	LOCN25	LOCN38	LOCN51	LOCN64	LOCN77	
CTBOOK	LOCN13	LOCN26	LOCN39	LOCN52	LOCN65	LOCN78	
LOCN01	LOCN14	LOCN27	LOCN40	LOCN53	LOCN66	LOCN79	
LOCN02	LOCN15	LOCN28	LOCN41	LOCN54	LOCN67	LOCN80	
LOCN03	LOCN16	LOCN29	LOCN42	LOCN55	LOCN68	LOCN81	
LOCN04	LOCN17	LOCN30	LOCN43	LOCN56	LOCN69	LOCN82	
LOCN05	LOCN18	LOCN31	LOCN44	LOCN57	LOCN70	LOCN83	
LOCN06	LOCN19	LOCN32	LOCN45	LOCN58	LOCN71	LOCN84	
LOCN07	LOCN20	LOCN33	LOCN46	LOCN59	LOCN72	LOCN85	
LOCN08	LOCN21	LOCN34	LOCN47	LOCN60	LOCN73	LOCN86	
LOCN09	LOCN22	LOCN35	LOCN48	LOCN61	LOCN74	LOCN87	
LOCN10	LOCN23	LOCN36	LOCN49	LOCN62	LOCN75	LOCN88	+
F12=Previous							
1-1 SA MW KS CL IM DM II MARVIN KB PKH318S1							

This screen lists all the locations you can use for the jobs.

For more details of these fields, see the Branch File Maintenance Section.



To return to the Branch File Enquiry Details Screen, select **F12=Previous**.

Period End Dates Enquiry

1... 24/WOP **2...**

Use this option to enquire on the service period end dates for a specific year.

Period End Dates Enquiry Selection Screen



Select the Period End Dates Enquiry option to display the selection screen.

Enter the year for which you want to display the period end dates.

SS504	Demonstration Company	USER BRERETM	17/01/94
	CENTRAL BRANCH		11:21:31
Period End Dates Enquiry			
	Year	<u>93</u>	
F3=Exit			

Fields:

Year

Enter the year you want to enquire on.



Press **Enter** to display the Period End Dates Enquiry Detail Screen.

Period End Dates Enquiry Detail Screen



To display this screen, select the year on the Period End Dates Enquiry Selection Screen and press **Enter**.

This displays all the service period numbers and end dates for the selected year.

SS504	Demonstration Company	USER BRERETM	17/01/94
	CENTRAL BRANCH		11:21:31
Period End Dates Enquiry			
		Year	<u>93</u>
Period	End date	Period	End date
01	0/00/00	15	0/00/00
02	0/00/00	16	0/00/00
03	0/00/00	17	0/00/00
04	0/00/00	18	0/00/00
05	0/00/00	19	0/00/00
06	0/00/00	20	0/00/00
07	0/00/00	21	0/00/00
08	0/00/00	22	0/00/00
09	0/00/00	23	0/00/00
10	0/00/00	24	0/00/00
11	0/00/00	25	0/00/00
12	0/00/00	26	0/00/00
13	0/00/00	27	0/00/00
14	0/00/00	28	0/00/00
		29	0/00/00
		30	0/00/00
		31	0/00/00
		32	0/00/00
		33	0/00/00
		34	0/00/00
		35	0/00/00
		36	0/00/00
		37	0/00/00
		38	0/00/00
		39	0/00/00
		40	0/00/00
		41	0/00/00
		42	0/00/00
		43	0/00/00
		44	0/00/00
		45	0/00/00
		46	0/00/00
		47	0/00/00
		48	0/00/00
		49	0/00/00
		50	0/00/00
		51	0/00/00
		52	0/00/00
F3=Exit F12=Previous			



Select **F3=Exit** to return to the menu.

Working Days Calendar File Enquiry



25/WOP

This enquiry displays the day types for all twelve months in the year, for a selected calendar code and year.

Working Days Calendar File Enquiry Screen



To display this screen, select the Working Days Calendar File option, and then enter a calendar code and year.

SS582	Demonstration Company		USER BRERETM	17/01/94																																				
	CENTRAL BRANCH			11:21:16																																				
Working Days Calendar Enquiry																																								
Calendar code.....	C01	Cust Grp 999																																						
Year	93																																							
	12345678901234567890123456789012345678901																																							
January	B	S	S	W	W	W	W	W	S	S	W	W	W	W	W	S	S	W	W	W	W	W	S	S	W	W	W	W	W	S	S	W	W	W	W	S	S			
February	W	W	W	W	W	S	S	W	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S		
March	W	W	W	W	W	S	S	W	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S		
April	W	W	S	S	W	W	W	W	B	S	S	B	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	
May	S	S	B	W	W	W	W	S	S	W	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	B	W	W	W		
June	W	W	W	W	S	S	W	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W
July	W	W	S	S	W	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	C	C	C	C	C	C	C	C	C	C	C	C	C	C	C	C	
August	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	B	W	
September	W	W	W	S	S	W	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	
October	W	S	S	W	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S
November	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W
December	W	W	W	S	S	W	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	W	S	S	W	W	W	S	S	B	B	W	W	W
F3=Exit F12=Previous																																								

This screen displays the day type for every day in the calendar.

For more details, see the Working Days Calendar File Maintenance section.



Select **F3=Exit** to return to the menu.