

-
-
-
-
-

Chapter 3

Contract Database



Contracts Maintenance



1/WOC

Use this option regularly to set up and maintain the details of all service contracts and quotations for contracts.

Concepts

A contract describes the maintenance terms for one, or more, pieces of equipment installed at one, or more, customer sites.

A contract normally has a start and end date, although it can be a never-ending contract. Each piece of equipment has an inclusion date (which can be later than the contract start date), and, if you remove the equipment from the contract before the contract end date, a removal date.

Always associate a contract with a single customer account, although the contract can be multi-site, to cover equipment installed at several sites.

Description

You identify a contract by the contract number, contract type, and start date.

A contract consists of:

- Contract header: the terms for the contract.
- Contract equipment: the pieces of equipment covered.
- Maintenance visit schedule: the schedule of planned maintenance visits.

You can define a maintenance visit schedule for each piece of equipment on the contract. You can set this up manually, or enter a scheduled visit profile for the contract, the model, or the model group. Workshop Management uses this profile to generate visits automatically.

For any piece of equipment, you can define a price to override the standard price calculated within contract invoicing.

New contracts have a status of pending start date. The day end or contract updating procedure changes the status to active, provided you have reached the contract start date.

You create contract quotations in exactly the same way as true contracts, but you assign the status quotation, using a function. You use the same function to convert the quotation into a contract when the customer accepts the quotation.

Implications

Use the data set up within this function to:

- Maintain a contract's database to identify the equipment's contract status, when a customer places a service call.
- Facilitate automatic invoicing of contracts for rental, meterage or service, in advance, in arrears, or by maintenance visit.
- Determine the pricing and invoicing procedure for engineer visits.

Contract Maintenance Selection Screen



Select the Contracts Maintenance option to display the Contract Maintenance Selection Screen.

Use this screen to select the contract you want to maintain or enter the identification details for a new contract.

SS024	Z1 - GB Demonstration Company	USER GBJBATD0	24/09/97
	"BAUM" TRAINING & SERVICE BRANCH		17:05:47
Contract Maintenance			
Contract Number..... _____			
Contract Type.....?.. _____			
Account Number....?.. GC01_____			
Account Address..... 000_____			
F3=Exit F4=Prompt			
6-24 SA MW KS CL IM DM II EDN400A KB PKH317S1			

Fields:



Note: To define a new contract, you must complete all the fields.

Contract Number

Enter a contract number.

If you only enter a contract number, all contracts with this contract number display, in contract type and start date sequence.

Contract Type

Enter an existing contract type file. You must also enter a contract number.

If you only enter the contract number and type, all relevant contracts display in start date sequence.

Account Number

Enter an account number.

If you only enter an account number, a list of all address codes for this account display.

Account Address

Enter an account address. You must also enter an account number.

If you only enter an account number and address code, all relevant contracts display, in contract type and start date sequence.



To display the next screen, press **Enter**.



Note: The next screen displayed depends upon the information entered.

Contract Selection Screen

 To display this screen, specify an account number and location code and press **Enter** on the Contract Maintenance Selection Screen.

Use this screen to select the contract you want to maintain for the specified account details.

```

SS614          Z1 - GB Demonstration Company    USER GBJBATD0    24/09/97
               "BRUM" TRAINING & SERVICE BRANCH  17:06:14
Contract Selection

Account Number..... GC01          Account Address..... 000
Account Name..... Reeves Chemist's

n   Contract.. Contract Type.....      Contract Start Date.
   0000101    B01          S&R Adv: Basic cover    24/09/97

Enter a selection or new Contract No./Type/Dt  _____ 0/00/00
1=Select
F3=Exit F4=Prompt F12=Previous

9-3      SR      MW      KS      CL      IM      DM      II      EDN400A      KB      PKH317S1
  
```

Fields:

N

Selection field. Enter 1 against the contract you want to maintain.

Contract No

To maintain an existing contract, enter the number of the contract.



Note: To set up a new contract, leave the contract number blank and enter the contract type and date. Workshop Management generates a new contract number.

Contract Type

Enter the type of the contract.

Contract Start Date

Enter the start date of the contract.



To display the Contract Header Maintenance Screen, either select a contract, or enter the contract details and press **Enter**.

Contract Header Maintenance Screen



To display this screen, on the Contract Maintenance Selection Screen or the Contract Selection Screen, enter the details for a new contract, or,

On the Contract Equipment Maintenance Screen, select **F12=Previous**.

Use this screen to enter the payment and other details for the contract.

W0035		Z1 - GB Demonstration Company		USER GBJBANB1	22/04/98
		CENTRAL WORKSHOP			15:59:21
Contract Header Maintenance					
Account Number.....	PLCUS001	000	PL Testing Company		
Contract Number.....	NIC001	Alt. Cont. No.	Version.		
Contract Type.....?	B01	S&R Adv: Basic cover	Status.	Pending start date	
Contract Start Date..	1/05/98	End Date.	30/04/99	Invoice Start.	0/00/00
Tot. Contract Value...					
Duration.....	12	Mantle Code...?			
Customer Order Ref 1..			Order Ref Date..	0/00/00	
Customer Contact.....	MARTIN JONES		Telephone No....	222690000	
Renew Contract (1/0)..	1	Region....	CT Central		
Non-posting Invoices..	0	Header level pricing (1/0)..	0		
Salesman Code.....?			Invoice Summ/Det Form (1/0)...	0	
Invoice Destination...			Direct Debit (1/0).....	0	
Contract Inv. Bill to.			Header currency (1/0).....	1	
Job Invoice Bill to...					
F3=Exit	F4=Prompt	F5=Re-Value	F12=Previous	F14=Service	
F16=Billing maint.	F18=Conditions maint				
F21=Text	F22=Quotation only		F23=Invoice enquiry		

Fields:



Note: Some of the fields on this screen only display if you select the function they relate to for the contract type.

Alt Cont No

Enter an alternative contract number, using up to seven alphanumeric characters.

Version

Enter a version number using up to five alphanumeric characters.

Contract Type

Select an existing contract type. You can only amend this if the contract has a status of Pending Start.

Contract Start Date

Enter the start date for the contract. You can only maintain this field when the contract status is Pending Start. You can backdate the contract.



Tip: The Day End Routines option makes the contract active when you reach the start date.

End Date

Enter the date on which the contract is to end.

If you leave the field blank, Workshop Management calculates the end date as the start date plus the contract duration.

If the contract duration is zero, this is a rolling contract with an end date of 99/99/99.

If you overwrite the original end date with an earlier date, the contract ends early.

Contract Updating and Contract Credit Selection use this date to calculate any credits.

Tot Contract Value

This field displays the total value of the fixed service charges, entered in the Contract Conditions Window, for each contract equipment line. It is the annualised, or term's, nominal value of the service elements of a contract.

Workshop Management does not display a value before the contract start date, or the effective dates for the equipment prices.

The total is not always the invoice value of the contract. For example, if you add or delete equipment during the course of the billing term, and you do not use this field for pricing or invoicing the contract, if header pricing applies.



Tip: Use **F5=Re-value** to update this field.

Header Price

The field only displays if you set the Header Level Pricing field to 1.

This displays the header, or block price for the contract, entered in the Contract Conditions Window. This is the price invoiced for the contract term.

Duration

Enter the contract duration, in months, up to a maximum of 120.

The initial value defaults from the contract type. You can only change this field if the contract status is Pending Start.

If the duration is zero, Workshop Management assumes it is a rolling, or never-ending contract, with an end date of 99/99/99.

Mantle Code

Enter a mantle code defined on the Inventory Descriptions file, against the parameter type MANT.

The Global Price Update option uses the mantle code to identify a group of contracts for a percentage price change.

Customer Order Ref 1

Enter the customer's order reference using up to 20 alphanumeric characters.

Order Ref Date

Enter a date, in DDMMYY format, for the customer's order.



Note: If you set the Contracts field to 1, in the Customer Additional Service Details Maintenance option, you must enter a Customer Order Reference and Date.

Customer Contact

Enter the person to whom you address enquiries relating to this contract. This defaults to the contact set in the Customer Additional Service Details option.

Telephone No

Enter the telephone number of the customer contact. This defaults to the number entered in the Customer Additional Service Details.

Renew Contract

Enter one of the following:

0 - To never renew the contract.

1 - To renew the contract with effect from the end date on the contract header.



Note: This indicator has no effect if you set the contract end date to 99/99/99.

Non-Posting Invoices

Enter one of the following:

0 - To post invoices produced for the contract to the ledgers.

1 - To keep the invoices within Workshop Management and not post them to the ledgers.

Header Level Pricing

Enter one of the following:

0 - To price the contract, for each of the equipment lines, from the contract rates file, if you have not entered a price in the Contract Header Contract Conditions Window. If you enter a price in the Contract Header Contract Conditions Window, this defaults to each charge entered in the Machine Contract Conditions Window for the equipment.

1 - To price the contract based upon the price in the Contract Header Contract Conditions Window. You must enter a fixed service charge on the Contract Header Contract Conditions Window before you can update the contract header. The pricing program ignores any prices you enter in the Machine Contract Conditions Window. Workshop Management uses the prices for comparison: it displays the total in the Tot Contract Value field.

Estimates Allowed

Enter one of the following:

0 - To make no metered charges.

1 - To produce invoices based on estimated meter readings.

Number Of Estimates

Enter the number of consecutive estimates, between 1 and 999, you allow for billing.

Pool Contracts

This is only valid for contracts with meterage billing parameters defined on the contract type. Enter one of the following:

0 - Unpooled. To assess contracts for invoicing on the basis of the individual machine. If the number of copies or vends is less than the minimum, then you charge the minimum; if the number exceeds the minimum, then you charge for the additional copies or vends.

1 - Pooled. To assess for invoicing on the basis of the aggregated minima of all the machines on the contract. That is, you can offset the machines with an excess of copies or vends against those machines whose usage is less than the minimum.

Tile Contracts

This is only valid for contracts with meterage billing parameters defined on the contract type. Enter one of the following:

0 - Non-tiled.

1 - Tiled. Tiled contracts are a special form of pooled contract. You can only use tiled contracts if you use pooled contracts. You define a termination date for pool contracts, however you can extend tiled contracts for each new item of equipment you add to the contract. Workshop Management calculates the new termination date by adding the contract term to the inclusion date of the machine you have added.

Copy Kit

For future development.

Salesman Code

Enter a salesperson. You set up the codes as parameter type SN on the Inventory Descriptions file. This is for memo purposes only.

Invoice Summ/Det Form

For future development.

Invoice Destination

Enter the customer's account and address. This is the address printed on all invoices and credit notes for the contract.

Direct Debit

For future development.

Contract Inv Bill To

If you want to send contract invoices to a different customer, enter the customer and address.

Header Currency

Enter one of the following:

0 - To invoice the equipment in the currency of the equipment installation site.

1 - To invoice all equipment in the currency of the account on the contract header.

Job Invoice Bill To

If you want to send job invoices to a different customer, enter the customer and the address.

Functions:

F5

Re-Value. Use this function to total the nominal value of the fixed service charges for all the contract lines. The new value displays in the Tot. Contract Value field.

F14

Service. Use this function to set up the service parameters.

F16

Billing Maint. Use this function to set up the billing types and charges.

F18

Conditions Maint. Use this function to set up the contract conditions.

F21

Text. Use this function to enter the text associated with the contract.

F22

Quotations Only/Accept Contract. Use this function to change Pending Start contracts to quotations and vice versa.

F23

Invoice Enquiry. Use this function to display the invoice enquiry.



Press **Enter** twice, and then select **F8=Update** to save the information and display the Contract Equipment Maintenance Detail Screen.

Service Parameters Window (F14)



To display this window, select **F14=Service** on the Contract Header Maintenance Screen.

Use this window to enter the response and visit profiles for the contract.

W0035	Z1 - GB Demonstration Company	USER GBJBANB1	22/04/98
	CENTRAL WORKSHOP		15:59:21
Contract Header Maintenance			
Account Number.....	PLCUS001	000	PL Testing Company
Contract Number.....	NIC001	Alt. Cont. No.	Version.
Contract Type.....?	B01	S&R Adv: Basic cover	Status. Pending start date
Contract Start Date..	1/05/98	End Date. 30/04/99	Invoice Start. 0/00/00
Tot. Contract Value..			
Duration.....	12	Mantle Code..?	
Customer Order Ref 1..		Order Ref Date..	0/00/00
Customer Contact.....	MARTIN JONES	Telephone No....	222690000
Renew Contract (1/0)..	1	Region....	CT Central
Service Parameters			
Response hours.....	8:00		
Schedule visit profile..			
Allow service cover when contract pending (1/0).	1		
Use start date rates....	1	Or, Until....	0/00/00
Global Price Code..?			
Bill to....			
F4=Prompt F8=Update F12=Previous			
F16=Billing maint. F18=Conditions maint			
F21=Text F22=Quotation only F23=Invoice enquiry			

Fields:

Response Hours

Enter the response time for the contract in hhh:mm format. The response applies to all contract lines, unless you give a line its own special response time.

Scheduled Visit Profile

Enter a scheduled visit profile (SVP) of up to three alphanumeric characters.

The profile generates the visits to each piece of equipment on a contract. Workshop Management selects the profile according to the following hierarchy:

1. Use the SVP on the contract header.
2. If there is none, use the SVP for the model.
3. If there is none, use the SVP for the model group.
4. If there is none, use the SVP from the company profile.
5. If there is none, do not generate visits.

As long as Workshop Management finds an SVP, it generates visits for the equipment line on the contract when you select option 8 on the Contract Equipment Maintenance Screen.



*Note: When you enter an SVP, you can use **F14=Schedule Override** to edit the SVP details.*

Use Scheduled Visit Override At Renewal

Enter one of the following:

0 - To leave the SVP field blank at contract renewal. If you leave the field blank, the SVP hierarchy determines the equipment visits generated on the renewed contract.

1 - To use the *OV amendments to the SVP when you renew the contract and generate equipment visits.

Allow Service Cover When Contract Pending

This defaults from System Parameters File Maintenance. Enter one of the following:

0 - For contract cover to be effective on and after the contract start date.

1 - To treat all calls for the equipment on the contract, logged prior to the contract start date, as though the contract cover is effective.

Use Start Date Rates

Enter one of the following:

0 - To use the price lists effective at the date you carry out the work, for the chargeable work.

1 - To use the labour rates and parts prices effective on the contract start date to price any chargeable work carried out on the equipment.

Or, Until



Note: Only enter a value if you set the Use Start Date Rates field to 0.

Enter a date (DDMMYY). Workshop Management only uses the labour and parts price lists for chargeable work until this date. After this date, it uses the price lists effective on the date you carry out the work.

Global Price Code

Enter a global price. The Global Price Update option uses this to select contracts to include in the price revision. Set up these codes under the parameter type GLPR, in the Codes/Parameter File Maintenance option.

Bill To

Enter the customer and address where you want to send the bill for this contract.

Functions:

F14

Schedule Override. Use this function to change the scheduled visit profile for the contract.



If you update the SVP, select **F8=Update**. Select option 8 to regenerate equipment visits for each record. The SVP code displays as *OV to show you have overridden the standard SVP code.

Billing Parameters Window (F16)



To display this window, select **F16=Billing Maintenance** on the Contract Header Maintenance Screen.

Use this window to define the pricing cycle, billing types and charges.

```

SS035                Z1 - GB Demonstration Company    USER GJBATD0    24/09/97
                   "BAUM" TRAINING & SERVICE BRANCH    17:09:40
Contract Header Maintenance    UPDATE

Account Number..... GC01          000    Reeves Chemist's
Contract Number..... 0000101      Alt. Cont. No.      Version.
Contract Type.....?.. B01    S&R Adv: Basic cover    Status. Pending start date
Contract Start Date.. 24/09/97    End Date. 23/09/98    Invoice Start. 0/00/00
Billing Parameters                                0.00
Set all Next pricing cycle to dates to: 2/00/00
Set all Next pricing cycle from start days to: 0

Billing type:      Term    Freq    Adv/Visit/Ann    Next pricing cycle
                  (mths) (mths) (0/1/2)              From      To
Fixed Service Chrg.: 12      3      0 (0/1/2)        24/09/97    23/09/98
Rental Charge.....: 12      3      0 (0/1/2)        24/09/97    23/09/98

F8=Update    F12=Previous
F3=Exit    F4=Prompt    F5=Re-Value    F8=Update    F12=Previous    F14=Service
F16=Billing maint.    F18=Conditions maint

10-46    SA    MW    KS    CL    IM    DM    II    EDN400A    KB    PKH317S1
  
```

Fields:



Note: Only the billing parameters selected for the contract type display.

Set All Next Pricing Cycle To Dates To

This defaults to the end date of the first contract term.

Enter a date if the first term of the contract is shorter than the standard term.

Set All Next Pricing Cycle From Start Days To

This defaults to the contract start day, or to the first day of the following month, if defined in System Parameters Maintenance.

Enter the day to send the invoice. If you enter a day earlier than the contract start day, Workshop Management assumes it is the following month.

Fixed Service Charge - Term

Enter the number of months, within the contract duration, for which you cannot change the contract price. This is also the number of periods covered by the Fixed Service Charge.

Rental Charge - Term

Enter the number of months, within the contract duration, for which you cannot change the rental price. This is also the number of periods covered by the Rental Charge.

Reconciliation Charge - Term

Enter the number of months after which you verify the number of machine cycles (copies or vends) against the cycles you have billed in advance, or as a result of an estimated or customer advised meter reading.

Freq

Enter how often you send an invoice. This must be between 0 and the maximum number in the term, and must be equally divisible into the term. For example:

1 - Monthly

3 - Quarterly

12 - Annual invoicing in a 12 month term.

Enter 0 if Adv/Vis/Arr is set to 1.

Adv/Visit/Arr

Advance, visit or arrears billing. This defaults to the value in the Invoice Schedule field on the contract type. Enter one of the following:

0 - To invoice in advance. The release date is the start of the invoice period. Issue the invoice for each invoice term before the term starts.

1 - To invoice each planned maintenance visit. This is a Job Invoice, raised as the result of the engineer's Technical Report. You must set Freq to 0.

2 - To invoice in arrears. The release date is the end of the invoice period. Issue the invoice for each invoice term after the term finishes.

Next Pricing Cycle To

This defaults to the Next Pricing Cycle From date plus the billing term.

Enter the end of the contract term. You can only change this field when you first enter a contract. The pricing cycle can cover one or more invoices, depending on the invoice frequency within the term.

Contract price increases during the term do not take effect until after the Next Pricing Cycle To date.



Select **F8=Update** to save the information and return to the previous screen.

Contract Conditions Window (F18)



To display this window, select **F18=Conditions Maintenance**, on the Contract Header Maintenance Screen.

Use this window to enter the charges that apply at contract level. The fields displayed depend upon the type of contract you are maintaining.



Note: These charges apply to all machine lines, unless you set up a machine line condition. If you amend the Header details, check the conditions for each machine.



Note: You must not change the Month or Term setting after you have set up Workshop Management.

```

W0035          Z1 - Demonstration Company      USER GBJBANB4   12/02/98
                  CENTRAL WORKSHOP              9:08:52
Contract Header Maintenance      UPDATE

Account Number..... C01          000    Collection document slu31125
Contract Number..... LML000B      Alt. Cont. No. _____ Version. _____
Contract Type.....?.. MEI    Meter type           Status. Active
Contract Start Date.. 1/01/98    End Date. 31/12/98 Invoice Start. 1/01/98

Contract Conditions

Cover type.?.  █    Eff.Date: 1/01/98    GBP
                               Minimum Volume.....: _____0

Meter 1: Band  Volume to  Per copy
      1  _____0  _____00
      2  _____0  _____00
      3  _____0  _____00
      4  _____0  _____00
      5  _____0  _____00

F4=Prompt  F8=Update  F10=Add  F12=Previous

11-20  SA  MW  KS  CL  IM  DM  II  EDN400A  KB  PKH318S1
  
```

Fields:



Note: Only the contract conditions selected for the contract type display.

Cover Type

Enter a header level cover type as required.

Eff Date

Enter the date the contract becomes effective. This defaults to the contract start date.

Fixed Service Charge

Enter the service charge. This either applies for the term of the contract, or for a month, depending on the setting of the Processing By Month Or Term field in the System Parameters File Maintenance option.

Fixed Visit Charge

Enter the charge for each visit.

Fixed Rental Charge

Enter the rental charge. This applies either for the term of the contract, or for a month, depending on the setting of the Processing By Month Or Term field in the System Parameters File Maintenance option.

Pre-Billing Value/Volume

The contract type determines whether this entry is for a monetary value or a number of copies or vends.

Enter the monthly value or quantity for copies or vends.

You can only use this field if you set the Processing By Month Or Term field on the System Parameters Maintenance Screen 1 to Month.



Note: The header charge applies to all machines on the contract, you cannot change this value on the conditions for individual machine.

Minimum Volume

Enter the number of copies, or vends, you invoice each month. You can only use this field if you set the Processing By Month Or Term field on the System Parameters Maintenance Screen 1 to Month.

Copies In Rental

Enter the number of copies, or vends, per month to include in the rental charge.

Free Copies

Enter the number of free copies you allow on each monthly billing.

Meter N - Band Volume To

Enter the maximum number of copies to which the price for the band applies.



Note: The volume for band 1 must not be less than the minimum volume.

Meter N - Band Price Per Copy

Enter the price per copy, charged up to the band maximum. To express the copy price in pence or cents, set the currency multiplier on the system parameter file.



Note: If you specify meterage, you must enter at least one price band for meter 2.

Functions:

F10

Add. Use this function to add more charges with different effective dates.



Tip: Page up and down to display differently

dated contract conditions.



Select **F8=Update** to save the information, and select **F12=Previous** to return to the previous screen.

Contract Maintenance Invoice Enquiry Screen (F23)



To display this screen, select **F23=Invoice Enquiry** on the Contract Header Maintenance Screen.

SS645	Demonstration Company	USER BRERETM	18/11/93
	CENTRAL BRANCH		13:32:40

Contract Maint Invoice Enquiry

Account Number..... C03 000 Jones and Crossland Ltd.
Contract Number..... 0000115 Alt. Cont. No: Version:
Contract Type..... B01 Basic cover Status: Active
Contract Start Date. 6/04/93 End Date: 99/99/99 Invoice Start: 6/04/93

Total Revenue.....: 179.19
Volume after last Interim/Reconciliation..:

Invoice		Value	Period	
Number	Type		From	To
1500641	01	150.00	6/04/93	5/04/94
1500641	02	4.17	6/04/93	5/05/93

F12=Previous

This screen displays the invoice details, including:

- Account number.
- Contract details.
- Invoice number, type, value and dates.

Functions:

F14

Base Currency. Use this function, in a multi-currency company, to change the base currency displayed.



To return to the previous screen, select **F12=Previous**.

Contract Equipment Maintenance Detail Screen



To display this screen, enter the details on the Contract Header Maintenance Screen and select **F8=Update**, or,

Select the contract you want to maintain on the Contract Selection Screen.

Use this screen to select the equipment you want to include on the contract. If the equipment, displayed at the bottom of the screen, is highlighted, you have already included it in a pending or active contract.

SS025	Z1 - GB Demonstration Company	USER GBJBATD0	24/09/97
	"BRUM" TRAINING & SERVICE BRANCH		17:07:42
Contract Equipment Maintenance		Contract Start Date.. 0000101 B01	24/09/97
Account Number..... GC01	000	Reeves Chemist's	
Position to Serial Number...			
Inst.Adr Loc Model	Serial	Stat Inc. Dt. Remov dt R.Hrs Ust	
GC01 000 WA10	WAN0001	Pen 24/09/97 0/00/00	0
Select by Account No...?.. GC01			
Loc Model	Serial	Addr. 000 Model..?. WA10	
_ 000 WA10	WAN0002	Loc Model	Serial
_ 000 WA10	WAN0003		
1=Add 2=Conditions 3=Peripherals 4=Invoice history 5=Meter history			
F3=Exit F4=Prompt F12=Previous F21=Text F23=More options			
8-2 SP MW KS CL IM DM II EDN400A KB PKH317S1			

Fields:

Position to Serial Number

Enter the serial number at which you want to position the cursor.

Unnamed (Select)

This is the select field on the top half of the screen.

Enter one of the following:

2 - Conditions. To enter charges applied to the machine. These charges override the contract header conditions. If Header Level Pricing applies to the contract, the Pricing Program ignores these values.

3 - Peripherals. To enter additional charges for any peripherals attached to the machine.

4 - Invoice history. To display a screen showing the invoice history.

5 - Meter history. To display a screen showing all the previous meter readings from all sources for the machine.

6 - Statistics. To display the average copies or vends and total usage. This is only available where you use meterage.

7 - Visits. To amend or display the service visits scheduled for the machine. You can add visits, but be careful if you have already priced or invoiced the contract. Run Load PM Jobs again to convert the added visits.

8 - Generate visits. To generate a schedule of planned visits by period for the machine. This depends on the schedule visit profile (SVP) hierarchy to generate visits using the first SVP found:

1. Use the SVP on the contract header.
2. If not found, use the model file SVP.
3. If not found, use the model group file SVP.
4. If not found, use the company profile SVP.
5. If not found, do not generate any visits.

If visits exist for the machine, the Vst column displays 1; if you have not generated visits, the column displays 0.



Note: Make sure you set up the Daily Calendar file far enough ahead to handle the visits; otherwise, the last column continues to display Vst - 0.

9 - Delete. To enter a date and cancellation reason code to remove the equipment line from the contract. You set up cancellation reason codes under parameter type CCRC in the Codes/Parameter File Maintenance option.

Inc Dt

Enter the date from which you want to include the equipment on the contract. This defaults to the contract start date.

The machine line remains at a status of pending until you reach the inclusion date and update the contracts (either by running the Contract Updating option, or the Day End Routines option).

Remov Dt

Enter the date from which you want to remove the machine from the contract.

The machine expires from the contract when you update the contract (either by running the Contract Updating option, or the Day End Routines option). Workshop Management then cancels all outstanding visits.

Rsp Hrs

Enter the response time for this machine in hours and minutes (hhh:mm).

This response time overrides the contract header response time, and Workshop Management uses it, when you log a job, to calculate the target time.

Select By Account Address

Enter an installation site and press **Enter** to display all equipment at the site.

Equipment already on a contract displays with the model and serial number highlighted. If you add this equipment to another contract, it appears on the Contract Updating error report, and its status on the new or active contract remains Pending. A machine can only be active on one contract at any one time.



Tip: Leave this field blank and enter a model in the next field to display all equipment of that model belonging to the customer account, regardless of installation site.

Model

To display a list of all equipment, for a model, for any site within the customer account, leave the Select By Account Address field blank and enter a model.

To display a list of all equipment, for a model, for a site within the customer account, enter an address in the Select By Account Address field and enter a model.

Untitled

This is the select field on the bottom half of the screen.

Enter 1 against a machine to add it to the contract. Highlighted machines are already on a contract. You can add them to a new contract, but they can only be active on one contract at a time. On all other contracts they are pending.

Adding a machine automatically displays the Equipment Conditions Window. If header level pricing applies to the contract, Workshop Management attaches the header price to the first machine you add to the contract. For this reason, you can add a dummy machine to use with header pricing.

Functions:

F21

Text. Use this function to amend and define text associated with the contract.



Press **Enter** to save the information, and then select **F3=Exit** to leave the screen.

Machine Contract Conditions Window (Option 2)



To display this window, on the Contract Equipment Maintenance Details Screen, select a piece of equipment, with option 2, or add new equipment to the contract.

Use this window to enter machine level charging information.

The charges apply, per visit, for the term of the contract, or for a month, depending on the setting of the Processing By Month Or Term field in the System Parameters File Maintenance option.



*Note: All these fields default to the header conditions you enter using **F18=Conditions**. Workshop Management does not carry through any subsequent changes to the **F18=Conditions** Maintenance.*



Note: You must not change the month or term processing after initially setting up the system.

W0025	Z1 - Demonstration Company	USER GBJBANB4	12/02/98																		
CENTRAL WORKSHOP			9:12:07																		
Contract Equipment Maintenance																					
Account Number..... C01	000	Contract Start Date.. LML000A MET	1/01/98																		
Position to Serial Number...		Collection document slv31125																			
Inst.Adr Loc Model	Serial	Stat Inc. Dt. Remov dt R.Hrs Vst																			
2 C01 METER	LML1	Act 1/01/98 0/00/00	0																		
Contract Conditions																					
Model.: METER		LML1																			
Cover Type..?.. *NQ	Eff.Date.: 1/01/98	GBP																			
		Minimum Volume..... 5000																			
<table border="1"> <thead> <tr> <th>Meter 1: Band</th> <th>Volume to</th> <th>Per copy</th> </tr> </thead> <tbody> <tr> <td>1</td> <td>9999999999</td> <td>999.99</td> </tr> <tr> <td>2</td> <td>0</td> <td>.00</td> </tr> <tr> <td>3</td> <td>0</td> <td>.00</td> </tr> <tr> <td>4</td> <td>0</td> <td>.00</td> </tr> <tr> <td>5</td> <td>0</td> <td>.00</td> </tr> </tbody> </table>				Meter 1: Band	Volume to	Per copy	1	9999999999	999.99	2	0	.00	3	0	.00	4	0	.00	5	0	.00
Meter 1: Band	Volume to	Per copy																			
1	9999999999	999.99																			
2	0	.00																			
3	0	.00																			
4	0	.00																			
5	0	.00																			
F8=Update F10=Add F12=Previous																					
11-20 SR MW KS CL IM DM II EDN400A KB PKH318S1																					

Fields:



Note: Only the contract conditions selected for the contract type display.

Cover Type

Enter an equipment level cover type.

Eff Date

Enter the date these charges become effective, in DDMMYY format.

Fixed Service Charge

Enter the charge to service this piece of equipment.

Leave blank and press **Enter** to display the appropriate charge for the division, model group, model sub-group and model, for the contract type and term.

If header level pricing applies to the contract, the pricing program ignores this charge. The sum of all the charges displays in the Total Contract Value field on the header screen.

Fixed Visit Charge

Enter the charge for each service visit to the machine.

For contracts billed in advance or in arrears, Workshop Management multiplies the fixed visit charge by the number of visits in the term.

For contracts invoiced after each visit, Workshop Management includes the fixed visit charge on a job invoice.

Leave blank and press **Enter** to display the appropriate charge for the division, model group, model sub-group and model, for the contract type and term.

Fixed Rental Charge

Enter the rental charge.

Leave blank and press **Enter** to display the appropriate charge for the division, model group, model sub-group and model, for the contract type and term.

Minimum Volume

Enter the minimum number of copies, or vends, you invoice each month.

Workshop Management only uses this value if you set the Processing By Month Or Term field, on the System Parameters File Maintenance Screen 1, to Month.

Copies In Rental

Enter the number of copies, or vends, per month to include in the rental charge.

Free Copies

Enter the number of free copies, or vends, allowed on each monthly billing.

Meter N - Band Volume To

Enter the maximum number of copies to which the price for the band applies.



Note: The volume for Band 1 must not be less than the minimum volume.

Meter N - Band Price Per Copy

Enter the price per copy to charge up to the band maximum.

You can express the copy price in pence, or cents, by setting the currency multiplier on the system parameter file.

For pool contracts, you can only define copy charges on the contract header conditions. All machines must use the same copy price.

Functions:

F10

Add. Use this function to add new conditions with different effective dates.



Tip: Page up and down to display differently dated contract conditions.



Select **F8=Update** to save any changes.



Note: If you set up this contract type with the Automatically Generate Service Schedule field set to 1, you can select a scheduled visit profile for the new piece of equipment before Workshop Management does the update.

Contract Equipment Peripherals Screen (Option 3)



To display this screen, select a piece of equipment with option 3 on the Contract Equipment Maintenance Details Screen.

Use this screen to select the peripherals for which you want to enter extra charges.

SS648	Demonstration Company CENTRAL BRANCH	USER BRERETM	10/03/94 11:12:38	
Contract Equipment - Peripherals				
Account Number.....	C03	000 Jones and Crossland Ltd.		
Contract Number.....	0000115	Contact: DAVID FEATHER	Tel: 0926 500600	
Model number.....	WA10	Serial number.....	W920100	
Contract Start Date.	6/04/93	End Date: 99/99/99	Invoice Start: 6/04/93	
Sel	Model number	Serial number	Date Inc.	Date Removed
1	SP100	W920100/P	6/04/93	<u>0/00/00</u>
1=Select				
F12=Previous				

Fields:

Sel

Selection. Enter 1 alongside a model number to enter the additional charges for the peripheral.

Peripheral Removal Date

Enter the date to remove the peripheral from the contract.

Contract Updating, which is part of the Day End procedures, removes the equipment from the contract on the removal date.



Select a particular peripheral, using option 1, to display the Peripheral Conditions Window.

Peripheral Conditions Window (Option 1)



To display this window, select a peripheral using option 1 on the Contract Equipment Peripherals Screen.

Use this window to set up the charges and effectivity date for the peripheral.



Note: When you invoice the contract, Workshop Management adds these charges to the main machine charge, according to the pricing rules applied to that machine.

SS648	Demonstration Company		USER BRERETM	10/03/94
	CENTRAL BRANCH			11:12:38
Contract Equipment - Peripherals				
Account Number.....	C03	000 Jones and Crossland Ltd.		
Contract Number.....	0000115	Contact: DAVID FEATHER	Tel: 0926 500600	
Model number.....	WA10	Serial number..... W920100		
Contract Start Date.	6/04/93	End Date: 99/99/99	Invoice Start: 6/04/93	
Peripheral Conditions				
Sel	Model number	Serial	Effective date....	6/04/93
1	SP100	W9201	Service charge....	25.50
			Rental charge....	15.02
F8=Update F10=Add F12=Previous				
1=Select				
F12=Previous				

Fields:



Note: Only the peripheral conditions selected for the contract type display.

Effective Date

Enter the date the price list becomes effective. This defaults to the contract start date.

Service Charge

Enter the additional service charge for the peripheral.

Rental Charge

Enter the additional rental charge for the peripheral.

Additional Minimum Volume

Enter the additional volume for the peripheral. Workshop Management adds this volume to the minimum for the main machine to calculate copy or vending charges.

Additional Copy Price

Enter the additional price per copy. Workshop Management adds this to the price per copy of the main machine, to calculate the total copy price, to apply when you invoice copy or vending charges.

Functions:

F10

Add. Use this function to add more peripheral conditions with different effective dates.



Select **F8=Update** to save the changes and return to the previous screen.

Contract Line Invoice Enquiry Screen (Option 4)



To display this screen, select a piece of equipment with option 4 on the Contract Equipment Maintenance Details Screen.

SS649	Demonstration Company	USER BRERETM	18/11/93
	CENTRAL BRANCH		13:36:17

Contract line invoice enquiry

Account Number..... C03 000 Jones and Crossland Ltd.
Contract Number..... 0000115 Contact: DAVID FEATHER Tel: 0926 500600
Model number..... WA10 Serial number..... 101000
Contract Start Date. 6/04/93 End Date: 99/99/99 Invoice Start: 6/04/93

Total Revenue..... 179.19
Volume after last Interim/Reconciliation...

Invoice		Value	Period	
Number	Type		From	To
1500641	02	4.17	6/10/93	5/11/93
1500641	02	4.17	6/09/93	5/10/93
1500641	02	4.17	6/08/93	5/09/93
1500641	02	4.17	6/07/93	5/08/93
1500641	02	4.17	6/06/93	5/07/93
1500641	02	4.17	6/05/93	5/06/93

F12=Previous

This screen displays the invoice line details, including:

- Account number.
- Contract details.
- Invoice number, type, value and dates.

Functions:

F14

Base Currency. Use this function, in a multi-currency company, to change the base currency displayed.



To return to the previous screen, select
F12=Previous.

Meter Reading History Screen (Option 5)

-  To display this screen, select a piece of equipment with option 5 on the Contract Equipment Maintenance Details Screen.

SS651	Demonstration Company CENTRAL BRANCH	USER BRERETM	18/11/93 13:36:38
-------	---	--------------	----------------------

Meter Reading History

Account Number..... C03 000 Jones and Crossland Ltd.
Contract Number..... 0000115 Contact: DAVID FEATHER Tel: 0926 500600
Model number..... WA10 Serial number.....: 101000
Contract Start Date. 6/04/93 End Date: 99/99/99 Invoice Start: 6/04/93

Reading date	Reading type	Meter 1	Meter 2
17/11/93	03	2125601	25456

F12=Previous

This screen displays, for the equipment selected on the Contract Equipment Maintenance Details Screen:

- Meter reading date.
- Reading type.
- Meter readings.

-  To return to the previous screen, select **F12=Previous**.

Meter Statistics Screen (Option 6)



To display this screen, select a piece of equipment with option 6 on the Contract Equipment Maintenance Details Screen.

SS650	Demonstration Company	USER BRERETM	18/11/93
	CENTRAL BRANCH		13:37:01
Meter Statistics			
Account Number.....	C03	000 Jones and Crossland Ltd.	
Contract Number.....	0000115	Contact: DAVID FEATHER	Tel: 0926 500600
Model number.....	WA10	Serial number....	101000
Contract Start Date.	6/04/93	End Date: 99/99/99	Invoice Start: 6/04/93
Copy Volumes...:	Months.....	3	6
	Produced...:	0	0
	Invoiced...:	0	0
	12		
Invoice Code	Period	Copies Produced	
	From To		
	THERE ARE NO CONTRACTING STATISTICS		
	AT PRESENT FOR THIS CONTRACT		
F12=Previous			

This screen displays, for the equipment selected on the Contract Equipment Maintenance Details Screen:

- Account and contract details.
- Copy or vend volumes.
- Invoice details.



To return to the previous screen, select **F12=Previous**.

Scheduled Visits Maintenance Screen (Option 7)



To display this screen, on the Contract Equipment Maintenance Details Screen, select a piece of equipment with option 7.

If you have previously selected 8 - Generate Visits, the screen displays the visits set up for the equipment. You can amend or delete existing visits and add further visits.

If you add visits after you have priced or invoiced the contract, you must charge separately for the new visits on a Job Invoice. Workshop Management only converts the new visits after the next run of the Load PM Jobs program.

SS026	Demonstration Company		BRERETM	9/04/93
	CENTRAL BRANCH			15:27:58
Scheduled Visits Maintenance				
Contract No./Type/Dt		0000115 B01 Basic cover	6/04/93	
Model.....	WA10	Serial....	101000	Quantity 1
n	Period	No.Vis	Job Category.....	Hours
-	9304	1	CM Service visit	1:30
-	9307	1	CM Service visit	2:00
-	9310	1	CM Service visit	1:45
-	9401	1	CAL Calibration	2:00
-	9404	1	CM Service visit	1:30
-	9407	1	CM Service visit	2:00
				+
Srv. Period (YYPP) ____		No. of Visits ____	Job Cat. ____	Est. Hours 0:00
Total Visits 7		Use these visits on renewal? (1/0) 0		
Start next profit load from (YYPP) 9999 (9999 = never, 0 = re-start)				
Special Price		.00000 Engineer		
1=Amend 4=Delete				
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous				
F21=Text				

Fields:

N

Selection field. Enter one of the following:

1 - To amend the line. The line displays in the fields in the lower half of the screen, where you can make changes.

4 - To delete the line. Workshop Management marks the line DELETED; and removes it when you update. If you are removing the machine from the contract, you only need to enter a date in the Remov DT field on the Contract Equipment Maintenance Detail Screen. When you run the Day End Routines option on that date, Workshop Management deletes the records, including the visit records.



Tip: Once you have run Load PM Jobs, you cannot delete visit lines.



Tip: To add or amend a visit complete the following fields, which display at the bottom of

the screen.

Service Period

Enter the service period of the scheduled visit, in YYPP format. This must be between the contract start and end dates.

Number of Visits

Enter the number of scheduled visits, for this piece of equipment, within this service period. This must be greater than 0.

Job Category

Select the type of job done on this scheduled visit.

Estimated Hours

Enter the estimated length for the scheduled job, in the format hhh:mm.

Total Visits

Enter the total number of scheduled visits to make to this piece of equipment during the contract term. This must be greater than 0.

Use These Visits on Renewal

Enter one of the following:

0 - When you renew the contract, to generate visits according to the contract header scheduled visit profile.

1 - When you renew the contract, to base the new scheduled service visits on the revised scheduled service visits shown here.

Start Next Profile Load from (YYPP)

Enter either a service period in YYPP format or 9999. This cannot be less than the current period.



Note: Workshop Management can update this by referring to the last scheduled visit generated.

Functions:

F21

Text. Use this function to add or update text associated with the visits.



Select **F8=Update** to save changes.

Delete Record Window (Option 9)

 To display this window, select a piece of equipment with option 9 on the Contract Equipment Maintenance Details Screen.

Use this screen to specify when Workshop Management should remove the equipment from the contract.

W0025	Z1 - GB Demonstration Company	USER GBJBANB1	22/04/98
	CENTRAL WORKSHOP		16:10:20
Contract Equipment Maintenance			
Account Number..... PLCUS001		Contract Start Date.. NIC001	B01 1/05/98
Position to Serial Number...		PL Testing Company	
Inst.Adr	Loc Model	Serial	Stat Inc. Dt. Remov dt R.Hrs Vst
g PLCUS001	PROJECTOR001	S5022	Pen 1/05/98 0/00/00 0
Select by Account No...?.. PLCUS001 Addr. 000 Model...?..			
Loc Model	Serial	Loc Model	Serial
DELETE RECORD			
Inst.Adr PLCUS001 Loc. 000 Model. PROJECTOR001 Serial. S5022			
Removal date... 0/00/00 Cancel Reas Code			
F4=Prompt F11=Delete F12=Previous			
6=Statistics 7=Visits 8=Generate visits 9=Delete			
F3=Exit F4=Prompt F12=Previous F21=Text F23=More options			

Fields:

Removal Date

Enter the date, in DDMMYY format, to remove this equipment from the contract.

Cancellation Reason Code

Select a cancellation reason code. You set up the codes under parameter type CCRC in Codes/Parameter File Maintenance.

Functions:

F21

Text. Use this function to add text to the deletion record.

 Select **F11=Delete** to delete the record and return to the previous screen.

Contract Type Maintenance

1... **2...** 2/WOC

Use this option to maintain the details of all contract types.

You use this option during set-up, and whenever you need to add, amend or delete a contract type code.

Contract types describe the different types of contract and their associated terms and billing parameters.

Implications

You must set up at least one contract type before you can create any contracts.

You cannot delete a contract type if you have used it in a contract.

Workshop Management uses the data associated with a contract type to provide:

- Default data (contract duration, invoice schedule, invoice at start date flag) when you create a contract.
- Call escalation monitoring, using the guaranteed response time to calculate the target arrival time for the engineer.

Contract Type Maintenance Selection Screen



Select the Contract Type (Maintenance) option to display the Contract Type Maintenance Selection Screen.

Use this screen to select the contract type you want to maintain or create.

SS032	Demonstration Company CENTRAL BRANCH	BRERETM	16/09/93 15:12:37
Contract Type Maintenance			
Contract Type..... <u>B01</u>			
F3=Exit F4=Prompt			

Fields:

Contract Type

Enter a new or existing contract type.

You must set up a contract type with the code *NO. This must have a fixed service charge for visit-only contracts. The contract routines do not invoice or price these, but job pricing and invoicing do.



Select a contract type and press **Enter** to display the Contract Type Maintenance Screen.

Contract Type Maintenance Screen



To display this screen, on the Contract Type Maintenance Selection Screen, select a contract type and press **Enter**.

Use this screen to enter the basic details for the selected contract type.

SS032	Demonstration Company	BRERETM	16/09/93
	CENTRAL BRANCH		15:13:24
Contract Type Maintenance ADD			
Contract Type..... B01 Basic cover			
Automatically generate service schedule?	1	(1=yes 0=no)	
Quotation required on renewal?	0	(1=yes 0=no)	
Use Contract Start Date Rates?:	0	(1=yes 0=no)	
Response hours guarantee: (hhh:mm)	0800		
Contract duration (months)	0		
Termination notice in days:			
Invoice Schedule.....	0	(0=Advance, 1=Visit, 2=Arrears)	
Contract Type to Include Following Parameters? (1=yes 0=no)			
Fixed Service Charge.....	1	Interim Charges.....	0
Fixed Rental Charge.....	1	Reconciliation Charges..	0
Fixed Visit Charge.....	0	Copies Incl. Rental....	0
Minimum Volume.....	0	Copy Charges 1.....	0
Pre Billing Value.....	0	Copy Charges 2.....	0
Pre Billing Volume.....	0	Free Copies.....	0
		Free Visits.....	0
F3=Exit F8=Update F12=Previous			

Fields:

Contract Type Description

Enter a description of up to 20 alphanumerics, to identify the type of contract.

Automatically Generate Service Schedule

Enter one of the following:

0 - To prevent users selecting a scheduled visit profile, when adding equipment to this contract type.

1 - To allow users to select a scheduled visit profile, when adding equipment to this contract type.

Quotation Required On Renewal

Enter one of the following:

0 - If this type of contract renews as a pending contract.

1 - If this type of contract renews as a quotation.

Use Contract Start Date Rates

Enter one of the following:

0 - To use, in job pricing, labour rates and parts prices effective on the date of call out or date of engineer's visit.

1 - To use, in job pricing, labour rates and parts prices effective on the contract start date.

Response Hours Guarantee

Enter the response time guaranteed by this type of contract. Job escalation routines use this.

Contract Duration (Months)

Enter the standard contract duration, in calendar months. Set this duration to zero (blank) if a contract runs indefinitely.

Termination Notice In Days

Enter the number of penalty days for contract cancellation. Workshop Management uses this to calculate the contract credit. For example, to charge a customer for 10 days' cover when they cancel a contract, enter 10.

Invoice Schedule

Enter one of the following:

0 - To invoice in advance.

1 - To invoice after each scheduled visit.

2 - To invoice in arrears. You cannot print the invoice until after the end of any instalment period.

Fixed Service Charge

Enter one of the following:

0 - To prevent users applying fixed service charges to this contract type.

1 - To allow users to apply fixed service charges, using contract conditions.

Interim Charges

Enter one of the following:

0 - To prevent users applying interim charges to this contract type.

1 - To allow users to apply interim charges, using contract billing.

Use interim charges to periodically invoice for actual or estimated copies, in excess of the minimum.

Fixed Rental Charge

Enter one of the following:

0 - To prevent users applying fixed rental charges to this contract type.

1 - To allow users to apply fixed rental charges using the Contract Conditions Window.

Reconciliation Charges

Enter one of the following:

0 - To prevent users applying reconciliation charges to the contract type.

1 - To allow users to apply reconciliation charges using contract billing.



Tip: Use reconciliation charges to credit, at the

end of the period, for excess invoiced copies.

Fixed Visit Charge

Enter one of the following:

- 0 - To prevent users applying fixed visit charges to this contract type.
- 1 - To allow users to apply fixed visit charges, using contract conditions.

Copies In Rental

Enter one of the following:

- 0 - To include no copies in the rental charge.
- 1 - To include a specified number of copies per month in the rental charge, using contract conditions to specify the number of copies.

Minimum Volume

Enter one of the following:

- 0 - To prevent users applying the minimum copy volumes to this contract type.
- 1 - To allow users to apply minimum copy volumes using contract conditions.

Copy Charges 1 And 2

Enter one of the following:

- 0 - To prevent users applying copy charge bands to this contract type.
- 1 - To allow users to apply copy charge bands using contract conditions.

Pre-Billing Value

Enter one of the following:

- 0 - To prevent users applying a predetermined value to this contract type.
- 1 - To allow users to apply a predetermined value using contract conditions.

Pre-Billing Volume

Enter one of the following:

- 0 - To prevent users applying a predetermined volume to this contract type.
- 1 - To allow users to apply a predetermined volume using contract conditions.

Free Copies

Enter one of the following:

- 0 - Not to include the number of free copies on each monthly billing.
- 1 - To allow the number of free copies, specified in the contract conditions, on each monthly billing.

Free Visits

For future development.



Select **F8=Update** to save any changes.

Scheduled Visit Profile Maintenance

1... 3/WOC **2...**

Use this option to maintain the schedule of planned maintenance visits, using a series of schedule visit profiles (SVP).

Concepts

A scheduled visit profile defines the number, type and frequency of scheduled maintenance visits. Each visit has an associated job category, to indicate the kind of work to do, and the scheduled period.

Once set up, you can link a visit profile to a model, a model group, or an individual contract. This defines the schedule of visits for that model, model group or contract.

Implications

Although you do not need to define schedule visit profiles, you can use them to save time within Contracts Maintenance. When you define the service visit schedule for the equipment on the contract, the visit profiles generate the schedule automatically, so you do not have to enter it manually.

Workshop Management holds the scheduled visit profile on the Codes/Parameter file under parameter type VSTP.

Scheduled Visit Profile Maintenance Selection Screen



To display this screen, select the Scheduled Visit Profile (Maintenance) option.

Use this screen to select the Scheduled Visit Profile (SVP) you want to maintain or define.

SS036	Demonstration Company CENTRAL BRANCH	USER BRERETM	18/11/93 16:04:04
-------	---	--------------	----------------------

Scheduled Visit Profile Maint.

Enter profile to be maintained..?. 4PA

F3=Exit F4=Prompt

Fields:

Enter Profile To Be Maintained

Enter a new scheduled visit profile to define, or select an existing SVP to maintain.



To display the Scheduled Visit Profile Maintenance Detail Screen, press **Enter**.

Scheduled Visit Profile Maintenance Detail Screen



To display this screen, select, or enter, the profile you want to maintain, or define.

Use this screen to enter the details for the scheduled visits.

SS036	Demonstration Company CENTRAL BRANCH	USER BRERETM	18/11/93 16:04:20
Scheduled Visit Profile Maint.			
Profile: 4PA 4 visits per annum			
Relative Period	Job Category.....	Est. Hours	
1	PSV Planned service visit	1:00	
3	PSV Planned service visit	1:00	
6	PSV Planned service visit	1:00	
9	CAL calibration	1:30	
12	*RP	0:00	
0		0:00	
0		0:00	
0		0:00	
0		0:00	
0		0:00	
0		0:00	
0		0:00	
0		0:00	
0		0:00	+
F3=Exit F4=Prompt F7=Resequence F8=Update F11=Delete F12=Previous			

Fields:

Profile

Enter a description, of up to 30 alphanumeric, for the visit profile.

Relative Period

Enter the number of periods, after the contract start period, for which you want to generate a scheduled service visit.

Enter 0 if the first visit is in the contract's start period.

The Relative Period is the service period relative to the period of the contract start date. For example, if you require a profile for three visits per year, use monthly service periods, and define the relative periods as 02, 06 and 10. Then for a contract which starts in July 1998 (period 07/98), Workshop Management generates a schedule of three visits, in periods 09/98, 01/99 and 05/99.

Job Category

Enter the type of job for the planned maintenance visit.

If you want to generate the same pattern of visits year after year, you do not have to enter these repeated visits. Enter the special job category of *RP to make Workshop Management generate the visit schedule as far ahead as the contract end date, or the Number Of Service Periods To Be Loaded (specified on the company profile), whichever is the sooner.



Note: Load PM Jobs loads any job category found here, not just a job category code set up as PM.

Est Hours

Enter the estimated job duration in hhh:mm format.

The current system does not use this value.



*Note: If you enter a relative period, and *RP in the job category column, Workshop Management generates a repeat cycle of visits using the existing visit profile, starting from the relative period entered.*

Functions:

F7

Re-sequence. Use this function to list the relative periods in numerical order.



Select **F8=Update** to save details.

Recommended Service Visits Maintenance

1... **2...** 4/WOC

Use this option to maintain the scheduled visit profile which applies to each model group, by effectivity date.

Concepts

This option defines the number, type and frequency of scheduled maintenance visits normally associated with a model group, by linking the model group with a scheduled visit profile code. Because of the effective date you can link the same model group to different profiles for different time windows. For more information about scheduled visit profiles, see Scheduled Visit Profile Maintenance.

Implications

You access the profile code detail within Contract Maintenance, when you generate the service visit schedule for the equipment on the contract, where there is no visit profile defined for the contract or the model. If you have not defined the recommended visit profile for the model group, Workshop Management uses the Company Profile visit profile; if this is absent, Workshop Management does not generate a visit schedule.

Recommended Visits Maintenance Selection Screen



To display this screen, select the Recommended Service Visits (Maintenance) option.

Use this screen to select the Model Group for which you want to define a scheduled visit profile.

SS028	Demonstration Company CENTRAL BRANCH	USER BRERETM	11/03/94 2:15:14						
Recommended Visits Maintenance									
Division.....?.. <u>10</u>									
Model Group.....?.. <u>?</u>									
F3=Exit F4=Prompt		<table border="1"><tr><td colspan="2">Model Group Selection</td></tr><tr><td>1 Code</td><td>Desc.</td></tr><tr><td><u>1</u> 100</td><td>Analysers</td></tr></table>		Model Group Selection		1 Code	Desc.	<u>1</u> 100	Analysers
Model Group Selection									
1 Code	Desc.								
<u>1</u> 100	Analysers								
		F12=Previous							

Fields:

Division

Enter a division.

Model Group

Enter a model group.



Select a division and model group, and press **Enter** to display the Recommended Visits Maintenance Screen.

Recommended Visits Maintenance Screen



To display this screen, on the Recommended Visits Maintenance Selection Screen, enter a division and model group and press **Enter**.

Use this screen to select the SVP used to generate the recommended visits.

SS028	Demonstration Company CENTRAL BRANCH	USER BRERETM	11/03/94 2:16:48
Recommended Visits Maintenance			
Division.....	10 Environmental Monitoring		
Model Group.....	100 Analysers		
Effective date.....	0/00/00		
Visit Profile Code.?.	___		
	Date	Visit Profile Code	
-	1/01/94	4PA 4 Visits per annum	
-	1/01/93	4PA 4 Visits per annum	
4=Delete			
F3=Exit F4=Prompt F12=Previous			

Fields:

Effective Date

Enter the date this profile becomes effective.

Visit Profile Code

Enter a Scheduled Visit Profile (SVP). Workshop Management uses the following hierarchy to generate scheduled service visits:

1. Use the SVP on the Contract Header.
2. If none, use the Model file SVP.
3. If none, use the Model Group file SVP.
4. If none, use the Company Profile SVP.
5. If none, generate no visits.

Select 8 on the Contract Equipment Maintenance Detail Screen to generate visits using the first SVP found.

Select Option

Enter 4 to delete the Visit Profile Code.



Select **F3=Exit** to return to the menu.

Contract Rates Maintenance

5/WOC

Use this option to maintain the term contract rates for each model group, sub-group, model and contract type combination, by effectivity date and currency.

You use this option during set-up, and whenever you want to amend, delete or add to the contract rates for a model group, sub-group, model, contract type or effective date.

Concepts

Term processing use contract rates to calculate the price for each piece of equipment on a contract. For each contract type and contract term, you can define the rates for each model group, sub-group or model. You can then derive the rates for any given model on any given type of contract.

Contract rates are of three types:

- A visit charge, which is the price charged for each scheduled maintenance visit
- A rental charge - the price charged for the equipment rental for the term
- A service charge - the price charged for the equipment's fixed service, for the term.

Any of these rates can be zero. The contract charge for a piece of equipment can comprise one or more of these rates.

Workshop Management stores contract rates by effectivity dates; so you can have different rates for different time windows.

Workshop Management also stores contract rates for different currencies.

Implications

You access contract rates data by contract maintenance when you set up the conditions for the contract equipment.

If contract rates data is completely absent, in the conditions window, you must enter a special price, or zero, for the contract line.



Note: When using monthly rather than term pricing, you cannot use these contract prices; you must set the rate per month within the contract.

Contract Rates Maintenance Selection Screen



To display this screen, select the Contract Rates (Maintenance) option.

Use this screen to select the Division, Model Group, Term and Currency Code combination for which to want to set up contract rates.

```

SS030          Z1 - GB Demonstration Company   USER GBJBATD0   24/09/97
               "BRUM" TRAINING & SERVICE BRANCH 11:40:55
Contract Rates Maintenance

Division.....?.. HW
Model Group.....?.. A-C
Term.....?.. 12
Currency Code.....?.. GBP

Based on :-

Division.....?.. 
Model Group.....?.. 
Term.....?.. 
Currency Code.....?.. 

F3=Exit F4=Prompt

14-27 SA MW KS CL IM DM II EDN400A KB PKH317S1
  
```

Fields:

Division

Enter a division.

Model Group

Enter a model group.

You can attach contract rates to each model group, with effective dates. Contract Pricing uses the current rate to price equipment for this model group.

Term

Enter the billing term, in calendar months; the default value is 12, and the range is 1 to 120.

This defines the length of the price protection period, and the number of periods for which contract pricing generates pending invoice, and actual invoice, records.

The contract rate for the contract header is for the same term as that entered in the contract billing parameters.

Currency Code

Enter a currency.

Based On Fields

To create a contract rate based on an existing rate, enter the existing details.

Workshop Management sets up the structure of the new rate based on the existing one.



Tip: You cannot amend the actual detail lines. To change the detail lines, you must delete them and enter new ones.



Complete the fields and press **Enter**, to display the Contract Rates Maintenance Screen.

Contract Rates Maintenance Screen



To display this screen, on the Contract Rates Maintenance Selection Screen, select a division and model group and press **Enter**.

Use this screen to enter the charges for each model or model sub-group in the selected model group.

SS030	Z1 - GB Demonstration Company		USER GBJBATD0	24/09/97
	"BRAUM" TRAINING & SERVICE BRANCH			11:41:13
Contract Rates Maintenance				
Division.....	HV	Heat and Ventilate		
Model Group.....	A-C	Air-Conditioning		
Term.....	12			
Model Sub-group...?..				
Model.....?..				
Effective Date.....	0/00/00	<----- Changes ----->		
Cover Type.....?..		Visit	Rental	Service
Currency Code.....	GBP			
MG MSG Model	Typ	Eff.Date		
- A-C	B01	1/11/95		480.00
- A-C	B02	1/11/95		1120.00
- A-C	B05	31/12/96		600.00
- A-C	B05	1/12/96	40.00	1900.00
- A-C	B05	1/11/95	35.00	1850.00
- A-C	B05	1/11/95	30.00	1800.00
- A-C	B05	1/06/94	32.00	1400.00
- A-C	B05	1/01/93	20.00	1200.00
- A-C	B10	1/11/95	36.00	480.00
				1344. +
4=Delete				
F3=Exit F4=Prompt F12=Previous				
8-27 SF MW KS CL IM DM II EDN400A KB PKH317S1				

Fields:

Model Sub-Group

Select a model sub-group.

If entered, the contract rates apply to all models belonging to this model sub-group, within the model group and division.

Model

Select a model.

You link a model to model sub-group, model group and division. If you set up a contract rate record at model level, at contract pricing, this rate overrides any set up at model sub-group or model group level.

Effective Date

Enter the date when the contract rate becomes active, in DDMMYY format.

This supersedes all existing contract rates, for the model group, model sub-group and model combination, with earlier effective dates.

Contract Type

Enter a contract type. Contract Pricing applies the specified service, rental or visit charges to this contract type, for the product combination selected.

Charges



Tip: Any charges set up in the Contract Conditions Window override these charges.



Note: Workshop Management calculates the price for a contract line by multiplying the charge per visit by the number of visits in the term and adding the rental and service charges for the term.

Visit

Enter the charge per visit made during the contract, if you set term processing on the System Parameter Maintenance Screen 1.

Rental

Enter the rental charged for the contract term, if you set term processing on the System Parameters Maintenance Screen 1.

Service

Enter the charge for a fixed service for the contract term, if you set term processing on the System Parameter Maintenance Screen 1.

Untitled

Selection. Enter 4 to delete the contract rates for this model group, model sub-group and model combination.



Press **Enter** to update.

Cover Type Maintenance



6/WOC

Use this option to define all the required cover types.

A cover type defines the charge conditions under which jobs are priced, and to which you can attach a service visit profile.



*Note: You must define at least one cover type:
NO, for no contract.

Cover Type Maintenance Selection Screen



Select Cover Type Maintenance.

Use this screen to select or define the cover type you want to maintain.

Fields:

Cover Type

Either select an existing cover type, or enter a new cover type using up to 3 alphanumeric characters.



Press **Enter** to display the Cover Type Maintenance Screen.

Cover Type Maintenance Screen



To display this screen press **Enter** on the Cover Type Maintenance Selection Screen.

Use this screen to specify the service visits profile for this cover type.

W0050	Z1 - GB Demonstration Company	USER GBJBANB1	22/04/98
	CENTRAL WORKSHOP		16:19:53
Cover Type Maintenance		UPDATE	
Cover Type.....	B01	<u>S&R Adv: Basic cover</u>	
Service Visit Profile...?	<u>001</u>	New 1	
F3=Exit F8=Update F11=Delete F12=Previous			

Fields:

Unnamed (Cover Type Description)

Enter the description of a new cover type.

Service Visit Profile

Enter a service visit profile to use for this cover type.



Select **F8=Update** to save the cover type and details.

Contracts Enquiry

1... **11/WOC** **2...**

Use this enquiry to display the details of service contracts, and quotations for contracts.

Description

To access a contract for enquiry, you can use one of the following:

- Contract number and, optionally, contract type.
- Customer account and, optionally, address code.
- Alpha search.

Depending on the entries, Workshop Management displays a list of customer sites or contracts matching the selection parameters.

When you select a contract, you can use the details displayed to enquire on the header, the equipment covered and any override details affecting service, invoicing, conditions and visits scheduled.

Contract Enquiry Selection Screen



Select the Contracts Enquiry option to display the Contract Enquiry Selection Screen.

Use this screen to specify for which contract you want to display the details.

SS524	Z1 - GB DEMO. SERVICE COMPANY	USER GBJBATD0	25/09/97
	"BAUM" TRAINING & SERVICE BRANCH		10:44:59
Contract Enquiry			
Contract Number..... _____			
Contract Type.....?.. _____			
Account Number...?.. G001 _____			
Account Address..... 000 _____			
F3=Exit F4=Prompt			
6-24 SA MW KS CL IM DM II EDN400A KB PKH317S1			

Fields:

Contract Number

Enter a contract number.

Contract Type

Enter the contract type. You must also enter a contract number.

If more than one contract has this contract number and, optionally, contract type, Workshop Management displays a list of contracts in contract type and start date sequence.

Account Number

Select a customer account.

If you only enter the account number, Workshop Management displays a list of all address codes for this account.

Account Address Code

Select an address. You must also enter a customer account.

Workshop Management displays a list of all contracts, in contract number, contract type and start date sequence.



Select a contract to display the Contract Header Enquiry Detail Screen.

Contract Header Enquiry Detail Screen



To display this screen, select a contract on the Contract Enquiry Selection Screen.

W0535	Z1 - GB Demonstration Company	USER GBJBANB1	22/04/98
	CENTRAL WORKSHOP		16:14:20
Contract Header Enquiry			
Account Number.....	PLCUS001	000 PL Testing Company	
Contract Number.....	NIC001	Alt. Cont. No.	Version.
Contract Type.....	B01	S&R Adv: Basic cover	Status. Pending start date
Contract Start Date..	1/05/98	End Date. 30/04/99	Invoice Start. 0/00/00
Tot. Contract value..			
Duration.....	12	Mantle Code.....	
Customer Order Ref 1..		Order Ref Date..	0/00/00
Customer Contact.....	MARTIN JONES	Telephone No....	222690000
Renew Contract (1/0)..	1	Region....	CT Central
Non-posting Invoices..	0	Header level pricing (1/0)..	0
Salesman Code.....		Invoice Summ/Det Form (1/0)...	0
Invoice Destination...		Direct Debit (1/0).....	0
Contract Inv. Bill to.		Header currency (1/0).....	1
Job Invoice Bill to...			
F3=Exit	F8=Detail	F12=Previous	F14=Service
F18=Conditions enq.			F21=Text
			F16=Billing enquiry
			F23=Invoice enquiry

The information displayed on this screen includes:

- Contract, alternative contract and version numbers.
- Contract type and status.
- Contract start, end dates and duration.
- Invoice details, including start date and destination.
- Contract value and header price.
- Contract mantle code.
- Customer order reference and date.
- Customer contact and telephone numbers.
- Whether you can renew the contract.
- Salesman and region codes.
- Whether you allow estimates.
- Whether the contract is a pooled contract.

For more details of the fields, see the Contract Maintenance Section.

Functions:

F14

Service. Use this function to display the Service Parameters Enquiry Window.

F16

Billing Enquiry. Use this function to display the Billing Parameters Enquiry Window.

F18

Conditions Enq. Use this function to display the Contract Conditions Enquiry Window.

F21

Text. Use this window to display the text for this contract.

F23

Invoice Enquiry. Use this function to display the invoice details for this contract.



Select **F8=Detail** to display the detail screen.

Service Parameters Window (F14)



To display this window, on the Contract Header Enquiry Details Screen, select **F14=Service**.

W0535	Z1 - GB Demonstration Company	USER GBJBANB1	22/04/98
	CENTRAL WORKSHOP		16:14:20
Contract Header Enquiry			
Account Number.....	PLCUS001	000	PL Testing Company
Contract Number.....	NIC001	Alt. Cont. No.	Version.
Contract Type.....	B01	S&R Adv: Basic cover	Status. Pending start date
Contract Start Date..	1/05/98	End Date. 30/04/99	Invoice Start. 0/00/00
Tot. Contract value..			
Duration.....	12	Mantle Code.....	
Customer Order Ref 1..		Order Ref Date..	0/00/00
Customer Contact.....	MARTIN JONES	Telephone No....	222690000
Renew Contract (1/0)..	1	Region....	CT Central
Service Parameters			
Response hours..... 8:00			
Schedule visit profile..			
Allow service cover when contract pending (1/0). 1			
Use start date rates.... 1 Or,Until.... 0/00/00			
Global Price Code.....			
Bill to...			
F12=Previous			
F18=Conditions enq.		F21=Text	F23=Invoice enquiry

The information displayed on this window includes:

- Response Hours.
- Scheduled Visit Profile.
- Whether you use Scheduled Visit Override when you renew the contract.
- Whether you allow service cover on pending contract.
- Which labour and price rates Workshop Management uses to price the contract.
- Whether you use contract start date rates.
- Global Price Update Code.

For more details of the fields, see the Contract Maintenance Section.



Select **F12=Previous** to return to the previous screen.

Billing Parameters Window (F16)



To display this window, on the Contract Header Enquiry Detail Screen, select **F16=Billing Enquiry**.

```

SS535          Z1 - GB DEMO. SERVICE COMPANY      USER GJBATD0  25/09/97
               "BAUM" TRAINING & SERVICE BRANCH    11:01:16
Contract Header Enquiry

Account Number..... GC01          000 Reeves Chemist's
Contract Number..... 0000101      Alt. Cont. No.      Version.
Contract Type..... B01 S&R Adv: Basic cover  Status. Pending start date
Contract Start Date.. 24/09/97      End Date. 23/09/98  Invoice Start. 0/00/00
Tot. Contract value..              Header price...
Duration..... 12                  Mantle Code.....

Billing Parameters
-----
Billing type:      Term  Freq  Adv/Visit/Ann  Next pricing cycle
                  (mths) (mths) (0/1/2)      From      To
Fixed Service Chrg.: 12    3    0 (0/1/2)      24/09/97  23/09/98
Rental Charge.....: 12    3    0 (0/1/2)      24/09/97  23/09/98

F12=Previous
F3=Exit  F8=Detail  F12=Previous  F14=Service  F16=Billing enquiry
F18=Conditions enq.  F21=Text      F23=Invoice enquiry

1-1  SA  MW  KS  CL  IM  DM  II  EDN400A  KB  PKH317S1
  
```

The information displayed on this window includes:

- Term the charge or rental is fixed for.
- How often and when you send an invoice.
- Dates of the next pricing cycle.
- Interim and reconciliation charge details.

For more details of the fields, see the Contract Maintenance Section.



Note: Only the billing parameters selected for the contract type display.



Select **F12=Previous** to return to the previous screen.

Contract Conditions Window (F18)



To display this window, select **F18=Conditions Enq**, on the Contract Header Enquiry Detail Screen.

W0535 Z1 - UK Demo		Contract Conditions	
CENTRA		Cover type... *N0 Eff.Date: 1/01/98 GBP	
Contract Header Enquiry			
Account Number..... C01		Minimum Volume.....: 5000	
Contract Number..... LML000A			
Contract Type..... MET Meter			
Contract Start Date.. 1/01/98			
Tot. Contract value..			
Duration..... 12			
Customer Order Ref 1..			
Customer Contact.....			
Renew Contract (1/0).. 1			
Non-posting Invoices.. 0			
Estimates Allowed(1/0) 1			
Pool Contract (1/0)... 0 Title			
Salesman Code.....			
Invoice Destination...			
Contract Inv. Bill to..			
Job Invoice Bill to...			
F3=Exit F8=Detail F12=Previo			
F18=Conditions enq. F20=Statis		F12=Previous	

The information displayed on this window includes:

- Cover type.
- Effective date.
- Currency.
- Fixed service, visit, or rental charge.
- Pre billing value or volume.
- Minimum volume.
- Band prices.

For more details of the fields, see the Contract Maintenance Section.



Tip: Page up and down to display differently dated contract conditions.



Note: Only the contract conditions selected for the contract type display.



Select **F12=Previous** to return to the previous screen.

Contract Equipment Enquiry Detail Screen (F8)



To display this screen, on the Contract Header Enquiry Detail Screen, select **F8=Detail**.

This screen displays, for each model on the contract, the location, serial number, status, inclusion and removal date, and response time.

W0525	Z1 - GB Demonstration Company	USER GBJBANB1	22/04/98
	CENTRAL WORKSHOP		16:17:34
Contract Equipment Enquiry			
Account Number..... PLCUS001		Contract Start Date.. NIC001 B01	1/05/98
000 PL Testing Company			
Inst.Adr	Loc Model	Serial	Stat Inc. Dt. Remov dt R.Hrs Vst
_ PLCUS001	000 PROJECTOR001	S5022	Pen 1/05/98 0/00/00 0
2=Conditions 3=Peripherals 4=Inv hist. 5=Meter hist. 6=Stats. 7=Visits F3=Exit F12=Previous F13=Fold/Truncate F21=Text			

Fields:

Untitled

Selection field. Enter one of the following:

- 2 - To display the Contract Conditions Window.
- 3 - To display the Peripherals Screen; from which you can access the Peripheral Conditions Screen.
- 4 - To display the invoice history.
- 5 - To display the meter history.
- 6 - To display the meter reading statistics.
- 7 - To display the scheduled visits.

Functions:

F13

Fold/Truncate. Use this function to toggle between the full and partial descriptions.

F21

Text. Use this function to display the text associated with the contract.



Select **F3=Exit** to leave the enquiry.

Contract Type Enquiry



12/WOC

Use this option to enquire on the details of service contract types.

Workshop Management uses the data associated with a contract type to provide:

- Default data (contract duration, invoice schedule, invoice at start date flag) for each contract when you create it.
- Call escalation monitoring, using the guaranteed response time to calculate the target arrival time for the engineer.

Contract Type Enquiry Selection Screen



Select the Contract Type (Enquiry) option to display the Contract Type Enquiry Selection Screen.

Use this screen to select the contract type you want to display the details for.

SS532	Demonstration Company CENTRAL BRANCH	USER BRERETM	24/11/93 16:19:23
Contract Type Enquiry			
Contract Type..... <u>B01</u>			
F3=Exit F4=Prompt			

Fields:

Contract Type

Select a contract type.



Select a contract type and press **Enter** to display the Contract Type Enquiry Detail Screen.

Contract Type Enquiry Detail Screen



To display this screen, on the Contract Type Enquiry Selection Screen, select a contract type and press **Enter**.

SS532	Demonstration Company CENTRAL BRANCH	USER BRERETM	24/11/93 16:19:41
Contract Type Enquiry			
Contract Type..... B01 Basic cover			
Automatically Generate Service Schedule	1	(1=yes 0=no)	
Quotation required on renewal	0	(1=yes 0=no)	
Use Contract Start Date Rates	0	(1=yes 0=no)	
Response Hours Guarantee: (hhh:mm)	8:00		
Contract Duration (months)			
Termination notice in days			
Invoice Schedule.....	0	(0=Advance, 1=Visit, 2=Arrears)	
Contract Type Includes the following parameters (1=yes 0=no)			
Fixed Service Charge.....	1	Interim Charges.....	0
Fixed Rental Charge.....	1	Reconciliation Charges.	0
Fixed Visit Charge.....	0	Copies Incl. Rental....	0
Minimum Volume.....	0	Copy Charges 1.....	0
Pre Billing Value.....	0	Copy Charges 2.....	0
Pre Billing Volume.....	0	Free Copies.....	0
		Free Visits.....	0
F3=Exit F12=Previous			

The information displayed on this screen includes:

- Contract type.
- Whether a quotation is required.
- Labour rates and parts used in job pricing.
- Guaranteed response time.
- Contract duration.
- Termination Notice.
- Invoice schedule.
- Contract charges.
- Copies or vends minimum volume.
- Number of copies included free.

For more information about these fields, see the Contract Type Maintenance Section.



Select **F3=Exit** to return to the menu.

Schedule Visit Profile Enquiry



13/WOC

Use this enquiry to display the details of scheduled service visit profiles.

A scheduled visit profile defines the number, type and frequency of scheduled maintenance visits. Each visit has an associated job category, to indicate the kind of work to do, and the scheduled period.

Scheduled Visit Profile Enquiry Selection Screen



Select the Schedule Visit Profile Enquiry option to display the Scheduled Visit Profile Enquiry Selection Screen.

Use this screen to select the Schedule Visit Profile for which you want to see the details.

SS036	Demonstration Company CENTRAL BRANCH	USER BRERETM	24/11/93 16:21:48
-------	---	--------------	----------------------

Scheduled Visit Profile Enq'y

Enter profile to enquire on.....?. ?

F3=Exit F4=Prompt

Fields:

Enter Profile To Enquire On

Enter a scheduled visit profile.



Select a profile and press **Enter** to display the Scheduled Visit Profile Enquiry Detail Screen.

Scheduled Visit Profile Enquiry Detail Screen



To display this screen, on the Scheduled Visit Profile Enquiry Selection Screen, select a profile, and press **Enter**.

SS036	Demonstration Company CENTRAL BRANCH	USER BRERETM	24/11/93 16:20:51
Scheduled Visit Profile Enq'y			
Profile: 4PA 4 visits per annum			
Relative Period	Job Category.....	Est. Hours	
1	PSV Planned service visit	1:00	
3	PSV Planned service visit	1:00	
6	PSV Planned service visit	1:00	
9	CAL calibration	1:30	
12	*RP	0:00	
F3=Exit		F12=Previous	

The information displayed on this screen includes:

- Relative Period - this is how many periods from this date.
- Job Category.
- Estimated hours for the job.

For more information about these fields, see the Scheduled Visit Profile Maintenance section.



Select **F3=Exit** to return to the menu.

Recommended Service Visits Enquiry



14/WOC

Use this enquiry to display the details of the recommended visits for each model groups

Recommended Visits Enquiry Selection Screen



Select the Recommended Service Visits Enquiry option to display the Recommended Visits Enquiry Selection Screen.

Use this screen to select the model group for which you want to display the details.

SS528	Demonstration Company	USER BRERETM	24/11/93
	CENTRAL BRANCH		17:37:13
Recommended Visits Enquiry			
Division.....?... 10			
Model Group.....?... 100			
F3=Exit F4=Prompt			

Fields:

Division

Enter a division code.

Model Group

Enter a model group which exists within the selected division.



Select a division and model group, then press **Enter** to display the Recommended Service Visits Enquiry Detail Screen.

Recommended Visits Enquiry Detail Screen



To display this screen, on the Recommended Visits Enquiry Selection Screen, select a division and model group, then press **Enter**.

SS528	Demonstration Company	USER BRERETM	24/11/93
	CENTRAL BRANCH		17:18:40
Recommended Visits Enquiry			
Division.....	10	Environmental Monitoring	
Model Group.....	100	Analysers	
Date	Visit Profile Code..		
1/01/94	4PA 4 Visits per annum		
1/01/93	2PA 2 Visits per annum		
F3=Exit F12=Previous			

The information displayed on this screen includes:

- Effective date.
- Scheduled visit profile.

For more information on these fields, see the Recommended Visits Maintenance Section.



Select **F3=Exit** to leave the enquiry.

Contract Rates Enquiry



15/WOC

Use this enquiry to display the details of contract rates for a model group and term, by currency.

Contract Rates Enquiry Selection Screen



Select the Contract Rates Enquiry option to display the Contract Rates Enquiry Selection Screen.

Use this screen to select the division, model group, term and currency combination for which you want to view the rates details.

SS030	Z1 - C&T TEST COMPANY	USER GBJBAJKG	28/02/96
	BIRMINGHAM BRANCH		16:34:58
Contract Rates Enquiry			
Division.....?	D1		
Model Group.....?	MG1		
Term.....?	12		
Currency Code.....?	GBP		
F3=Exit F4=Prompt			
05-27	SE	MW	KS IM II KENB20A PED129S1

Fields:

Division

Select a division.

Model Group

Select a model group.

Billing Term

Enter the billing term, in calendar months.

Currency Code

Enter the currency for the contract.



Enter the details on the Contract Rates Enquiry Selection Screen, and press **Enter** to display the Contract Rates Enquiry Detail Screen.

Contract Rates Enquiry Detail Screen



To display this screen, enter some selection details on the Contract Rates Enquiry Selection Screen, and press **Enter**.

SS030	Z1 - C&T	TEST COMPANY	USER GBJBAJKG	28/02/96
		BIRMINGHAM BRANCH		16:37:10
Contract Rates Enquiry				
Division.....	D1	Division 1		
Model Group.....	MG1	Model Group 1		
Term.....	12			
Currency Code.....	GBP		<..... Charges>	
MG MSG Model	Typ	Eff.Date	Visit	Rental
MG1 MSG MODEL1	B10	31/01/96	50.00	3000.00
				2000.00
F3=Exit F12=Previous				
01-02	82	MW	KS	IM II KENB20A PED129S1

The information displayed on this screen includes:

- Division.
- Model group.
- Model Sub-group.
- Model.
- Contract Type.
- Effective Date.
- Contract Charges.



Select **F3=Exit** to leave the enquiry.

Cover Type Enquiry

1... 16/WOC **2...**

A cover type defines the charge conditions under which jobs are priced. You can attach a service visit profile to a cover type.

Use this option to enquire on cover types that already exist on the system.

Cover Type Enquiry Selection Screen



Select Cover Type Enquiry.

Use this screen to select the cover type for which you want to see the details.

Fields:

Cover Type

Select an existing cover type.



Press **Enter** to display the Cover Type Enquiry Screen.

Cover Type Enquiry Screen



To display this screen, select a cover type and press **Enter** on the Cover Type Enquiry Selection Screen.

```

W0050                Z1 - GB Demonstration Company    USER GBJBANB1    22/04/98
                   CENTRAL WORKSHOP                  16:22:27

Cover Type Enquiry

Cover Type..... ALL    all conditions

Service Visit Profile...? 001    New 1

```

This screen displays the cover type description and the service visit profile assigned to this cover type.



Select **F3=Exit** to leave the enquiry.

Contract Quotation Print



20/WOC

Use this option to print quotations for all contracts which have a status of Quote.

Use this option whenever you need to send out contract quotations.

When you select this option from the menu, you submit a batch job. This generates a printer file of quotations.

If there is an account address at the top of the report it is the contract invoice Bill To account.

After you have printed a quotation, Workshop Management flags it so it does not print again, when you next run this option.



To run this batch job, select the Contract Quotation Print option, then select **F8=Confirm Submit**.

Contract Renewal



21/WOC

This option renews all contracts due to expire, and flagged as renewable. You should use this option on a regular basis (for example, monthly).



Note: You must have exclusive use of the company to do this.

Which Contracts Does Workshop Management Renew?

Workshop Management only renews contracts if the Renew Contract field on the contract header is set to Yes.

The contracts must be Active; renewal fails if the contracts are Pending or Expired.

The contract termination date must be less than or equal to the date selected on the Contract Renewal Selection Screen.

How Does Workshop Management Create The Renewed Contract?

The new contract has a start date one day after the termination date of the original, and an end date of the start date plus the contract duration for the contract type.

The contract type remains the same.

The contract number depends on the setting of the Company Profile field New Contract No At Renewal. If you set this to No, then Workshop Management retains the same number; if you set it to Yes, Workshop Management generates a new number, from the sequence on the company profile.

The status of the new contract is Pending Start Date, unless the contract type indicates that you require a quotation on renewal, in which case Workshop Management sets the status to Quotation. In the latter case, Workshop Management prints a quotation in the next run of the Print Contract Quotations option, and you can then change the quotation to a true contract through Contract Maintenance.

The renewal procedure also renews the service schedule for each piece of equipment on the contract. This depends on the following:

- If the existing schedule has the Use These Visits On Renewal field set on, the new schedule mirrors the existing one.
- If the existing contract header has a non-standard visit profile, and is flagged to say Use The Non-Standard Profile On Renewal, Workshop Management generates the new schedule using the non-standard profile (and attaches this profile to the new contract).
- If the existing contract header has a standard visit profile held against it, Workshop Management uses this to generate the new schedule.
- If the model number or group for the piece of equipment has a standard visit profile, Workshop Management uses this to generate the new schedule.

- If the company profile has a standard visit profile, Workshop Management uses this to generate the new schedule. If not, then this procedure cannot generate a new schedule.

What Should You Do After Renewal?

After you renew the contracts, check the equipment contract conditions (option 2 from the Contract Equipment Maintenance Screen). It is these conditions which Workshop Management applies when you price the contract, not the conditions at header level.

Contract Renewal Selection Screen



Select the Contract Renewal option to display the Contract Renewal Selection Screen.

Use this screen to select the contracts you want to renew, by entering an expiry date.

SS480P	Demonstration Company	USER BRERETM	24/11/93
	CENTRAL BRANCH		16:27:58
Contract Renewal			
Renew those which will expire on or before DDMMYY: <u>24/11/93</u>			
F3=Exit F8=Submit job			

Fields:

Expiry Date

Enter a date in the format DDMMYY.



Select **F8=Submit** to submit the job for processing.

Contract Updating



22/WOC

Use this option to perform various housekeeping procedures on the contracts for a branch.

The Day End Routines option also includes these procedures, when they apply to the whole company.



Note: You must have exclusive use of the company to do this.

Description

When you select this option, a batch job does the following for contracts owned by the requesting service branch:

- Identifies any active contracts which have reached their termination date and sets their status to Expired. It also updates the installation to show that the contract no longer covers the equipment.
- Sets any Pending Start contracts, which have reached their start date, to active. It also updates the installation to show that the contract now covers the equipment.
- Includes pieces of equipment supposed to become active, but already covered by a different contract, on an error report.
- Selects contracts with a termination date before the end of their current term for credit processing. The contracts appear on the report of contracts selected for credit.



Tip: Because this processing is part of the Day End Routines option, only run this option if there is a requirement to update a contract status during the day.



To run this batch job, select the Contract Updating option, then select **F8=Confirm Submit**.

Request Quotes From Contract



23/WOC

Use this option to create contract quotations from existing service contracts.

Use this option if your customer already has a contract, and wants a quote for a different type of contract to cover the same equipment.

You can generate the new quotation immediately, or store the request and generate the new quotation later, by running the Generate Deferred Request Quotes From Contracts option.

Request Quotes From Contract Detail Screen



Select Request Quotes From Contract option to display the Request Quotes From Contract Detail Screen.

Use this screen to select the contract you want to create from the specified contract details.

SS930	Demonstration Company CENTRAL BRANCH	USER BRERETM	24/11/93 16:33:04
-------	---	--------------	----------------------

Request Quote from Contract

New contract..... 9400115 ...?. B01 060494

Based-on contract..... 0000115 ...?. B01 060493

Service visits - copy(1)/generate(2)/none(3) 2

Service visit profile...?. 4PA

F3=Exit F4=Prompt F13=Process later F22=Process now

Fields:

New Contract

Enter a new contract number, of up to seven alphanumeric characters. The number must not already exist.

Enter a contract type. If you are basing this new contract on an existing one, then both must have the same contract type.

Enter the date (DDMMYY) on which the new contract starts.

Based-On Contract

To base the new contract on an existing one, enter the existing contract.

Enter the contract type of the existing contract. This must be the same as the contract type of the new contract.

Enter the start date (DDMMYY) of the based-on contract.

Service Visits

Enter one of the following:

1 - Copy. To copy the existing, remaining, or outstanding visits for each piece of equipment on the old contract to the new; leave Service Visit Profile blank.

2 - Generate. To generate new visits for each piece of equipment on the new contract, for the contract's duration. This may be a more extensive series of visits than that set up by 1 - Copy; you must enter a Service Visit Profile.

3 - None. To set up no visits; leave Service Visit Profile blank.

Service Visit Profile

Enter a service visit profile. Workshop Management uses the profile to generate scheduled visits for each piece of equipment on the new contract.

Functions:

F13

Process Later. Use this function to generate the new quotes at a later time by running the batch job Generate Deferred Request Quotes From Contract.

F22

Process Now. Use this function to generate the new quote now.



Select **F3=Exit**, after selecting either
F13=Process Later or **F22=Process Now**.

Generate Deferred Request Quotes From Contracts

1... 24/WOC
2...

Use this option to generate quotations, from existing service contracts, using stored requests.

Description

This submits a batch job to perform the processing. This takes outstanding requests for Quotes From Contracts (made through the Request Quotes From Contracts option) and generates contract quotation records. It copies the contract header and contract equipment records from the Based-On contract to the new contract, and either copies or generates the service schedule records for the new contract.



To run this batch job, select the Generate Deferred Request Quotes From Contracts option, then select **F8=Confirm Submit**.

Global Price Update



25/WOC

Use this option to apply percentage price increases, or decreases, to selected groups of product families, customers or contracts.

Description

You can group contracts by price code and by mantle code or both, so you can apply selective price changes.

You can enter one or more criteria to select only those contract records to which you want to apply the price change. Workshop Management then generates a new dated price list for those contracts.

By default, you run the price change program, as a model; that is, it only updates a work file and produces a report showing the current and new prices. Once you confirm the model as correct, you can run the pricing program to update the files directly.

Implications

You price protect contracts by their Term. The application of a global price change may generate a new dated price list for a contract. This does not become effective until the end of the Term, even if the price list has an effective date prior to the end of the Term.



Note: There is no provision for updating contract visit charges. You can only update service, rental and copy charges.

Global Price Update Detail Screen



Select the Global Price Update option to display the Global Price Update Detail Screen.

Use this screen to specify the details for the pricing update.



Note: You must complete at least one of the seven selection fields (three contract selections and four price change selections).

SS905P	Z1 - Demonstration Company WORKSHOP BRANCH	USER GBJBATD0	11/12/97 14:17:36
Global Price Update			
Effective from date..... 0/00/00			
Contract selection: Mantle code...?.. ____			
Price code...?.. ____			
Contract type...?.. ____			
Currency code...?.. GBP			
Price change selection:			
Division.....?.. ____			
Model group...?.. ____			
Model sub-grp...?.. ____			
Model.....?.. ____			
Service change... ____ .00 %			
Rental change... ____ .00 %			
Price per copy... ____ .00 %			
Update conditions file..... 0 (1=Yes/0=No)			
F3=Exit F4=Prompt F8=Submit Job			
5-32 SR MW KS CL IM DM II STUD140 KB PKH318S1			

Fields:

Effective From Date

Enter the date (DDMMYY) on which the update comes into force.

Mantle Code

Select a mantle code.

Workshop Management checks the code against parameter type MANT on the Inventory Descriptions file. The mantle code determines which contracts Workshop Management selects for the price update, by matching the entered code with that set up on the contract header.

Price Code

Select a price code. Code 00 is a system code, and not for general use.

Workshop Management validates the price code against parameter type GLPR on the Codes/Parameter file.

The price code determines which contracts Workshop Management selects for the price update. Workshop Management matches the entered code against the global price code set up on the Contract Header Conditions (Service Parameters) Window.

Contract Type

Select a contract type.

If you specify a contract type, it limits the price update selection to that type; if blank, it includes all contract types within the other selection criteria.

Currency Code.

Select a currency.

Division

Select a division.

If you specify a division, it limits the price update selection to that division; if blank, it includes all divisions within the other selection criteria.

Model Group

Select a model group.

If you specify a group, it limits the price update selection to that group; if blank, it includes all groups within the other selection criteria.

Model Sub-Grp

Select a model sub-group.

If you specify a sub-group, it limits the price update selection to that sub-group; if blank, it includes all sub-group within the other selection criteria.

Model

Select a model.

If you specify a model, it limits the price update selection to that model; if blank, it includes all models within the other selection criteria.

Service Charge

Enter a percentage in the range 0.01 to 999.99, positive or negative.

Rental Charge

Enter a percentage in the range 0.01 to 999.99, positive or negative.

Price Per Copy

Enter a percentage in the range 0.01 to 999.99, positive or negative.



Note: You must enter one of Service Charge, Rental Charge or Price Per Copy.

Update Contract Conditions

Enter one of the following:

0 - No. Not to update the contract conditions.

1 - Yes. To update the contract conditions, to take account of the percentage changes specified.



Select **F8=Submit Job** to submit the job for processing.

Copy Kit Batch Job



26/WOC

Use this option to report details of contracts based on copy volume, which expire when the customer has used an agreed volume of copies.

You base Copy Kit contracts on providing service and materials (for example, paper, toner and so on) for either a predefined period of time, or a predefined number of copies, whichever runs out first.

Description

This function is only available if you select copies on the contract type file a Copy Kit select flag displays on the contract header.

If you select copy kit, the Minimum Copies, entered in the conditions window for the contract, become the number of copies for the termination of the contract.

Submitting the Copy Kit Batch Job reads the contract file and the meterage file, and produces a report of contracts which have reached the number of copies for termination.

Implications

You can use the report to decide whether to cancel or renew the contract.

The contract end date is the normal termination date for the contract. The standard contract updating program handles contracts reaching this date and produces no report.

Contract Credit Selection

27/WOC

This option identifies any contracts which you have terminated prior to their contracted expiry date, and may therefore require a credit.

It also selects expired contracts which need a retrospective credit.

This presupposes that you have already used Contract Maintenance to reset the Contract End Date on the Header Screen, particularly if the contract is header priced. Alternatively, you can reset Remove Details on the equipment records if the contract is not header priced, and you only want to omit and credit certain machines.

Description

You must select contracts for credit before you can access Contract Credits Maintenance. See the Contract Credits Maintenance section of this product information.

The selection process does the following:

1. Selects records for both pending and actual invoices. Pending invoice records do not produce a credit, but Workshop Management recalculates the value to ensure you use the correct value when you produce the invoice.
2. Puts the selected records in a work file, together with the expected credit and re-invoice values. Workshop Management bases the records on the termination date plus the penalty days defaulted from the Termination Days on the contract type.
3. Produces a report of all the records in the work file, which require editing or acceptance. The section Contract Credit Maintenance provides details of the processing required after you have run the report, Contracts Awaiting Edit And Acceptance Of Credits/Re-Invoices.



Note: If there are pending invoice records on SSP44, but you do not want to recalculate the invoice, remove the equipment via Contract Maintenance. Generate and Print (Contract) Invoices clear the records from SSP44 on the removal date specified.



Note: Do not attempt to use contract credit functionality, as you do not need to credit an invoice amount.

Selection Of Contracts For Credit Screen



Select the Contract Credit Selection option to display the Selection Of Contracts For Credit Screen.

Use this screen to select the contracts for which you want to produce credits.

SS423P	Z1 - GB Demonstration Company	User GBJBABL	8/03/96
	"BRUM" TRAINING & SERVICE BRANCH		9:46:52
Selection of contracts for credit:			
Branch.....?..: <u>BT</u>		(*A for all)	
Contract number.....: _____		(Blank for all)	
Contract type.....?..: _____			
Contract date.....: <u>0/00/00</u>			
Invoice number.....: _____			
Contracts terminating on or before.....: <u>8/03/96</u>			
F3=Exit F4=Prompt			
06-47		MW	KS IM II KENB20A PED129S1

Fields:

Branch

Enter the branch. This defaults to the current branch. Enter *A to select all branches.



Note: If you only enter the branches and the termination date, Workshop Management selects all contracts terminating on or before this date.

Contract Number

Enter a contract number to select a specific contract for credit. You can enter pending, active, deleted and expired contracts which you have priced or invoiced or both. You must also enter the contract type and date.

Contract Type

Select a contract type.

Contract Date

Enter the contract start date.



Tip: If you are selecting an expired or deleted contract for credit, you only need to enter the number, type and date.

Invoice Number

Enter the invoice number, in the format Innnnnn, to select an invoice contract that requires credit.

Contracts Terminating On Or Before

Enter the contract termination date. This must be later than the default, which is the current date.



Press **Enter** to check the information, then select **F8=Submit Job** to submit the job for processing.

Contract Credit Selection Report Layout

After the batch run has completed successfully, you can run the Contracts Awaiting Edit And Acceptance Of Credits/Re-Invoices report.