

-
-
-
-
-

Chapter 6

Warranty Claims



Warranty Claim Creation







1/WOW

Use this option to manually enter a warranty claim. Workshop Management does not check any of the information entered, it just stores the record.

Workshop Management makes a copy of the information entered and creates a workshop job for the warranty claim. When Workshop Management creates the job, it checks and highlights all problems with the information.

When you maintain the Warranty Claim, it is the copied job you maintain. Workshop Management stores the original record, with all the errors, so that you can analyse it, if required.



Warranty Claim Header Creation Screen



To display this screen, on the Warranty Claim Creation Selection screen, select a customer and location and press **Enter**.

Use this screen to enter the warranty claim information. Once you save the information on this screen, Workshop Management copies the information and creates a job.



Note: Once you have entered and saved the initial information, you maintain the job and not the original record.

W0300	Z1 - Demonstration Company	User GBJBANB4	22/01/98
	CENTRAL WORKSHOP		09:52:11
Warranty Claim Header Creation		Claim Number 0000015	
Account Number	GC03 / 000	The Make-Up Shop	
Ownership.....?..	0		
Claim type.....?..	1		
Job category.....?..	WTY Warranty call		
Claim reference.....	W23456		
Model number.....?..	WA10	Serial number...:	
Purchase date.....	10/10/97		
Received for repair....	22/01/98		
Repair completed.....	0/00/00		
Condition code.....?..	-	Symptom code?:	- - -
Repair time...(HH:MM)...			
Authorisation number...			
Extended warranty nbr ..		Contract type .?..	Start date .. 0/00/00
Non-Reportable.....	0		
F3=Exit F4=Prompt F6=History F8=Update F12=Previous			
F14=End User F16=Original Dealer F18=Parts F21=Fault Information			

Fields:

Ownership

Enter one of the following:

0 - End customer. If the warranty claim is for equipment at a customer site.

1 - Dealer Stock Repair. If the warranty claim is for equipment which is part of the dealer's stock.

Claim Type

Enter one of the following:

0 - Parts. The claim is for parts only.

1 - Labour. The claim is for labour only.

2 - Both. The claim is for both parts and labour.

Job Category

Select the job for this warranty claim. This defaults to the warranty claim default job category.

Claim Reference

Enter a reference for the claim.

Model Number

Select the model this warranty claim is for.

Serial Number

Enter the serial number of the equipment.

Purchase Date

Enter the purchase date of the equipment.

Received For Repair

Enter the date the workshop received the faulty equipment.

Repair Completed

Enter the date the workshop completed the repair.

Condition Code

Select the condition of the equipment.

Symptom Code

Select the symptoms shown by the equipment.

Repair Time

Enter the length of time it took to repair the equipment, in hh:mm format.

Authorisation Number

Enter the repair authorisation number.

Extended Warranty No.

Enter the number of the extended warranty.

Contract Type

Enter the type of contract that covers this equipment.

Start Date

Enter the start date of the contract.

Non-Reportable

Enter one of the following:

0 - If you need to report the repair. This is the default.

1 - If you do not need to report the repair.

Functions:

F6

History. Use this function to display the Warranty Claim Enquiry screen.

F14

End User. Use this function to maintain the name and address details of the end user of this machine.

F16

Original Dealer. Use this function to maintain the name and address details of the original dealer of this machine.

F18

Parts. Use this function to display the Warranty Claim Parts Creation screen. If there is no installation record for this machine, and the Ownership field is set to Customer, a window displays for you to enter the details of where this machine is installed.

F21

Fault Information. Use this function to add fault information to the warranty claim.



Select **F8=Update** to save the information.



Note: If you set the Ownership to 0 - Customer and have not yet entered the name and address, a window displays so you can enter the customer details.



Note: If you set the Claim Type to 1 - Labour, and there are no parts associated with the claim, then a window displays so you can enter a reference, the faulty section, the defect and required repair for future reporting.

Warranty Claim Parts Creation Screen (F18)



To display this screen, select **F18=Parts** on the Warranty Claim Header Creation screen.

Use this screen to enter the parts required or fitted for this warranty claim.

W0301		Z1 - Demonstration Company WORKSHOP BRANCH		User GBJBATD0		9/01/98 15:52:48	
Warranty Claim Parts Creation				Claim Number 0509791			
Account Number	G003 / 000	The Make-Up Shop					
Ownership	0 End Customer						
Model Number	WA10	WATER ANALYSER : 10-LITRES/MIN					
Part Number	Description	Ref. No	Qty	Rec	Sect	D	R Invoice No
							More...
F3=Exit F4=Prompt F6=History F8=Update F10=Dealer F14=End User F16=Original Dealer							

Fields:

Part Number

Enter the part. This must be defined to Inventory Management.

Ref. No

Enter the reference number for this part.

Qty

Enter the quantity required.

Rec

Enter the quantity received.

Sect

Enter the faulty machine section.

D

Enter the defect with this part.

R

Enter the repair required or carried out.

Invoice No

Enter the invoice number.

Functions:

F6

History. Use this function to display the Warranty Claim Enquiry Screen.

F10

Dealer. Use this function to enter the name and address of the dealer making the claim.

F14

End User. Use this function to maintain the name and address details of the end user of this machine.

F16

Original Dealer. Use this function to maintain the name and address details of the original dealer of this machine.



Select **F8=Update** to save the information.



Note: If you set the Ownership to 0 - Customer and have not yet entered the name and address, a window displays so you can enter the customer details.

Fault Information Window (F21)



To display this window, select **F21=Fault Information** on the Warranty Claim Header Creation screen.

Use this window to enter the fault information if you have reported no parts for this warrant job.

W0300	Z1 - GB Demonstration Company	User GBJBANB1	24/04/98
	CENTRAL WORKSHOP		10:09:57
Warranty Claim Header Creation		Claim Number 0505227	
Account Number	PLCUS001 / 000	PL Testing Company	
Ownership.....?..	0 End Customer		
Claim type.....?..	1 Parts and Labour		
Job category.....?..			
Claim reference.....?			
Model number.....?..		Serial number....	
Information required if no parts are reported			
Section code...?..	CTL Controller	ptom code?:	_ _ _
Defect code...?..	A WORN OUT		
Repair code...?..	A REPLACEMENT		
Reference number...			
F4=Prompt F8=Update F12=Previous			
F3=Exit	F4=Prompt	F6=History	F8=Update F12=Previous
F14=End User	F16=Original Dealer	F18=Parts	F21=Fault Information
MA	a	17/025	

Fields:

Section code

Select the section of the machine that is faulty.

Defect Code

Enter the fault with this section.

Repair Code

Enter the repair carried out.

Reference Number

Enter a reference number for this repair.



Select **F8=Update** to save the information and return to the previous screen.

Warranty Claim Maintenance



2/WOW

Once you have created and initially validated a warranty claim, use this option to progress the claim until you either credit or reject the claim.

Warranty Claim Maintenance Selection Screen



To display this screen, select the Warranty Claim Maintenance option.

Use this screen to select the warranty claim you want to progress.

```
W0320          Z1 - Demonstration Company      USER GBJBATDO    9/01/98
                WORKSHOP BRANCH                16:12:09

Warranty Claim Maintenance

      Action Code.....?..:  █
And/Or Claim Number.....:
Or   Account Number.....?..:  Address Code.....:
Or   Model Number.....?..:
Or   Serial Number.....:
Or   Claim Reference no....:

F3=Exit  F4=Prompt
```

Fields:



Tip: You can enter the action code alone or the action code and one of the other selection fields.

Action code

Select the action of the claim you want to progress.

Claim number

Enter the claim number you want to progress.

Account Number

Enter the customer.

Address Code

Enter the address for the specified customer.

Model number

Enter the model for the warranty claim.

Serial Number

Enter the serial number of the equipment.

Claim Reference No

Enter the warranty claim reference number.



Enter the selection details and press **Enter** to display the Warranty Claim Maintenance screen.

Warranty Claim Maintenance Screen



To display this screen, enter the selection details and press **Enter** on the Warranty Claim Maintenance Selection screen.

Use this screen to maintain the selected claim. This screen displays, for each claim, the claim number, action code, creation date, customer and equipment details.

```

W0320          Z1 - Demonstration Company          USER GBJBATD0    9/01/98
                WORKSHOP BRANCH                    16:13:09

Warranty Claim Maintenance

   Claim Act Creation
n  Number Code   Date   Account/Address Model Number   Serial Number
■  509792 WR     9/01/98  GC03      / 000  WA10

1=Action 2=Maintain 3=History 4=Text
F3=Exit  F12=Previous F13=Fold/Truncate
  
```

Fields:

N

Selection field. Enter one of the following:

- 1 - Action. To enter an action using the Action Entry window as described in the Workshop Operations section of this product guide.
- 2 - Maintain. To maintain a warranty claim using the Warranty Claim Header Maintenance screen.
- 3 - History. To display the Warranty Claim History Enquiry for this claim.
- 4 - Text. To enter job story text for this warranty claim.

Functions:

F13

Fold/Truncate. Use this function to toggle the display between one and two lines of information.



Select **F3=Exit** to return to the menu.

Warranty Claim Header Maintenance Screen (Option 2)



To display this screen, select a warranty claim with option 2 on the Warranty Claim Maintenance screen.

Use this screen to maintain the header details for the selected warranty claim.

W0321	Z1 - Demonstration Company	USER GBJBATD0	9/01/98
	WORKSHOP BRANCH		16:16:11
Warranty Claim Header Maintenance			
Account Number....?..	GC03 / 000	The Make-Up Shop	
Claim Number.....	509792	Creation Date....	9/01/98
Ownership.....	0 End Customer	Job Category...?..	WBD Warranty C
Action Code.....?..	03 Book In	Claim Type....?..	2 Both Parts
Claim Reference.....		Non-Reportable...?	0
Model Number.....?..	W010	Serial Number....	
Purchase Date.....	0/00/00	Ext.Warranty.....	
Received for repair..	0/00/00	Contract Type...?	001
Repair Completed....	0/00/00	Start Date.....	0/00/00
Condition Code....?..	-	Symptom Code...?..	
Authorisation Code..		Repair Time.....	
Duplicate Reference..		Header Errors.(0/1)..?	0
Reject	Active	Description	
15	1	Blank Purchase Date & End Cust	
18	1	Date Received for Repair Inval	
21	1	Invalid repair completed date	
25	1	Invalid Condition Code	+
F3=Exit F4=Prompt F7=Text F8=Update F12=Previous F14=Parts F24=More keys			

Fields:

Account Number

Enter the customer name and address you want to send this credit to. This customer must be a warranty claims customer defined to Workshop Management.

This field defaults to the customer details on the Installation record.

Ownership

Enter the type of ownership.

Job Category

Enter the job category defined on the Job Category file.

Action Code

Enter an action defined for this Workshop Branch. This new action and the previous action must be a valid combination.

The initial actions are created by the batch program run when you create the warranty claim. Thereafter you must manually maintain the actions, unless you use **F23=Revalidate** to revalidate the entire claim.

Claim Type

Enter one of the following:

- 0 - Parts. If the claim is for parts only.
- 1 - Labour. If the claim is for labour only.
- 2 - Both. If the claim is for both parts and labour.

Claim Reference

Enter a reference for the claim.

Non-Reportable

Enter one of the following:

- 0 - If you need to report the repair. This is the default.
- 1 - If you do not need to report the repair.

Model Number

Select the model for this claim.



Note: Unless you enter a valid model, you cannot set the action to clear for payment.

Serial Number

Enter the serial number of the equipment.

Purchase Date

Enter the date the equipment was purchased.

Ext. Warranty

Enter the number of any extended warranty.

Received For Repair

Enter the date the workshop received the equipment for repair.

Contract Type

Enter the type of contract that covers this equipment.

Repair Completed

Enter the date you completed the repair.

Start Date

Enter the start date of the contract.

Condition Code

Select the condition of the equipment.

Symptom Code

Select the symptoms shown by the equipment.

Authorisation Code

Enter the repair authorisation number.

Repair Time

Enter the length of time it took to repair the equipment, in HH:MM format.

Duplicate Reference

This is a memo only field. Enter the number of previous claims made on this model and serial number combination.

Header Errors

Enter one of the following:

- 0 - To only print the header errors on the customer letters.
- 1 - To print both header and parts errors on the customer letters.

Reject

This displays the reject reasons created by the batch program run when you created the warranty claim. You cannot remove any system controlled reject reasons, you must correct the data to do this. You can however, add or delete user created codes at any time.



Tip: You can inhibit the functionality of a system generated reason code using the Active flag.

Active

Enter one of the following:

- 0 - If you do not want this reject reason used when creating prints and clearing files.
- 1 - If you want this reject reason used when creating prints and clearing files.



Note: You cannot clear a claim until all reject reasons are inactive. You can make the codes inactive either by correcting the data, or setting this field to 0.

Description

This displays the description of the reject reason.

Functions:

F7

Text. Use this function to maintain text associated with this warranty claim.

F8

Update. Use this function to update the files.

If the claim is labour only, and you have no parts associated with it, then a window displays so you can enter and update the reference, machine section, and repair codes. Workshop Management then checks if it needs to assign any reject reasons. Once the reject reasons are assigned the files are updated.

F14

Parts. Use this function to access the Warranty Claims Parts Maintenance screen.

F15

End User. Use this function to maintain the name and address details for the end user.

F16

Orig. Dealer. Use this function to maintain the name and address details for the original dealer.

F17

Override Name & Address. Use this function to change the installation contact and address details, using the Verify Installation Address screen.

F18

Org. Claim. Use this function to display the Warranty Claim Original Data screen which shows the data entered when you created the warranty claim.

F19

Document History. Use this function to display the document history for this warranty claim.

F20

Claim Progress. Use this function to display the Claim Progress window.

F21

Fault Info. Use this function to enter fault information at any time during the maintenance of the warranty claim.

F22

Warranty Claim Enquiry. Use this function to display the Warranty Claim Enquiry.

F23

Revalidates. Use this function to re-run the validation process for this claim. Any resulting reject codes display on this screen. This removes the existing reject reasons and actions but you must select **F8=Update** to update the files.



Select **F8=Update**, to save the changes and return to the previous screen.

Warranty Claims Parts Maintenance Screen (F14)



To display this screen, select **F14=Parts** on the Warranty Claim Header Maintenance screen.

Use this screen to maintain the parts entered on the warranty claim. This displays the customer details and the parts on the claim. For each part, it displays the quantity, quantity returned, machine section, defect, repair required, reject reason, invoice number, and whether the item is to be paid for.

W0322		Z1 - Demonstration Company WORKSHOP BRANCH		USER GBJBATD0		9/01/98 16:18:49	
Warranty Claim Parts Maintenance				Claim Number 509792			
Account Number		GC03 / 000		The Make-Up Shop			
Claim Action		A3 Book In		Stock Type 0		End Customer	
Model Number		WA10		Serial Number			
Part Number	Qty	Qty Ret'd	Sect D R	Rej	Invoice No	Pay	
■ F54666	1			52	0000000	0	
				Unit Price			
1 = Reject Codes 2 = Invoice Search							
F7=Text		F12=Previous		F15=End User		F16=Orig Dealer	
F17=Override Name & Address		F18=Orig Claim		F20=Audit		F22=History	

Fields:

Untitled

Selection field. Enter one of the following:

- 1 - Reject code. To display the reject reasons and whether they are active for this part. You can also add more reject reasons.
- 2 - Invoice search. To display all parts claim lines entered for any customer with this invoice number, so you can see if the invoice is being used for multiple claims.

Functions:

F7

Text. Use this function to maintain text associated with the warranty claim.

F15

End User. Use this function to enter the name and address details for the end user.

F16

Orig. Dealer. Use this function to enter the name and address details for the original dealer.

F17

Override Name & Address. Use this function to change the installation contact and address details, using the Verify Installation Address screen.

F18

Org. Claim. Use this function to display the Warranty Claim Original Data screen which shows the data entered when you created the warranty claim.

F20

Audit. Use this function to display the Claims Progress window.

F22

History. Use this function to display the document history for the claim.



Select **F12=Previous** to return to the previous screen.

Verify Installation Address Screen (F17)



To display this screen, select **F17=Override Name & Address** on any Warranty Claims Maintenance screen.

Use this screen to change the details of the site where the equipment is installed.

SS146	Z1 - Demonstration Company WORKSHOP BRANCH	USER GBJBATD0	9/01/98 16:20:20
Verify Installation Address			
Machine.....:	WA10 /	Job number.....:	509792
Customer number..:	GC03 000	WATER ANALYSER : 10-LITRES	
Customer name....:	The Make-Up Shop	Currency customer 1	
Customer address:	141 Great Hampton Street	Currency code...?:	GBP
	Hockley	Curr rate code...?:	PERD
	Birmingham	VAT code.....?:	001
	England		
		B18	6AS
Machine location:			
Contact person...:		Geo code.....:	B18 6AS
Telephone number:		Fax number...:	
Opening hours....:	Mon	Tue	Wed
	Thur	Fri	Sat
	Sun		
From...:			
Until...:			
From...:			
Until...:			
F4=Prompt F8=Update F12=Previous			

Fields:



Tip: All these fields default to the values entered on the installation details.

Customer Name

Enter the new customer name.

Customer Address

Enter the new address.

Currency Customer

Enter one of the following:

0 - If this customer is not a currency customer.

1 - If this customer is a currency customer.

Currency Code

Enter the currency for this customer.

Curr Rate Code

Enter the currency rate for this customer.

VAT Code

Enter the VAT code for this customer.

Machine Location

Enter the exact location of the faulty equipment.

Contact Person

Enter the contact for this piece of equipment. If you change the name, Workshop Management only updates the details for this machine.

Geo Code

Enter the customer geocode.

Telephone Number

Enter the telephone number for the customer.



Note: Do not change a 20 figure telephone number because Workshop Management loses the last 5 characters, since the override address only holds 15 numbers.

Fax Number

Enter the fax number for the customer.

Opening hours

Enter the opening hours for the customer.



To save the information and return to the previous screen, select **F8=Update**.

Warranty Claim Original Data Screen (F18)



To display this screen, select **F18=Org Claim** on any Warranty Claim Maintenance Screen.

This screen displays the details entered when you created the warranty claim. These details include: customer name and address, claim status, equipment details, fault, and reference numbers.

W0329	Z1 - Demonstration Company WORKSHOP BRANCH	User GBJBATD0	9/01/98 16:20:57
Warranty Claim Original Data		Claim Number 0509792	
Account Number	GC03 / 000	The Make-Up Shop	
Claim Status		Ownership	0 End Customer
Claim Type	2 Both Parts and Labou	Claim Date	090198
Model Number	WA10	Serial Number	
Date of Purchase	000000	Claim Ref	
Date Recd for Rep	000000	Condition	
Date Rep Complete	000000	Symptom Code	
Repair Time	0000	Ref Number	000000
Labour Rate 0/V		Auth Number	
Ext Warr Number		Start Date	000000
Sel Part Number	Contr. Typ B01	Qty	Ref. No Sect D R NR
1 F54666	Description	001	002345 0
		Bottom	
1=Original reject codes			
F3=Exit	F12=Previous	F16=Header Reject Codes	F23=Code Descriptions

Fields:

Sel

Selection field. Enter 1 - Original Reject Codes to display the original reason for rejecting the claim.

Functions:

F16

Header Reject Codes. Use this function to display all job header reject codes which are the same as those shown on the Warranty Claim Header Maintenance screen. If Workshop Management finds no reject codes, it displays No Records To Display.

F23

Code Descriptions. Use this function to display two lines of details for each part.



Select **F12=Previous** to return to the previous screen.

Claim Progress Window (F20)



To display this window, select **F20=Claims Progress** on any Warranty Claims Maintenance screen.

This window displays, for each action completed so far, the date and time of the action and the user who entered the action on the system.

W0321	Z1 - Demonstration Company	USER GBJBATD0	9/01/98
	WORKSHOP BRANCH		16:22:08
Warranty Claim Header Maintenance			
Account Number....?..	GC03 / 000	The Make-Up Shop	
Claim Number.....	509792	Creation Date....	9/01/98
Ownership.....	0 End Customer	Job Category...?	WRD Warranty C
Action Code.....?..	A3 Book In	Claim Type....?..	2 Both Parts
Claim Reference.....		Non-Reportable...?	0

Date	Time	User ID	Act	Description
9/01/98	16:00	GBJBATD0	WR	Warranty Suggest Rejection
9/01/98	16:14	GBJBATD0	A3	Book In



Select **F12=Previous** to return to the previous screen.

Returned Parts Maintenance



10/WOW

Use this option to maintain a list of parts which need to be automatically flagged as returned, if they are on any warranty claim.

If one of these items is on a claim and has not already been flagged as received, the workshop validation routines set the action of the call to Awaiting Parts.



Note: This list is not date controlled. If the item is on the list when you run the validation routines, the action is set to Awaiting Parts.

Parts Required for Return Maintenance Selection Screen

 To display this screen, select the Returned Parts Maintenance option.

Use this screen to enter or delete the parts from the list of parts which must be flagged as returned.

W0330

Z1 - Demonstration Company
WORKSHOP BRANCH

User: GBJBATD0

9/01/98
16:30:22

Parts required for return maintenance

Part Number.....?:

n	Part Number	Description
-	PLUG	Plug
-	RCOIL1	150mm x 3mm Coil Steel
-	RDITEM2	Sys test item 2
-	RDITEM3	Test item 3

4=Delete

Bottom

F3=Exit

F4=Prompt

F8=Update

F12=Previous

 *Note: Only the part number field displays until you add a part number to the list.*

Fields:

Part Number

Enter the part you want to add to the list and press **Enter**. The part displays in the list below.

n

Selection field. Enter 4 - Delete next to the part you want to delete from the list.

 Select **F8=Update** to save the list.

Warranty Claim Labour Credit Code



11/WOW

Use this option to set up a table of credit rates which are credit code and currency specific. The credit rates are for all levels of the model hierarchy and have effectivity dates.

You can raise a credit note to credit a dealer for a fixed amount of labour or an hourly rate for the number of hours worked on the claim. The type of credit note raised depends upon the setting of the Warranty Claim flag on the Customer Additional Details Maintenance Screen 2.

Workshop Management uses this table to calculate the credit. The value used depends upon which labour rate list you entered in the Warranty Claim Labour Credit List field on the Additional Details Maintenance Screen 2.

During batch validation, Workshop Management checks this table for the relevant value if you require a labour credit, and outputs an error if the required value does not exist.

Labour Credit List Maintenance Selection Screen



To display this screen, select the Warranty Claim Labour Credit Code option.

Use this screen to select the credit code and currency for which you want to maintain labour credit values.

W0331	Z1 - UK Demonstration Company	User: GBJBANB4	10/02/98
	CENTRAL WORKSHOP		11:31:44
Warranty Claim Labour Credit list maintenance			
Warranty Claim Labour credit code..?: <u>L01</u>			
Currency code.....?: <u>GBP</u>			
F3=Exit F4=Prompt			

Fields:

Warranty Claim Labour Credit Code

Select the labour credit list you want to maintain.

Currency Code

Select the currency code you require. This defaults to the standard base currency of the Accounts Receivable company.



Enter the details and press **Enter** to display the Warranty Claim Labour Credit Maintenance screen.

Warranty Claim Labour Credit Maintenance Screen



To display this screen, enter the details and press **Enter** on the Labour Credit Maintenance Selection screen.

Use this screen to maintain and define labour credit values for divisions, models groups, model sub-groups and models.

W0331	Z1 - UK Demonstration Company	User GBJBANB4	10/02/98
	CENTRAL WORKSHOP		11:32:17
Warranty Claim Labour credit maintenance		UPDATE	
Labour Credit code LC1	Labour Credit code 1	Currency Code...	GBP
Division.....?..	_____		
Model group.....?..	_____		
Model sub group....?..	_____		
Model.....?..	_____		
Effective date.....	0/00/00		
Job Category.....?..	_____		
Fixed credit value....	_____	Hourly credit value..	_____
	_____		_____
n	Div Grp S/Grp Model group	Cat Effec. Date	Fixed Value Hourly Rate
_	10 100	WTY 1/03/98	20.00 10.00000
			Bottom
1=Select 4=Delete			
F3=Exit F4=Prompt F8=Update F12=Previous			

Fields:



Tip: You must enter a division, the model, group, and sub-group fields are optional. You only need to enter a model group, if you enter a model sub-group, and you only need to enter a model sub-group if you enter a model.

Division

Select the division required.

Model Group

Select the model group required.

Model Sub Group

Select the model sub-group required.

Model

Select the model required.

Effective Date

Enter the date that these credit rates become effective.

Job Category

Enter the category of job that these rates apply to.

Fixed Credit Value

Enter the value of credit for Fixed Credit value claims.

Hourly Credit Value

Enter the hourly rate of credit given.

N

Selection field. Enter one of the following:

1 - Select. To maintain the defined credit rates. The details display in the fields at the top of the screen. You can only maintain credit rates with an effective date of greater than or equal to today's date. If you have used the credit values to generate a credit note, they are retained so you can enquire on them.

4 - Delete. To delete the defined credit rates. You can only delete credit rates with an effective date of greater than or equal to today's date.



Select **F8=Update** to save all new entries, and delete all files marked for deletion.

Model/Parts Relationship Maintenance



12/WOW

Use this option to define the parts that customers can make warranty claims for, for each model.



Note: If you do not set up a model and parts relationship using this option, Workshop Management presumes that customers can claim for any part against a model.

Model/Parts Relationship Maintenance Selection Screen



To display this screen, select the Model/Parts Relationship option.

Use this screen to select the model for which you want to define parts relationships.

Fields:

Model

Select the model required. This model must exist on the Model Master file.



Select the model and press **Enter** to display the Model/Parts Relationship Maintenance screen.

Model/Parts Relationship Maintenance Screen



To display this screen, select the model and press **Enter** on the Model/Parts Relationship Maintenance Selection screen.

Use this screen to define the parts for which you can make warranty claims against this model.

```

W0332                Z1 - UK Demonstration Company      User GBJBANB4      10/02/98
                     CENTRAL WORKSHOP                  11:33:16
Model/Part Relationship Maintenance

Model Number.....: METER                METER MACHINE
Part Number.....?: 

S Part Number      Description

4=Delete
F3=Exit   F4=Prompt   F8=Update   F12=Previous

```

Fields:

Part Number

Enter the part number and press **Enter** to add the part to the relationship list.

The part displays in the list below.

S

Selection field. Enter 4 - Delete alongside the part you want to delete from the relationship list.



Select **F8=Update** to save any changes and return to the selection screen.

Customer/Model Invalid Claims

1... 13/WOW **2...**

Use this option to create an exclusion file. The exclusion file prevents a customer from requesting warranty claims for a particular model during a particular time period.

Use this option when a dealer buys out the guarantee for a particular model, model sub-group or division.

Whenever Workshop Management validates a claim, it checks this file. If a record exists for the customer, model and date combination, Workshop Management rejects the claim and assigns the relevant rejection reason.

Customer/Model Claimable Maintenance Selection Screen



To display this screen, select the
Customer/Model Invalid Claims option.

Use this screen to select the customer for which you want to define a model
exclusion file.

Fields:

Account Number

Enter the customer name.

Address code

Enter the customer address.



Tip: Leave the address code field blank and
press **Enter** to display a list of all addresses for
this customer. Select the required address.



Enter the customer details and press **Enter** to
display the Customer/Model Claimable
Maintenance screen.

Customer/Model Claimable Maintenance Screen



To display this screen, enter the customer details and press **Enter** on the Customer/Model Claimable Maintenance Selection screen.

Use this screen to define the models and dates for which this customer cannot make warranty claims.

```

W0333          Z1 - UK Demonstration Company   User GBJBANB4   10/02/98
                  CENTRAL WORKSHOP              11:43:47
Customer/Model Claimable Maintenance

Account Number..... GC03      / 000   The Make-Up Shop
Division.....?..:  █
Model group.....?..:  █
Model sub group.....?..:  █
Model number.....?..:  █
Date range.....:  0/00/00   to  0/00/00

n Division  Group  Sub-group  Model          Date range
-   10       100    -         1/02/98 - 1/04/98
-   10       100    -         1/06/98 - 1/07/98

4=Delete

Bottom

F3=Exit  F4=Prompt  F8=Update  F12=Previous
  
```

Fields:



Tip: You must enter a division, the model, group, and sub-group fields are optional. You only need to enter a model group, if you enter a model sub-group, and you only need to enter a model sub-group if you enter a model.

Division

Select the division required.

Model Group

Select the model group required.

Model Sub Group

Select the model sub-group required.

Model Number

Select the model required.

Date Range

Enter the date range that this exclusion applies to.

N

Selection field. Enter 4 - Delete to delete the defined exclusion.



Select **F8=Update** to save all changes and return to the selection screen.

Warranty Claim History Enquiry

1... 20/WOW
2...

Use this enquiry to display the details of all warranty claims and warranty jobs.

Warranty Claim Enquiry Initial Screen



To display this screen, select the Warranty Claim History option.

Use this screen to select the machine or customer for which you want to display the claim details.

W0326	Z1 - UK Demonstration Company CENTRAL WORKSHOP	USER GBJBANB4	10/02/98 11:45:04
-------	---	---------------	----------------------

Warranty Claim Enquiry

Action Code.....?.. █

And/Or Claim Number.....: _____

Or Account Number.....?..: _____ Address Code.....: ____

Or Model Number.....?..: _____

Or Serial Number.....: _____

Or Claim Reference no...: _____

F3=Exit F4=Prompt

Fields:



Tip: You can enter the action code alone or the action code and one of the other selection fields.

Action Code

Select the action of the claim you want to display.

Claim Number

Enter the claim number you want to display.

Account Number

Enter the customer.

Address Code

Enter the address for the specified customer.

Model Number

Enter the model for the warranty claim.

Serial Number

Enter the serial number of the equipment.

Claim Reference No.

Enter the warranty claim reference number.



Enter the selection details and press **Enter** to display the Warranty Claim Enquiry Claim Selection Screen.

Warranty Claim Enquiry Claim Selection Screen



To display this screen, enter the selection details and press **Enter** on the Warranty Claim Enquiry Initial screen.

Use this screen to select the enquiry for which you want to display the details.

For each claim, the screen displays the number, the action, branch, creation date, customer and equipment details.

W0326	Z1 - Demonstration Company				USER GBJBATDO		9/01/98	
	WORKSHOP BRANCH						16:15:38	
Warranty Claim Enquiry								
n	Claim Number	Act Code	Branch	Creation Date	Account/Address	Model Number	Serial Number	
1	509792	A3	W0	9/01/98	GC03 / 000	WA10		
1=Detail 2=Parts 4=Text								
F3=Exit F12=Previous								

Fields:

N

Selection field. Enter one of the following:

- 1 - Details. To view the Warranty Claim Enquiry Header screen.
- 2 - Parts. To view the Warranty Claim Enquiry Parts screen.
- 4 - Text. To view the text associated with the warranty claim.



Select **F3=Exit** to leave the enquiry.

Warranty Claim Enquiry Header Screen (Option 1)



To display this screen, select a claim with option 1 on the Warranty Claim Enquiry Claim Selection screen.

This screen displays the customer, model, purchase and job details for the claim. It also shows the reject reasons and whether they are active. The job details include the repair time, reference numbers, claim type, symptoms and repairs.

W0327	Z1 - GB Demonstration Company	USER GBJBANB1	24/04/98
	CENTRAL WORKSHOP		10:44:45
Warranty Claim Header Enquiry			
Account Number.....	PLCUS001 / 000	PL Testing Company	
Claim Number.....	505086	Creation Date....	10/02/98
Ownership.....	0 End Customer	Job Category.....	CSR
Action Code.....	81 WTY - SUGGEST R	Claim Type.....	0
Claim Reference.....			
Model Number.....	TV13	Serial Number....	SERIAL-001
Purchase Date.....	1/01/98	Ext.Warranty.....	
Received for repair..	0/00/00	Contract Type....	*NO
Repair Completed....	0/00/00	Start Date.....	0/00/00
Condition Code.....	1 CONSTANTLY	Symptom Code....	110 testing
Authorisation Code..		Repair Time.....	
Duplicate Reference..		Header Errors.(0/1)..	0
	Reject Active Description		
F3=Exit F7=Text F12=Previous F14=Parts F24=More Keys			
M0 a			01/001

Functions:

F7

Text. Use this function to display the text associated with this warranty claim.

F14

Parts. Use this function to display the Warranty Claim Enquiry Parts screen.

F15

End User. Use this function to display the name and address details for the end user.

F16

Original Dealer. Use this function to display the name and address details for the original dealer.

F17

Name/Address Override. Use this function to display the override customer details. This is the name and address that is printed on any credit note produced.

F18

Orig. Claim. Use this function to display the Warranty Claim Original Data screen.

F20

Claim Progress. Use this function to display the Claim Progress window.

F22

Document history. Use this function to display the document history for this claim.



Select **F3=Exit** to leave the enquiry.

Warranty Claim Enquiry Parts Screen (Option 2)



To display this screen, select a claim with option 2 on the Warranty Claim Enquiry Claim Selection screen.

This screen displays the customer, model, and labour credit number and the parts on the warranty claim. For each part this screen displays the quantity received and required, the machine section, defect, repair and invoice details.

W0328	Z1 - GB Demonstration Company	USER GBJBANB1	24/04/98
	CENTRAL WORKSHOP		10:45:56
Warranty Claim Parts Details		Claim Number	505086
Account Number	PLCUS001 / 000	PL Testing Company	
Claim Action	81 WTY - SUGGEST R	Stock Type	0 End Customer
Model Number	TV13	Serial Number	SERIAL-001
Labour Credit No.		Labour Value	
Part Number/ Description	Qty 1	Qty Ret'd	Invoice / Rej Credit No.
ALLUN			
Standard Costed Item			
1=Reject Codes Enquiry 2=Invoice Search			
F3=Exit F7=Text F12=Previous F13=Toggle Desc. F24=More Keys			
M8 a			12/002

Fields:

(Untitled)

Enter one of the following:

- 1 - Reject Codes Enquiry. Use this option to display a list of all the reject codes for this claim.
- 2 - Invoice Search. Use this option to display a list of all the claims on an invoice.

Functions:

F7

Text. Use this function to display the text associated with this warranty claim.

F13

Toggle Desc. Use this function to toggle the screen between one and two lines of details for each part.

F15

End Users. Use this function to display the name and address details for the end user.

F16

Original Dealer. Use this function to display the name and address details for the original dealer.

F17

Name/Address Override. Use this function to display the override customer details. This is the name and address that is printed on any credit note produced.

F18

Orig. Claim. Use this function to display the Warranty Claim Original Data screen.

F20

Claim Progress. Use this function to display the Claim Progress window.

F22

Document history. Use this function to display the document history for this claim.



Select **F3=Exit** to leave the enquiry.

Model Failure Analysis Enquiry



21/WOW

Use this enquiry to give a quick summary view of common fault problems.

This is to assist in the technical support you give to customers.

Model Failure Analysis Selection Screen



To display this screen, select the Model Failure Analysis option.

Use this screen to select the model and date for which you want to view the failures.

```
W0325          Z1 - GB Demonstration Company   User GBJBANB1   24/04/98
                CENTRAL WORKSHOP              10:50:39
Model Failure Analysis Enquiry

Model Number.....?..:
Date Range.....: 0/00/00 to 24/04/98

F3=Exit  F4=Prompt

M& a                                05/029
```

Fields:

Model Number

Select the model required. This must be a model defined on the Model file.

Date Range

Enter the range of dates.

The From date can be blank and cannot be greater than the To date.

The To date defaults to today's date, and cannot be greater than the current date.



Enter the model and date range, then press **Enter** to display the Model Failure Analysis screen.

Model Failure Analysis Screen



To display this screen, enter the model and date range, then press **Enter** on the Model Failure Analysis Selection Screen.

This screen displays all the warranty claims for the model in the date range. The information displayed is the condition, symptom, description, and total number of claims for this fault.

W0325	Z1 - GB Demonstration Company	User GBJBANB1	24/04/98
	CENTRAL WORKSHOP		10:51:33
Model Failure Analysis Enquiry			
Model Number.....?: TV19		TELEVISION 19"	
Date Range.....: 0/00/00 to 24/04/98			
n	Condition	Symptom Description	Total
1=Select			
F3=Exit F12=Previous			
MA	a	01/001	

Fields:

Untitled

Selection field. Enter 1 - Select against a condition to display more details on the Model Failure Analysis Parts Details Screen.



Select a condition with option 1 to display the Model Failure Analysis Parts Details Screen.

Model Failure Analysis Parts Details Screen (Option 1)



To display this screen, select a condition with option 1 on the Model Failure Analysis screen.

This screen displays, for the condition selected, the parts, machine section affected, defect, repair, and the total number of claims. The model, date range, condition and symptom, selected previously display at the top of the screen.



Select **F3=Exit** to leave the enquiry.

Batch Generation of Credit Notes



40/WOW

Use this option to create Sales Order (SOP) credit notes for all warranty claims cleared for credit.

This batch job can create two types of credits for each claim line, one for labour and one for parts. These are combined onto one SOP credit note.

Processing

The batch job:

1. Selects all claims with an action of Cleared For Credit.
2. Consolidates all credits for parts for one customer. This credit note does not have a Stock Update attached.
3. Values the credit. The value for parts is the price of the item on the original invoice, if this available, or the price of the item, using Advanced Pricing and the purchase date, or the repair completion date, or the claim creation date. Any discounts associated with the customer on the selected date are also included.
4. Consolidates all credits for labour for a customer site.
5. Calculates the hourly credit rate, where applicable, using the labour credit code and values defined.
6. Generates each line and a credit note number, which is written to the technical report parts file. Labour lines are written to the credit note before the part claim lines. Text associated with the claim is written as line 2 of the external text associated with the order.
7. If you created an override name and address file for the warranty claim, this is written to the override file for the Invoice / Credit header.
8. Updates the action code on the warranty claim as Payment Paid.

This batch job also prints the account summary document for the customers that require this documentation.



To run the batch job, select the Batch Generation Of Credit Notes option.