

-
-
-
-
-

Chapter 9

Utilities



Copy Company Utility



1/WOU

Use this option to create a new company by copying data from an existing company.

AS/400s keep details of the physical files copied, and at what copying level, on SSPFS in the files library.

You can make any changes in the new company (for example, company name) using the Application Manager file maintenance options. Remember to extend user profiles to include the new company code.



Note: You must have exclusive use of Workshop Management to do this.

You have to specify the amount of data you want to copy. Level 1 copies the minimum; level 4 copies the maximum amount.

The system copies the following database files for each level:

Level 1 copies:

Company Profile (SSP00, SSP87).

Calendar Control (SSP01, SSP02).

Daily Calendar: Period End Dates (SSP03) and Day Types (SSP14).

Branch (SSP10).

Codes/Parameter (SSP12).

System Parameters (SSP04, SS04E).

User/Branch Authorities (SSP15).

Division (SSP75).

Model Group (SSP32).

Model Sub-Group (SSP16).

Contract Rates (SSP17).

Recommended Service Visits (SSP19).

Scheduled Visit Profile (SSP37).

Job Category (SSP63).

Contract Type (SSP64).

Contract Type/Job Category (SSP65, SSP58, SSP59).

Escalation Control (SSP85).

Escalation Report Data (SSP86).

Tax Codes (SSP90).

Level 2 copies all the Level 1 files, plus:

Engineer Master (SSP24).
Assisting Engineer (SSP76).
Alternative Engineer (SSP29).
Model (SSP30, SSP27).
Volume Segment (SSP69).
Geocode/Territory (SSP61).
Team (SSP67).
District (SSP68).
Field Service Group (SSP88).
Engineer Assignment (SSP62).
Labour Rates Price List (SSP66).
Record Locking (SSP99).
Zone Charges (SSP60).
3-D Matrix(SSP77).

Level 3 copies all the Level 1 and 2 files, plus:

Text (SSP11).
Customer Additional Service Details (SSP21).
Installation Details: Machines and Peripherals (SSP22, SSP23).
Contract Header, including Service Parameters (SSP35) and Billing Cycle (SSP40).
Contract Header and Equipment: Conditions (SSP39).
Contract Equipment and Peripherals (SSP38, SSP28).
Contract Scheduled Visits (SSP36).
Quotes Based on Contract Request Log (SSP82).
Special Serial No. Response Times (SSP78).

Level 4 copies ALL the SSP files, that is: all the above, plus jobs, technical reports, invoices, and so on.



Note: This utility does not copy customer records (SLP05). Use the Copy Company utility in Accounts Receivable to do this.



Note: If you interface to Inventory and SOP, you need to use the Inventory option to copy the engineer stockrooms and the stockroom balances; and the SOP utility to copy the parts price and discount lists.

Copy Company Utility Screen



To display the Copy Company Utility Screen,
select the Copy Company Utility option.

Use this screen to select the company and level of information to copy to the new company.

SS970P	Demonstration Company	USER BRERETM	1/12/93 11:44:25
COPY COMPANY UTILITY			
Copy from company: <u>ZM</u> to company: <u>NW</u>			
Copy detail level: <u>1</u> - this parameter specifies the amount of information that is to be copied and should be a value from 1 to 4. (1 representing the least information and 4 the most). For further explanation please refer to the user's guide).			
Max. no. of records: <u>99999</u>			
F3=Exit F8=Submit job			

Fields:

Copy From Company

Enter an existing company. This defaults to the current company.

Copy To Company

Enter the company to create. This company must not already exist.

Copy Detail Level

Enter the level of information to copy:

1 - Base data only. This is company profile, calendar, job categories, price lists, contract types.

2 - Second level data. This is base data plus engineers, models, territories and engineer assignments;

3 - Third level data This is level 1 and 2 data, plus installations, contracts and customer additional service details;

4 - Fourth level data. This copies all data in the company, including transaction data such as jobs, technical reports and invoices.

Max No Of Records

Enter the maximum number of records to copy from each file. This must be greater than zero.



Note: You copy the customers using the Copy Company utility in Accounts Receivable.

You copy price and discount lists for parts using the Copy Company option in SOP.

You copy stockrooms used by the engineers, using the Inventory Copy Company option.



To copy the company, select **F8=Submit**.

Delete Company Utility



2/WOU

Use this option to delete all the Workshop Management data associated with a company.





Note: You must have exclusive use of Workshop Management to do this.



Note: You must end the sub-system which runs the job escalation batch update.



Note: Once you have submitted the job, you must exit Workshop Management.



Codes/Parameter Maintenance

3/WOU

Use this option to maintain various reserved code values, supplied as part of Workshop Management. These codes are essential to Workshop Management operation.

Only use this option in special circumstances, and then only under the guidance of an experienced technical adviser on Workshop Management, since if you corrupt reserved codes it causes severe problems. Therefore access to the option should be restricted to the most senior person(s) responsible for data integrity.



Note: You must have exclusive use of Workshop Management to do this.

Concepts

Workshop Management uses a number of different parameter types, some of which are of a sensitive nature. The system identifies the special codes with a * before the parameter type description.

The following rules apply:

- Parameter type code - you must not amend.
- Parameter type description - you must not amend.
- Code ID - you must not amend.
- ID description - can amend if advised and approved by your software support organisation.

Codes/Parameter Maintenance Screen 1

 To display this screen, select the Codes/Parameter File Maintenance option.

Use this screen to select the parameter type you require.

SS00861 - 61 - Demonstration CompanyUSER SSV311/12/9518:03:54

CENTRAL BRANCH

Codes/Parameter Maintenance

Parameter Type Enter PTDS to define new type

Parameter I.D.

1

Type

Description

ABSC

Engineer Absent Codes

CCAL

Customer Calendar Codes

CCRC

Contract Cancellation Reason

CHGT

Miscellaneous Charge Types

CHST

* Contract Header Status

CLST

* Contract Line Status

CONF

Configuration code

CORA

Corrective actions

CREA

Call Cancellation Reason

DAYS

* Day Descriptions

+

1=Select

F3=Exit F4=Code Selection

05-20

SP

MM

KS

IM

II

KENB20A

PET113S1

Fields:

Parameter Type

Enter an existing parameter type to add, amend or delete the associated parameters. Or enter PTDS to add or amend a parameter type.

Parameter ID

Enter the parameter ID for the parameter type you selected.

1

Selection field. Enter 1 against the parameter you want to select.

 **Warning: Do not amend or delete any of the system supplied parameter type definitions unless specifically advised to by your software support organisation.**

Functions:

F4

Code Selection. Enter a parameter type then select this function to display the Parameter Code Selection Screen.

 To display the Parameter Code Selection Screen, enter 1 against a parameter type.

Parameter Types

There are two types of codes: reserved codes, required by the system, and codes used and defined by users. You can create additional parameters to control processing. For example, the Field To Be Mandatory field for parameter type VLDN only appears for that parameter type, and determines whether you must enter the engineer and the fault code at call logging.

The parameter types available and where you use them, are:

ABSC

Engineer Absent Codes.

Code ID - one character.

You must have 1 - Logged on and 0 - logged off. You can define other possible reasons for an engineer's absence: For example, holiday, sickness.

ACTN

* Action Codes

Code ID - two numerics.

Defines the actions for a job: For example, replaced part, no fault detected.

CCAL

Customer Calendar Codes

Code ID - two characters.

Defines the calendar used by Workshop Management.

CCRC

Contract Cancellation Reason

Code ID - one character.

Defines the reasons for cancelling a contract: For example, Too expensive.

CHGT

Miscellaneous Charge Types

Code ID - three character.

Defines the types of expenses incurred when doing a job: For example, hotel costs, bought spare parts.

CHST

* Contract Header Status.

Code ID - one character.

Defines the possible status of a contract header: For example, quotation, active.

CLMT

Warranty Claim Type.

Code ID - one character.

Defines the Warranty Type. For example, Labour, Parts.

CLST

* Contract Line Status.

Code ID - one character.

Defines the status of a contract line: For example, active, expired.

CODC

Condition Code (Accessories).

Code ID - one Character.

Defines the condition code for accessories. This should only be used in the job accessory maintenance panel.

COLM

Collection Method.

Code ID - two character.

Defines how you get the equipment: For example, courier, customer delivers.

CONC

IRIS Condition Code.

Code ID - one character.

Defines the IRIS condition code for fault reporting. For example, overheats, no power.

CONF

Configuration Code.

Code ID - one character.

Defines the area or piece of faulty equipment: For example, keyboard, screen.

CORA

Corrective Actions.

Code ID - three characters.

Defines the action taken to correct the fault: For example, replaced part, soldered joint.

CRDR

Credit Assessment Reason Code.

Code ID - two characters.

Defines the credit assessment. For example, credit not available, credit required.

CREA

Call Cancellation Reason.

Code ID - two characters.

Defines why you can cancel a logged call: For example, customer cancelled, not covered by contract.

CRTY

Credit Type.

Code ID - one character.

Defines the credit type. For example, credit not applicable, credit required.

DAYS

* Days Description.

Code ID - three characters.

Defines the descriptions used for the days of the week.

DAYT

Day Type.

Code ID - one character.

Defines the type of day: For example, working, non-working, or bank holiday.

DEFC

Defect Code.

Code ID - one character.

Defines the problem found with the faulty equipment: For example, loose wire, broken PCB.

DESM

Despatch Methods.

Code ID - one character.

Defines how you return the equipment to the customer: For example, courier, customer collected.

DFDM

Default Despatch Methods.

Code ID - one character.

Defines the default despatch method: For example, courier.

DISC

Discount Reasons.

Code ID - one character.

Defines the reasons for a discount: For example, Major Account, no discount.

DSST

Default Action Codes.

Code ID - two characters.

Defines the default actions for a fault: For example, replace part, scrap equipment.

EDAY

Elapsed Days.

Code ID - four characters.

Defines elapsed days. For example, warranty claim returns, quotation elapsed days.

EGRD

Engineer Job Grades.

Code ID - two characters.

Defines the engineer grades: For example, senior engineer, technician.

EQST

Equipment Status.

Code ID - one character.

Defines the status of the equipment.

ERRC

* Remote Communications Error codes

Code ID - two characters.

Defines the possible errors with the remote communications: For example, invalid company, invalid log off.

ETAR

* Engr Assignment Error Codes.

Code ID - two character.

Defines the error codes for automatic call assignment: For example. ACA not allowed for company, Unable to place call in queue.

FLTC

Faults.

Code ID - three characters.

Defines the faults reported for the equipment: For example, jammed, noisy.

GLPR

Global Price Increase Code.

Code ID - two character.

Defines the groups used to implement a price increase: For example, Dealer Groups Code, No Price Increase.

GLTX

* GL Deferred Revenue Transaction Text.

Code ID - one character.

Defines the text transferred to GL with the deferred revenue: For example, Service Contract Number, Service Deferral.

GTXT

* General System Text.

AC - F22=Accept Contract, QU - F22=Quotation Only.

INVT

Settlement Discount Invoice Type.

Code ID - one character.

Defines the type of invoice for settlement discount. For example, job invoice, contract invoice.

JETT

Job Entry Type.

Code ID - one character.

Defines the type of job entry. For example, pre-book job, book-in job.

JHST

* Job Header Status.

Code ID - one character.

Defines the status of the job header: For example, Open, Cancelled.

JLAB

* Job Line Abbreviated Status

Code ID - two character.

Defines the abbreviations for the job line status: For example, Opn, ASS.

JLST

* Job Line Status.

Code ID - two characters.

Defines the job line statuses: For example, 00=Open, 09=Partial Report.

LHTY

Labour Hours Type Codes.

Code ID - four characters.

Defines the type of labour hours available: For example, Basic, Overtime.

LOAN

Loan Types.

Code ID - one character.

Defines the type of loans available: For example, on service loan, demonstration.

MAJF

Major Fault Flag.

Code ID - one Character.

Defines the Major Fault. For example, burnt, destroyed.

MROV

Reason for Override.

Code ID - two characters.

Defines the reason for a meter reading override: For example, Meter Change, Previous Actual Incorrect.

MRSR

Meter Reading Source.

Code ID - one character.

Defines the methods used for getting the meter reading: For example, customer reading, engineer reading.

MTHS

* Months Descriptions.

Code ID - three characters.

Defines the monthly descriptions.

OPER

Physical Condition Code.

Code ID - two characters.

Defines the physical condition of the equipment. For example, scratched.

OWNP

Warranty Claim Ownership Code.

Code ID - one character.

Defines the warranty claim ownership. For example, end customer.

PAYR

Payroll Interface.

Code ID - four characters.

Defines the payroll interface. For example, Z1-P/Y Company for Interface.

PAYT

Payment Terms.

Code ID - one character.

Defines the payment terms. For example, Payment Method no. 1.

PCDF

Remote Communications Process Index

Code ID - one.

Defines the process condition of remote jobs: For example, Processed, Rejected.

PTCH

Geocode/Territory/Patch Description.

Code ID - three characters.

Defines the geocode/Territory/Patch. For example, all territories for team *DF.

REAS

Req Date Change Reason Code.

Code ID - two.

Defines the date change reason. For example, Date Input Mistake.

RECT

* Invoice Line Type.

Code ID - two characters.

Defines the type of lines allowed on an invoice: For example, Fixed Labour Hours, Parts.

REC2

* Invoice Line Type Short Description.

Code ID - two characters.

Defines the abbreviations for the invoice lines: For example, FXD LBR, LBR HRS.

REGN

Regions.

Code ID - two characters.

Defines the regions for the workshop branch: For example, Central, Southern.

REPC

Repair Code.

Code ID - one character.

Defines the repair codes: For example: Replacement, Cleaned.

RJCD

Warranty Claims Reject Code.

Code ID - one characters.

Defines the rejects for warranty claims. For example, Invalid Account, Invalid Location.

RRES

Credit Release Reason.

Code ID - one character.

Defines the reasons for releasing the credit: For example, Payment agreed, Life threatening Problem.

RVTY

Default Return Visits.

Code ID - two characters.

Defines the reason for return visits.

SECT

M/c Section Repaired.

Code ID - three characters.

Defines the section of the machine repaired: For example, Processor Board, Paper Tray.

SRVC

* Special Revenue Categories.

*SC - Sundry Credits, *SI - Sundry Invoices.

SSCT

M/c Sub-section Repaired.

Code ID - three characters.

Defines the sub section of the machine repaired: For example, Detection Circuits, Filters.

STAT

Equipment Status.

Code ID - one character.

Defines the equipment status and owner: For example, Leased, Sold.

STA1

Statistical Family (Models).

Code ID - three characters.

Defines the statistical groups for the models: For example, Imperial measurement, Metric Measurement.

SYM1

Symptom Code 1.

Code ID - one character.

Defines the possible symptom codes for the equipment.

SYM2

Symptom Code 2.

Code ID - one character.

Defines the possible symptom codes for the equipment.

S2SE

*Serious Error Codes.

The only one defined is 01 - End of Calendar File Reached.

TEAM

Team Description.

Code ID - three characters.

Defines the workshop teams.

TRPT

Report Type.

Code ID - one character.

Defines the type of report: For example, Technical, Quotation.

TRST

* Technical Report Status.

Code ID - one character.

Defines the status of the technical report: For example, Avail, Rp Fin.

TTYP

* Remote Comms. Trans Type.

Code ID - two characters.

Defines the remote transmission type: For example, Engineer Log On, New Job Details.

TXTI

Standard document text.

Code ID - two characters.

Defines the text for standard documents. For example, Advice Note, Acknowledgement.

TXTO

Text Destination Codes.

Code ID - three characters.

Defines the people who you can send text to: For example, Sales Manager, Operator.

TYDS

* Billing Type Description.

Code ID - two characters.

Defines the type of billing allowed: For example, Fixed Service, Rental.

UNSP

* Unspecified Machine.

MACH - Unknown (Model Code).

VATC

VAT Codes And Rates.

Code ID - three characters.

Defines the VAT codes available to workshop.

VLDN

* Validation Rules.

221A - Engineer Number On SS221. 221B - Fault code on SS221.

VSTP

Scheduled Visit Profiles.

Code ID - three characters.

Defines the quantity of visits produced using the scheduled visit profile: For example, fortnightly, monthly.

WAIT

Wait Times For Sleeper Jobs.

Code ID - one character.

Defines the delay time for specific jobs, such as Incoming Transaction Monitor.

WCLC

Warranty Claim Labour Credit.

Code ID - three characters.

Defines the warranty claim labour credit.

WRFL

Warranty Claim Flag.

Code ID - one characters.

Defines warranty claim. For example, warranty parts claim allowed.

XTYP

* Text Types.

Code ID - two Characters.

Defines the type of text allowed: For example, Equipment Text, Engineer Text.

ZONE

Zone Charge Description.

Code ID - one character.

Defines the codes for the zones: For example, Inner City, Suburbs.

240P

* W240 Options.

Code ID - two character.

Defines the current status of workshop jobs: For example, Waiting for parts.

Parameter Code Selection Screen (F4)



To display this screen, on the Parameter Type Selection Screen, enter a parameter type and select **F4=Code Selection**.

Use this screen to select a parameter type from the list of existing types.

SS608	Z1 - C&T TEST COMPANY	USER GBJBAJG	14/05/96
	BIRMINGHAM BRANCH		14:09:50
Parameter Code Selection			
Parameter Type JLST * Job line status			
1	Code	Description	
█	00	00=Open	
-	01	01=Assigned	
-	02	02=Scheduled	
-	03	03=Despatched	
-	04	04=Work in progress	
-	05	05=Telephone	
-	06	06=Parts	
-	07	07=Credit Hold	
-	08	08=Complete	
-	09	09=Partial Rpt	
-	98	98=Cancelled	+
Enter selection or required code _			
1=Select			
F3=Exit F12=Previous			
08-02 82 MW KS IM II KENB20A PED129S1			

Fields:

1

Selection field. Enter 1 against a parameter ID to display its details.

Enter Selection Or Required Code

Enter one of the existing codes to display its details for update.

Enter a new code to display the screen for creating a new parameter ID.



To display the Codes/Parameter Maintenance Screen, select an existing parameter ID and press **Enter**.

Codes/Parameter Maintenance Screen 2 (Option 1)



To display this screen, select an existing parameter ID on the Parameter Code Selection Screen and press **Enter**.

Use this screen to enter the details for the selected parameter type. The fields displayed on this screen vary depending upon the parameter type selected.

```
SS000      Z1 - C&T TEST COMPANY      USER GBJBAJKG  14/05/96
              BIRMINGHAM BRANCH      14:16:46
Codes/Parameter Maintenance

Parm Type   JLST  * Job line status
Parm I.D    00                      AMENDMENT

Description.: 00=Open                Max size 30

Allow Tech.Report Entry (1/0)?  1
Escalation Active (1/0)?        1

-----
F3=Exit  F11=Delete  F12=Previous

12-10      S      MW      KS      IM      II  KENB20A  PED129S1
```

Fields:

Description

Enter the description of the parameter I.D.

User-Defined Fields

Complete these fields as appropriate.

For each parameter type you can set up extra fields which you must complete for each parameter ID defined.

For example, each parameter ID under parameter type JLST (job line status) is a status for a job line. You must include all statuses under this same type.

To specify whether you can make a technical report entry for a job line of status 00, 01, 02, and so on, you must create a field, with description, to display on the Codes/Parameter Maintenance Screen 2. You then complete this for each parameter ID.



Amend the ID and then press **Enter** to return to the previous screen. The screen displayed depends on the route taken through the option.

Codes/Parameter Maintenance Screen 3



To display this screen, on the Codes/Parameter Maintenance Screen 1, enter a parameter type of PTDS and a parameter ID, and press **Enter**.



Warning: Do not amend or delete any of the system supplied parameter type definitions unless specifically advised to do by your software support organisation.

Use this screen to define a new parameter ID for Parameter Type PTDS.

SS008	Demonstration Company CENTRAL BRANCH	USER BRERETM	1/12/93 12:19:26
Codes/Parameter Maintenance			
Parm Type	PTDS		
Parm I.D	JLST	AMENDMENT	
Description (Maximum) Size....:	30		
I.D. Size....:	2	& Format....:	C (C=Character/N=Numeric)
Description..:	* Job Line Status	Max size	30
Value required....:	-	Value Description	
(1=yes)		Value Type Description	
Character 1 req?...:	1 (1=yes/0=no)	Description	Allow Tech.Report Entry (1/0)?
Character 2 req?...:	1 (1=yes/0=no)	Description	Escalation Active (1/0)?
Character 3 req?...:	(1=yes/0=no)	Description	
Allow blanks?.....:	0 (1=yes/0=no)		
F3=Exit F11=Delete F12=Previous			

Fields:

Description (Maximum) Size

Enter the maximum length of the parameter ID description. This must be between 1 and 30.

Include a * at the start of the description to restrict the maintenance of the parameter type. You can only maintain the parameter using the Codes/Parameter Maintenance option.

ID Size

Enter the maximum length of the parameter ID. This is between one and four characters.

ID Format

Enter one of the following:

C - The parameter ID must be characters only.

N - The parameter ID must be numeric.

Description

Enter the parameter type description of up to 30 characters.

Value Required

Enter one of the following:

Blank - Not to display the value field.

1 - To specify you must enter either an absolute value or a percentage when maintaining parameter IDs of this parameter type.

Value Description

Enter the text to display alongside the field where you enter the value. The system holds details under parameter type PMVD.

Value Type Description

Enter the text to display next to the Percentage/Value flag field. The system holds details under parameter type PMVT.

Character # Req

Where # is 1 or 2 or 3. Enter one of the following:

0 or blank - Not to display the numeric field when maintaining parameter IDs of this type.

1 - To display a single numeric field when maintaining parameter IDs of this parameter type. The system holds the entry in parameter type PMC#.

Description #

Where # is 1 or 2 or 3. If you enter 1 in the Character Req field, enter a description for the field. The system holds the entry in parameter type PMC#.

Allow Blanks

Enter one of the following:

0 - If you do not want to allow blank in the Character 1 Req and Character 2 Req fields.

1 - If you do allow blanks in the Character 1 Req and Character 2 Req fields.

The rule does not apply to the Character 3 Req field of two alphanumerics.



To save the entered information and return to the previous screen, press **Enter**.

Recreate Customer Search Index



4/WOU

The customer search index is a complete index of the words, or part words, in the customer name. In addition, you can select two extra fields from the customer's details for use as search arguments. You set up the requirements for these two search fields in the Inventory Management Descriptions file, under the parameter type OTHR.

Workshop Management calls this rebuild automatically when you add new customer details. If you change any of the search criteria, or think you have corrupted the index, run this option to rebuild the index.

This batch job resets all the index data to those items selected from the customer details.



Note: Workshop Management loses any additional information entered into the index.



To run the batch job, select Recreate Customer Search Index.

Install AFI Control Data

1... 5/WOU **2...**

Use this option to set up the control data for operating the link from Workshop Management to Advanced Financial Integrator and General Ledger.

You can switch the link from the Advanced to the Basic Financial Integrator by selecting a function key. Basic mode limits General Ledger postings to the accounts set up in the Workshop Management company profile.

Description

After you select the Install AFI Control Data option, a screen displays so you can specify the installation names given to the Workshop Management and AFI files libraries. If standard names apply, leave the default values unchanged.

This option sets up the Workshop Management details in the AFI files. These include the module name, the logical files to use and the database records to access. The database identifies the files and the specific fields to make available to AFI. It also sets up the journal conditions and posting definitions for the main invoicing routines.

The four Workshop Management journals are:

- **Service job invoices** with posting rules for J-type invoices to debtors (that is invoice total of goods plus VAT), standard VAT and sales.
- **Service contract invoices** with posting rules for C-type invoices to debtors (that is invoice total of goods plus VAT), standard VAT and deferred revenue.
- **Sundry invoices/credit notes** with posting rules for S-type invoices and credit notes to debtors (that is invoice total of goods plus VAT), standard VAT and sales.
- **Deferred revenue to sales** with posting rules for C- and D-type invoices; this automatically runs with service contract invoices to post any current GL period journals to sales.

A separate update job, run as part of the invoicing process, makes the postings to Accounts Receivable.

You need to copy these journals into your test and live companies, and apply your chart of account's account codes to each posting rule.

The Workshop Management AFI extract program (FI532) is in library OSLS2P3. It takes account of Workshop Management invoicing through different files from those used for SOP invoicing. If you set the Automatically Update field to 2 in the Maintain Application option, then the extract runs automatically at each invoice run, and produces a detailed postings report.

You should take a standard AFI maintenance option, to set up the basic application parameters and the suspense account to use.

Implications

Once installation is complete, you can use the journal conditions and posting definitions for service-orientated invoicing, within the demonstration company.

These cover job invoices, sundry invoices and credit notes, service contract invoices and deferred revenue postings arising from the latter.



Warning: Only one of each of the four journals should be live at any one time, otherwise duplication of the journal's postings occurs.

You need to re-create these journal conditions and posting definitions, incorporating your own General Ledger account numbers. You can set up additional account rules, data conversion codes and templates, as necessary.

To extend the database, use a standard utility, such as DFU, to add files or fields. If you add files, amend the extract program FI532 to access the new files.

If you need to re-install the AFI control data, select the following files in the FI library, and delete all WO module records using SQL or DFU:

FIP05, 06, 07, 15, 20, 25, 30, 31, 32 and 40.

Start Workshop Sub-System



6/WOU

Use this option to start the sub-system S2BACK3, without which key functions will not operate.

Description



To start the sub-system, select Start Workshop Sub-System and press **Enter**.

The sub-system is active within seconds.



Note: Separate menu options start Automatic Call Assignment, Job Escalation and the Remote Communications Monitors.

Implications

If the sub-system is inactive, the following functions do not operate:

- Escalation Of Outstanding Calls.
- Automatic Call Assignment.
- Remote Communications.

End Workshop Sub-System

1... 7/WOU
2...

Use this option to end the sub-system.

Description



To end the sub-system, select End Workshop Sub-System and press **Enter**.

The sub-system ends after the longest sleeper delay expires.

Implications

You may have to stop the sub-system, or certain functions running with it, so you can maintain certain exclusive use files.



Warning: Automatic Call Assignment must be inactive if you are running the overnight Re-assign Undespached Calls option.

Job/Model Maintenance



8/WOU

Use this option to change the model or serial number, or both, associated with a job. The rest of the job details remain the same.

Job/Model Maintenance Screen.



To display this screen, select Job/Model Maintenance, enter a job number and press **Enter**.

Use this screen to enter the new model or serial number, or both, for the selected job number.

W0224	Z1 - UK Demonstration Company	USER GBJBANB4	21/01/98
	CENTRAL WORKSHOP		15:24:22
Job/Model Maintenance			
Job Number.....	6		
Model Number.....?	■ LTESHOW500	LCD PROJECTOR	
Serial Number.....	LML4		
F3=Exit F4=Prompt F8=Update F12=Previous			

Fields:

Job Number

This displays the selected job.

Model Number

Select the model for the job number selected.

Serial Number

Enter the serial number for the job number selected.



To save the changes and return to the menu, select **F8=Update**.

Change Branch



9/WOU

Use this option to select another branch to work in.



Select the Change Branch option.

A list of all the branches authorised to you is displayed, each with a select field alongside it.



Enter 1 against the appropriate branch and press **Enter**. You return to the menu in the branch you selected.



Note: The branch you are working in is normally displayed at the top of the screen.

Contract Initial Load



11/WOU

Use this option to load contracts, already active in a different Workshop Management application, into JBA System 21 Workshop Management.

Only use this option for contracts invoiced in full or in part by the old application. Use the standard Contracts Maintenance option to load contracts which have never been invoiced.



Note: You cannot use the Contract Initial Load option for copy-based contracts. You must enter these contracts through the normal Contracts Maintenance option, to take effect from their next renewal date. The system can then track estimates and interim billings.

Description

The Contract Initial Load option is very similar to the standard Contracts Maintenance option; refer to that section for full details.

There are two major differences:

- The system flags all equipment added to a contract as already invoiced, and does not invoice them again until you reach the next invoicing frequency period. Set this in the Contract Header Billing parameters.
- You can maintain the date From and To of the next period of time (contract invoice term) the application next invoices.

To use this option effectively, extract the following key information about each contract from the old contract application, with the normal information such as contract start date, termination date, equipment covered and corresponding inclusion dates.

Invoice Frequency

This only applies if there are any instalments within the invoice term, For example: For four instalments within an invoice term of 12 months, set the months between invoices to 3. If instalments are not applicable, set the months between invoices to the same value as the normal invoice term.

For each contract you want to load, determine what period of time to invoice next, and whether you require instalments.

The next term Starts On date must not equal the contract start date; this means that you have never invoiced the contract. If this is the case, do not load the contract using the Contract Initial Load option. Use the standard Contracts Maintenance option instead.

If the contract termination date equals the next term ends on date, you have previously fully invoiced the contract.



Note: If the date is not a multiple of the contract start date and the frequency terms, a warning

*displays. Press **Enter** or **F8** to continue.*

The warning displays in the Contract Initial Load Option, and the Contracts Maintenance option, to notify you that the next term Starts On date and the next term Ends On date may be getting out of step. However, as long as the next term starts on date is always earlier than the next term Ends On date (except in the case of a fully invoiced contract), you can enter almost any values for these two dates.

Scheduled Service Visits

If applicable, the system generates scheduled service visits from the contract start date until the contract termination date.

However, since the system never generates visits before today's date, it only creates those visits forward from today's date for each piece of equipment. You should check all visits generated for a contract.