

-
-
-
-
-

Chapter 2

Production Definition Enquiries And Reports



Item Enquiry



1/MDE



Select Items on the menu to display the first
Production Data Item Master Enquiry screen.

Production Data Item Master Enquiry Screen

1



Select Items on the menu to display the first Production Data Item Master Enquiry screen.

DB034 JW - Multiplant Phase II QA Company USER GBJBAJFW 6/03/98 15:07:23

Production Data - Item Master Enquiry

Item.....-

F3=Exit F4=Prompt F16=Item search F18=Cost presentation

5-26 SA MW KS CL IM DM II MARVIN KB PET165S1

Fields:

Item

Enter a code in the Item field.



Select **F18=Cost Presentation** on the first Production Data Item Master Enquiry screen to display the Cost Presentation window.



Press **Enter** on the first Production Data Item Master Enquiry screen to display the second screen.

Functions:

F16

Item Search. Select this function to display the Item Master Scan window.

F18

Cost Presentation. You can select the order in which cost elements appear on this report. Select this function to display the Cost Presentation window.

Cost Presentation Window (F18)

You can select the order in which cost elements appear on this report.



Select **F18=Cost Presentation** on the first Production Data Item Master Enquiry screen, or on the Production Data Item Master Report Selection screen, to display the Cost Presentation window.

DB034 E2 - Enterprise-Adu-No MPL USER GBJBASCC 11/12/97 11:50:18
Production Data - Item Master Enquiry
Item.....- _____

Cost Presentation				
Cost Element	Order	Add to	Roll to	Fixed Description
1 Relief Costs	1	—	—	Relief Costs
2 Direct Material	2	—	—	Direct Material
3 Packaging	3	—	—	Packaging
4 Utility	4	—	—	Utility
5 Labour	5	—	—	Labour
6 Set-up	6	—	—	Set-up
7 Machine	7	—	—	Machine
8 Sub-Contract	8	—	—	Sub-Contract
				1=Fixed cost

F5=Refresh F12=Previous F15=Save F16=Restore
Function key not allowed.

14-27 SA MW KS CL IM DM 11 STUD140 KB PET165S1

Fields:

Order

Select the order by entering suitable numbers against each Cost Element in the Order column.

Functions:

F15

Save. Saves you selection for another time.

F16

Restore. Restores your saved cost presentation.

Production Data Item Master Enquiry Screen 2

Most of the fields in this screen are the same as the fields in Production Details Screen 2. For more information see Production Details.



Press **Enter** on the first Production Data Item Master Enquiry screen to display the second screen.

DB034		JW - Multiplant Phase II QA Company		USER GBJBAJFW	6/03/98
					15:07:44
Item	CD-ASS1	Multiplant QA Plant 1 Top Level			(1 of 2)
Revision Level.....					
Item Type.....	M Manufactured				
Control policy					
Specification Ref....		GT Family.....			
		Low Level Code.....			
Primary Stockroom....	G1 Finished Goods J1				
Planner.....	JFW	Planner JFW			
Planning Type.....	1	Costing Route.....	A		
Planning Route.....	A	Cost Route Designate:			
Production Lead Time:	.00	Cumulative Lead Time:	.01		
Demand Policy.....	1 F/C	vs Independent Demand	Sugg.Demand Policies:		
Independent Demand...					
Forecast Comparison..					
Smoother Policy.....	0 No Smoothing				
Forecast Time Fence..	(Days)				
Seasonal Profile.....					
F3=Exit F12=Re-select Item F18=Additional Parameters					F22=Costs
1-1	SA	MW	KS	CL	IM DM II MARVIN KB PET165S1

Fields:

Item

The code previously entered.

Revision Level

Indicates the current revision level of a route/structure.

Item Type

The general classification of an item within the Production system.

Control Policy

Shows the method in which this item is issued to production. This may be: formal issue; backflush or floor stock issue.

Specification Ref

This refers to how the item is specified.

GT Family

Group Technology family. This is a user-defined classification which may be used as a selection parameter both on a Selective MRP run and MPS and MRP reports.

Low Level Code

This field is unique to this enquiry. It represents the lowest point in any item structure or work order component requirement at which this item exists. It is used by MRP and MPS to defer reviewing an item until all its potential parents have been reviewed. This identifies all possible dependent demand for this item. If the item is at the top of a multi level bill, and has no parents, the code is 0. If it is on the first level down, the code is 1. The low level code is automatically input and maintained by the system so that changes in the structure are always accurately reflected.

Primary Stockroom

Shows the primary stockroom for this item.

Planner

Shows the planner for this item.

Planning Type

Identifies the planning category of the item. Either MPS or MRP.

Costing Route

Specifies the costing route used for this item, that is, the route designated for the item in order to calculate its unit cost within a stockroom.

Planning Route

Specifies the planning route used for this item.

Cost Route Designate

The replacement route not yet active, if applicable.

Production Lead Time

The amount of manufacturing time required to produce the item from its immediate inputs and operations.

Cumulative Lead Time

The total amount of time required to produce the item.

Demand Policy

Shows one of the six demand policies currently available.

Independent Demand

The demand for the item originating from sales orders or forecasts

Sugg Demand Policies

Suggested Demand Policy. This field works in conjunction with the Independent Demand field.

Forecast Comparison

Reserved for future use.

Smoothing Policy

The policy which smoothes sale forecast demand to provide a level production schedule.

Forecast Time Fence

The time in days during which no recommendations are made by MPS or MRP to change existing production or to suggest new production.

Seasonal Profile

Used to speedily determine forecast values which display seasonal fluctuations



Select **F18=Additional Parameters** on the second Production Data Item Master Enquiry screen to display the Additional Parameters window.



Select **F22=Costs** on the second Production Data Item Master Enquiry screen to display the Cost Set Selection window.



Press **Enter** on the second Production Data Item Master Enquiry screen to display the third screen.

Functions:

F18

Additional Parameters. Select this function to display the Additional Parameters window.

F22

Costs. Select this function to display the Cost Set Selection window.

Additional Parameters (F18)



Select **F18=Additional Parameters** on the second production Data Item Master Enquiry screen to display the Additional Parameters Window.

```

DB034          JW - Multiplant Phase II QA Company      USER GBJBAJFW      6/03/98
                                           15:08:08

Item .....: CD-ASS1          Multiplant QA Plant 1 Top Level
Revision Level.....:
Item Type.....: M Manufact
Control policy .....:
Specification Ref...:

Primary Stockroom...: G1 Finishe
Planner.....: JFW Plan

Planning Type.....: 1
Planning Route.....: A
Production Lead Time: .00

Demand Policy.....: 1 F/C vs
Independent Demand...:
Forecast Comparison.:
Smoothing Policy....: 0 No Smoot
Forecast Time Fence.: (Days)
Seasonal Profile....:

Additional Parameters
Schedule Controlled..... 0 Orders
Primary Process Group...
Process Group Type.....
Major Sequence.....
Material Type..... -
Item O/H Cost Centre....
Yield Item..... (1=Yes)
Trigger Tolerance.....
Stock Run Out Policy....
Stock Run Out Route.....
Stock Run Out Date..... 0/00/00

Time Fence Policy..... 0 (0/1)
Delivery Days Basis...?..
Delivery Lead Time..... (days)

F12=Previous F15=Substitutes

F3=Exit F12=Re-select Item F18=Additional Parameters      F22=Costs

1-1  SA  MW  KS  CL  IM  DM  II  MARVIN  KB  PET165S1

```

Fields:

The fields outlined here are the same as those described in the Additional Parameters Window (F18) of Productions Details.

Cost Set Selection Window (F22)



Select **F22=Costs** on the second Production Data Item Master Enquiry screen to display the Cost Set Selection window.

```

DB034          JW - Multiplant Phase II QA Company   USER GBJBAJFW   6/03/98
                                           15:08:45
Item .....: CD-ASS1          Multiplant QA Plant 1 Top Level
Revision Level.....:
Item Type.....: M Manufactured
Control policy .....:
Specification Ref....:          GT Family.....:
                                           Low Level Code.....:
Primary Stockroom...: G1 Finished Goods J1
Planner.....: JFW   Planner JFW

PI  Cost Set Selection
PI  Item: CD-ASS1
Pr  S Process Group  Rte  Op.  C.Set  Description

De
In
Fo
Sm
Fo
Se  1=Select          Position To:
F12=Previous
F3=Exit  F12=Re-select Item  F18=Additional Parameters  F22=Costs

21-62  SA  MW  KS  CL  IM  DM  II  MARVIN  KB  PET165S1
  
```

Fields:

Item

The item code is displayed for your information only and cannot be amended.

S

You can enter the following options:

1 - Select. Enter this option to display the Item Cost Maintenance screen.

Process Group

Each process group is displayed for your information only and cannot be amended.

Rte

Route. For each process group, the route is displayed for your information only and cannot be amended.

Op

Operation. For each process group, the operation is displayed for your information only and cannot be amended.

C Set

Cost Set. For each process group, the cost set is displayed for your information only and cannot be amended.

Description

For each process group, the text description is displayed for your information only and cannot be amended.



Enter 1 in the S field on the Cost Set Selection window to display the Item Cost Maintenance screen.

Production Data Item Master Enquiry Screen 3

The fields in this screen are the same as the fields in Production Details Screen 3.
For more information see Production Details.



Press **Enter** on the second Production Data Item
Master Enquiry screen to display the third
screen.

DB034	JW - Multiplant Phase II QA Company	USER GBJBAJFW	6/03/98
			15:07:53
Item	CD-ASSI	Multiplant QA Plant 1 Top Level	(2 of 2)
Safety Stock.....	.000		
Order Policy.....	A Discrete		
Number of days Supply..			
Minimum Order Quantity..	.000		
Maximum Order Quantity..	.000		
Multiple Order Quantity..	.000		
Fixed Order Quantity...	.000		
Minor Sequence.....			
MPS/MRP Filter.....			
Material Policy.....	0 Formal issue		
F3=Exit F12=Previous			
1-1	SA	MW	KS CL IM DM II MARVIN KB PET165S1

Fields:

Safety Stock

Order Policy

Number Of Days Supply

Minimum Order Quantity

Maximum Order Quantity

Multiple Order Quantity

Fixed Order Quantity

Minor Sequence

MPS/MRP Filter

Material Policy



*Note: For more information on these fields refer
to Production Details Screen 2.*



Press **Enter** on the third Production Data Item
Master Enquiry screen to display the first screen.

Item Audit



3/MDE

Item Audit Enquiry allows you to see production changes made to items either as a result of change management or due to independent item maintenance. In order to record audit information you should enter 1 in the control policy field of Production Data Item Master Maintenance.



Select Item Audit in the enquiries list on the menu to display the first Item Audit screen.

Production Data Item Master Audit Enquiry Screen 1

-  Select Item Audit in the enquiries to display the Production Data Item Master Audit Enquiry screen.

DB030	PB - Manufacturing test company	USER GBJBAEPB	4/03/98 15:55:01
Production Data - Item Master Audit Enquiry			
Item.....-			
F3=Exit F4=Prompt F16=Item search			
5-26 ☐ ☐ KS CL IM DM II STUD140 KB PET165S1			

Fields:

Item

Enter the item you wish to enquire upon.

-  Press **Enter** to display the second Production Data Item Master Audit Enquiry screen.

Production Data Item Master Audit Enquiry Screen 2



Press **Enter** on the first Production Data Item Master Audit Enquiry screen to display the second.

DB030		PB - Manufacturing test company		USER GBJBAEPB	9/03/98
					14:57:00
Production Data - Item Master Audit Enquiry					
Item.....- PB001.1					
Test parent					
--Changed---					
Sel	Date	Time	Changed By User	Change Request Details	Rev. Level Record Type
1	9/03/98	14:54	GBJBAEPB	8/001	RevA Change
	4/02/98	15:55	GBJBAEPB		Invoked
1= Select					
F3=Exit F12=Reselect Item					
9-3 SA MW KS CL IM DM II MARVIN KB PET165S1					

Fields:

Sel

Select the line corresponding to the change you wish to enquire upon.



Press **Enter** to display the Production Data Item Master Audit Enquiry Screen 3 screen.

Production Data Item Master Audit Enquiry Screen 3



Press **Enter** on the second Production Data Item Master Audit Enquiry screen to display the third screen.

PB0030		PB - Manufacturing test company		USER GBJBAEPB	4/03/98
					15:55:24
Item	PB001.1	Test parent			
Revision Level.....				(1 of 2)	
Item Type.....	M Manufactured				
Control policy	1 Audit Only				
Specification Ref....		GT Family.....			
		Low Level Code.....			
Primary Stockroom...	FG FINISHED GOODS				
Planner.....					
Planning Type.....	0	Costing Route.....	A		
Planning Route.....	A	Cost Route Designate:			
Production Lead Time:	.00	Cumulative Lead Time:	.00		
Demand Policy.....	1 F/C vs Independent Demand	Sugg.Demand Policies:			
Independent Demand..					
Forecast Comparison..					
Smoother Policy.....	0 No Smoothing				
Forecast Time Fence..	(Days)				
Seasonal Profile.....					
F3=Exit F12=Re-select Item F18=Additional Parameters					
1-1	SR	MW	KS	CL	IM DM II STUD140 KB PET165S1

Fields:

The fields displayed are the same as those shown in the Production Details Maintenance screen, but are for your information only and cannot be amended.

Functions:

F18

Additional Parameters. Select this to display the additional parameters window. The fields contained therein are the same as those described on the Additional Parameters Window (F18) in Productions Details.



Press **Enter** on the third Production Data Item Master Audit Enquiry screen to display the fourth screen.

Production Data Item Master Audit Enquiry Screen 4



Press **Enter** on the third Production Data Item Master Audit Enquiry screen to display the fourth screen.

DB030	PB - Manufacturing test company	USER GBJBAEPB	4/03/98 15:55:30
Item	PB001.1	Test parent	(2 of 2)
Safety Stock.....	.000		
Order Policy.....	A Discrete		
Number of days Supply..			
Minimum Order Quantity..	.000		
Maximum Order Quantity..	.000		
Multiple Order Quantity..	.000		
Fixed Order Quantity...	.000		
Minor Sequence.....			
MPS/MRP Filter.....			
Material Policy.....	0 Formal issue		
F3=Exit F12=Previous			
1-1 SP MM KS CL IM DM II STUD140 KB PET165S1			

Fields:

The fields displayed are the same as those shown in the Production Details Maintenance screen, but are for your information only and cannot be amended.



Select **F12=Previous** to return to the previous screen or **F3=Exit** to choose another option.

Cost Centre Enquiry



4/MDE



Select Cost Centres in the Enquiries list on the menu to display the first Cost Centre Enquiry screen.

Cost Centre Enquiry Screen 1



Select Cost Centres in the Enquiries list on the menu to display the first Cost Centre Enquiry screen.

Fields:

Cost Centre

Enter a cost centre to enquire on.



Press **Enter** on the first Cost Centre Enquiry screen to display the second screen.

Cost Centre Enquiry Screen 2



Press **Enter** on the first Cost Centre Enquiry screen to display the second screen.

The second Cost Centre Enquiry screen is displayed containing the details of the selected cost centre. The second Cost Centre Enquiry screen contains the same fields as the second Cost Centre Maintenance screen but, in this case, the fields are for your information only and cannot be amended.

DB020		Z1 - GB Demonstration Company		USER GBJBAMS		5/12/95 15:00:46	
Cost Centre Enquiry							
Cost Centre... CC01							
Description... Cost Centre							
Department....							
		Standard				Current	
Machine	Rate/hr	13.00000				13.00000	
Labour	Rate/hr	4.65000				4.65000	
Setting	Rate/hr	5.50000				5.50000	
O/H 1	Method	E		E			
O/H 1	Rate		12.00000			12.00000	
O/H 2	Method	L		L			
O/H 2	Rate		10.00000			10.00000	
O/H 2	Value		.00000			.00000	
F3=Exit F12=Re-select Cost Centre							
01-02		SF	MM	KS	IM	II	KENB20A PET166S2

Work Station Enquiry



5/MDE



Select Work Stations in the Enquiries list on the menu to display the first Work Station Enquiry screen.

Work Station Enquiry Screen 1



Select Work Stations in the Enquiries list on the menu to display the first Work Station Enquiry screen.

The first Work Station Enquiry screen is displayed containing the Work Station field. Enter a work station code.



Press **Enter** on the first Work Station Enquiry screen to display the second screen.

Work Station Enquiry Screen 2



Press **Enter** on the first Work Station Enquiry screen to display the second screen.

The second Work Station Enquiry screen is displayed containing the same fields as the second Work Station Maintenance screen.

DB005	Z1 - GB Demonstration Company	USER GBJBAMS	5/12/95
			15:06:47
Work Station Enquiry			
Work Station.. WS01			
Description... Work Station 01			
Department....			
Foreman.....	Queue Time.	Std. Efficiency	%
	Max Length	Std Length	Max Capacity
Shift 1.....	8.0	8.0	8.0000
Shift 2.....			8.0000
Shift 3.....			
Duration Calculation Basis (Default): 3 M/C + Run Labour + Set Up Time			
Shift Profile (Default).....:			
Default Shift Profile Capacity Factor...:		Max...	.00
		Std...	.00
Cost Centre... CC01 Cost Centre			
Calendar Code. 01			
F3=Exit F12=Re-select Work Station F20=Daily Profile			
01-02	SP	ML	KS
IM	II	KENB20A	PET166S2

Functions:

F20

Daily Profile. You can add and amend the daily shift profiles and capacities. For more information see Profile Window (F20).

Work Centre Enquiry



6/MDE



Select Work Centres in the Enquiries list on the menu to display the first Work Centre Enquiry screen.

Work Centre Enquiry Screen 1




Select Work Centres in the Enquiries list on the menu to display the first Work Centre Enquiry screen.

The first Work Centre Enquiry screen is displayed containing the Work Centre field. Enter a work station code.



Press **Enter** on the first Work Centre Enquiry screen to display the second screen.

Work Centre Enquiry Screen 2



The second Work Centre Enquiry screen is displayed containing the same fields as the second Work Centre Maintenance screen.

```

DB021                Z1 - GB Demonstration Company      USER GBJBAMS      5/12/95
                                                           15:10:04

Work Centre Enquiry

Work Centre..... ASSEM

W/Stn   Description                                W/Stn   Description
ASEM    Assembly
ASSV    Assemble Car Boot
AUTO    Auto Process for Car Boot Manf

-----
F3=Exit   F12=Re-select Work Centre

00-02    SF      MW      KS      IM      II  KENB20A  PET166S2

```

Routes/Structures Enquiry



7/MDE



Select Routes/Structures on the menu to display the Routes/Structures Enquiry screen.

Routes/Structures Enquiry Screen



Select Routes/Structures on the menu to display the Routes/Structures Enquiry screen.



Note: If the Configurator is being used, additional details about the Configurator route are displayed.

DB630	Z1 - GB Demonstration Company	USER GBJBAMS	5/12/95 15:58:38
Routes/Structures Enquiry			
Parent Item	?..		
Route	?..	_	
Quantity.....		(Zero assumes Economic Order Qty.)	
Include shrinkage..	@	(1=Yes)	
As at.....	5/12/95		
Ignore Effectivity.	@	(1=Yes)	
F3=Exit F4=Prompt F16=Item search			
06-25	SF	MW	KS IM II KENB20A PET166S2

Fields:

Parent Item

Enter the parent item code of the process group code to display.

Quantity

Enter the lot size for this enquiry. This increases or decreases the dependant material requirements so that the effect of changes can be seen. If left blank the system assumes the EOQ as specified in route/component maintenance.

Include Shrinkage

This option is given to include or exclude material shrinkage.

Enter 1 if shrinkage is to be included, otherwise leave blank.

As At

Enter the control date for this enquiry. The effective start and stop dates are compared with this control date. Any components in the structure which are not effective at this date are excluded. The default is the current date.

Ignore Effectivity

To ignore effectivity enter 1; the whole structure is seen. Otherwise leave blank.



Press **Enter** on the Routes/Structures Enquiry Screen to display the Process Route Header Enquiry screen.

Process Route Header Enquiry Screen

This screen is the same as the Process Route Header Maintenance screen, except that all the fields are for your information only and cannot be amended. Refer to the Process Route Header Maintenance screen for more information.



Press **Enter** on the Routes/Structures Enquiry Screen to display the Process Route Header Enquiry screen.

Fields:

Parent Item/Group

Route

Type

Process Group Type

Receiving Stockroom

Cost Route

Unit Of Measure

Cost Route Designate

Standard Lot Size

Planning Route

Economic Order Quantity

Balancing Quantity

Route Validation

Output Validation

Revision Level

Effective From Date

Effective To Date

Reference

Filler Item



If Multi-Sourcing is being used, select **F16=Route Resources** display the Route Critical Resources Enquiry screen. For more information see the Route Critical Resources Maintenance screen. The fields are for your information only and cannot be amended.



Press **Enter** to display the Process Route Enquiry Inputs screen. For more information see the Process Route Maintenance Inputs screen.

The fields are for your information only and cannot be amended.

Functions:

F16

Route Resources. If Multi-Sourcing is being used, this function is displayed. Select this function to display the Route Critical Resources Enquiry screen.

F21

Text. Allows you to enter or edit additional text about the process. For more information see Additional Text.

Route Structures Audit



8/MDE

This is a similar enquiry to Item Audit. The review details screen shows the full audited route structure. An additional summary screen is featured showing the route details including operations, inputs, outputs and alternate operations that have been altered during a maintenance session.



Select Route Structures Audit from the list of enquiries to display the Routes Structures Audit Enquiry screen.

Route Structures Audit Enquiry



Select Route Structures Audit from the list of enquiries to display the Routes Structures Audit Enquiry screen.

DB630A	PB - Manufacturing test company	USER GBJBAEPB	4/03/98
Routes/Structures Audit Enquiry			15:58:27
Parent Item?.. █			
Route?.. _			
F3=Exit F4=Prompt F16=Item search			
6-25	SR	MD	KS CL IM DM II STUD140 KB PET165S1

Fields:

Parent Item

Enter the parent item you wish to enquire upon.

Route

Enter the route of the parent item.



Press **Enter** to display the Routes Structures Audit Enquiry Header Details screen.

Routes Structures Audit Enquiry Header Details Screen



Press **Enter** on the Routes Structures Audit Enquiry screen to display the Routes Structures Audit Enquiry Header Details screen.

DB630A		PB - Manufacturing test company		USER GBJBAEPB	4/03/98
					15:58:45
Routes/Structures Audit Enquiry - Header Details					
Parent Item A#1					
Route A					
--Changed--					
Sel	Date	Time	By User	Change Request Rev.	Record Type
1	27/01/98	8:44:54	GBJBAEPB	3/001	Invoked
1=Review Details 2=Route Structure Enquiry					
F3=Exit F12=Reselect Item/Route					
Bottom					
8-3 SP MW KS CL IM DM II STUD140 KB PET165S1					

Fields:

Sel

Option. Select the type of enquiry you want to see against any line. You can enter one of the following options:

1 - Review Details. Use this to display the Routes Structures Audit Enquiry Review Details Screen (Option 1).

2 - Route Structure Enquiry. Use this to display the Routes Structures Audit Enquiry Screen (Option 2).



Select **1=Review Details** to display the Routes Structures Audit Enquiry Review Details Screen (Option 1).



Select **2=Route Structure Enquiry** to display the Routes Structures Audit Enquiry Screen (Option 2).

Routes Structures Audit Enquiry Review Details Screen (Option 1)

-  Select **1=Review Details** on the Routes Structures Audit Enquiry Header Details screen to display the Routes Structures Audit Enquiry Review Details Screen (Option 1).

DB630A		PB - Manufacturing test company		USER GBJBAEPB	4/03/98 15:58:58
Routes/Structures Audit Enquiry - Review Details				Changed	
Parent Item A#1				Date.: 27/01/98	
Route A				Time.: 8:44:54	
				User.: GBJBAEPB	
				Change Request	Record Type
Opsq	Iseq	Oseq	Description/Item	Details	
10			Operation 10		Invoked
10	10		ABCD		Invoked
20			Operation 20		Invoked
20	10		CAB		Invoked
30			Operation 30	3/001 Add	
					Bottom
F3=Exit F12=Reselect Item/Route F18=Route Structure Enquiry					
1-1 SR MW KS CL IM DM II STUD140 KB PET165S1					

Fields:

This screen shows more detailed information of the changes made to operations, inputs and outputs.

Functions:

F18

Route Structure Enquiry. Displays the Routes Structures Audit Enquiry Screen (Option 2).

-  Select **F2=Reselect Item/Route** to process another Routes Structures Audit enquiry.

Routes Structures Audit Enquiry Screen (Option 2)



Select either **F18=Route Structure Enquiry** on the Route Structures Audit Enquiry Review Details screen or **2=Route Structure Enquiry** on the Routes Structures Audit Enquiry Header Details screen to display the Routes Structures Audit Enquiry Screen (Option 2).

DB651A		PB - Manufacturing test company		USER GBJBAEPB		4/03/98 15:59:47	
Parent Item/Group.....	A#1	A#1					
Route.....	A	Type.. 0 Discrete Route					
Route Revision Level...							
Route Classification....	MH						
Control Policy.....	2	Change Controlled					
Process Group Type.....							
Receiving Stockroom.....	FG	Cost Route..	(1=Yes)	Planning Route..	(1=Yes)		
Standard Lot Size.....	1.000		for Primary Co-Product:				
Economic Order Quantity.....	1.000		/				
Balancing Quantity.....							
Route Validation.....							
Unit Of Measure.....							
Effective From Date.....	0/00/00		Effective To Date..	99/99/99			
Reference.....							
F3=Exit F12=Reselect Route/Item F21=Text							
1-1 SA MW KS CL IM DM II STUD140 KB PET165S1							

Fields:

This screen shows details extracted from Process Route Header Maintenance. The fields are for information only and cannot be amended.

Functions:

F21

Text. Use this to display text entered for the route structure.



Select **F12=Reselect Item/Route** to return to the Routes Structures Audit Enquiry screen.

Text Enquiry



9/MDE



Select Text on the menu to display the Text Inquiry screen.

TX003	Z1 - GB Demonstration Company	USER GBJBAMS	5/12/95
Text Inquiry			14:38:55
Major Type	_____		
Sub-Type	■		
File Key	_____		
F3=Exit F4=Prompt			
04-15	SF	ML	KS IM II KENB20A PET166S2

Fields:

Major Type

Enter the required major type.

Sub-Type

Enter the required sub-type.

File Key

Enter the item code, cost centre code, work centre code etc. whose text you wish to enquire on.




Press **Enter** to display the second Text Enquiry screen. This screen contains the same fields as the second Text Maintenance screen.

Indented Enquiry

10/MDE

It is appreciated that some structures are relatively simple using only perhaps one or two levels. Others may be complex using many levels and large numbers of items.

Standard Structure Example:



Enquiry Types

When making an Indented enquiry it is necessary to decide:

- (a) The level at which the enquiry is to be made
- (b) The direction of the enquiry

The direction may be downwards (explosion) from the parent or upwards (implosion) from the input. The upwards enquiry is also called a where-used enquiry.



Note: Some items in a multi level structure may be parents and inputs at the same time.

It is therefore possible to make enquiries on these items in both directions. Both kinds of enquiry can be made with or without shrinkage.

Shrinkage

Shrinkage is expressed as the percentage loss of material which can take place on an operation or on an input. The Indented Enquiry can be made in the following ways:

- Structures without shrinkage (Downwards)
- Structures with shrinkage (Downwards)
- Where-used without shrinkage (Upwards)
- Where-used with shrinkage (Upwards)

The type of enquiry being made is shown at the top of the enquiry screen, but normally shrinkage is apparent from the display of the decimal quantities.



Note: Shrinkage is compounded if both types are present and also if there is shrinkage on more than one operation.



Select Indented Enquiry in the Enquiries list on the menu to display the Indented Inputs Enquiry screen.

Indented Inputs Enquiry Screen



Select Indented Enquiry in the Enquiries list on the menu to display the Indented Inputs Enquiry screen.

```

DB007                Z1 - GB Demonstration Company      USER GBJBAMS      5/12/95
                                           15:54:03

Indented Inputs Enquiry

Item.....?..: _____
Process Group.?..: _____
Route.....?..: _

Inputs Route..?..: 2                1=Costing Route      2=Planning Route
                                           3=Entered Route

Quantity.....: _____ .000 (Zero assumes Economic Batch Size)

Enquiry Type.....: 1                1=Explosion without shrinkage
                                           2=Explosion with shrinkage
                                           3=Where-used without shrinkage
                                           4=Where-used with shrinkage

As at.....: 5/12/95
Ignore Effectivity: _                1=Yes

-----
F3=Exit      F4=Prompt      F16=Item Search

05-22      SF      MW      KS      IM      II      KENB20A      PET166S2

```

Fields:

Item

Enter the item for which an indented display is required. The item can be a parent for which an indented exploded list is required, or an input item for which an indented where-used retrieval is desired.

Process Group

Enter the relevant process group if the item is a co-product, and the process group route is to be used to determine input values.

Route

Enter the route code required.

For an Explosion enquiry (Enquiry type 1 or 2) this extracts all the inputs used on this route.

For Where-Used enquiries (Enquiry Type 3 or 4) all occurrences of this item are displayed for this route.

Inputs Route

Enter the route code that you want the procedure to use when exploding beyond the immediate inputs or imploding beyond the immediate parents. Choose from:

- 1 - For the costing route.
- 2 - For the planning route.

3 - For the route chosen above.

Quantity

Enter the batch quantity to be used as the basis for this enquiry. Material requirements are calculated from this quantity.

If a blank is left the system uses the economic order quantity specified on the route/input maintenance for this route.

Enquiry Type

You can perform four types of indented enquiry.

- 1 - For structure enquiry without shrinkage.
- 2 - For structure enquiry with shrinkage.
- 3 - For input where-used enquiry without shrinkage.
- 4 - For input where-used enquiry with shrinkage.

The With Shrinkage options show material requirements based on the occurrence of planned operational and material shrinkage in the selected routes.

As At

Enter the control date for this enquiry. All effective inputs at this date are displayed.

For Where-Used enquiries only parents in which this input is effective are displayed.

A default of the current date is displayed.

Ignore Effectivity

You can view all inputs regardless of their effectivity dates by selecting this option.

Enter 1 to ignore As at date; otherwise leave blank.

Functions:

F16

Item Search. You can search the database for an item. For more information see Item Master Scan Window One (F16).



Press **Enter**. The Indented Structure Enquiry screen is displayed.

Indented Structure Enquiry Screen



The Indented Structure Enquiry screen is displayed.

The Indented Structure Enquiry screen displays the detail for the selected enquiry - structures without shrinkage.

DB007		Z1 - GB Demonstration Company		USER GBJBAMS	5/12/95 15:54:35
Indented Structure Enquiry					
Parent: MS001		Product A			
Quantity: 100.000		UOM: EA Route: 1 As at 5/12/95 * Excludes shrinkage			
Receive into Stockroom FG		T			
Level	Input	St	Description	P	Quantity UOM
1	RAM01	RM	Raw material 1	P	234.000 EA
1	RAM02	RM	Raw material 2	R	500.000 EA
1	RAM03	RM	Raw material 3	P	200.000 EA
1	RAM04	RM	Raw material 4	P	150.000 EA
Item: MS001		Proc.Group:		Route: 1 Qty: 100.000	
Input Route: 2		(1=Costing Route 2=Planning Route 3=Entered Route)			
Enquiry Type: 1		(1 or 2 Parent Explosion - 3 or 4 Input Where-Used)			
F3=Exit F4=Prompt		F12=Previous F16=Item Search			
21-08 SF		MW KS IM II KENB20A PET166S2			

Fields:

Level

This is the level code of the input in the exploded structure relative to the selected parent item, which is assumed level zero.

Stockroom

This is the issuing stockroom for the input.

Type

This is the item type as configured in the Production Item Master file.

Quantity Req'd

This is the quantity required of the input to make the selected batch quantity of the parent.

It may or may not include shrinkage, depending on your Enquiry Type selection (this example does not).

Unit Of Measure

This is the issuing unit of the input from the stockroom.



Note: The lower part of the screen allows you to re-select the enquiry without you having to return to the Selection screen.

The fields are:

- Item
- Process group
- Route
- Quantity
- Input route
- Enquiry type

These fields are used as explained earlier. But note for Enquiry Type:

- If a 3 or 4 are entered in the Enquiry Type field, the Where-Used option is selected. In this case, the elected item must be an input and the default item may need to be changed. The Indented Where-Used Enquiry screen is displayed.
- If a Structure option is chosen check which routes are available by using the prompt in the Route field.

Functions:

F16

Item Search. You can search the database for an item. For more information see Item Master Scan Window One (F16).

Indented Where-Used Enquiry Screen



This screen is displayed if either of the Input Where-Used enquiry types are selected.



Note: Enquiry Type 3 or 4 from this menu always displays all levels for the item with this particular route - i.e., one route all levels.

DB007		Z1 - GB Demonstration Company		USER GBJBAMS	5/12/95 15:55:23
Indented Where-Used Enquiry					
Input:	RAM01	Raw material 1			
Quantity:	100.000	UOM:	EA	Route: 1	As at 5/12/95 * Excludes shrinkage
Issue from Stockroom:	RM	T			
Level	Parent Item	St	Description	P	Quantity UOM
1	CO001	FG	Co-product process group	M	234.000 EA
1	MS001	FG	Product A	M	234.000 EA
1	MS002	FG	Product B	M	234.000 EA
1	MS003	FG	Co-product process group	M	234.000 EA
1	MS005	FG	Product D	M	234.000 EA
Item: <u>RAM01</u> Prc.Group: _____ Route: <u>1</u> Qty: <u>100.000</u> Input Route: <u>2</u> (1=Costing Route 2=Planning Route 3=Entered Route) Enquiry Type: <u>3</u> (1 or 2 Parent Explosion - 3 or 4 Input Where-Used) F3=Exit F4=Prompt F12=Previous F16=Item Search 21-08 <u>SF</u> MW KS IM II KENB20A PET166S2					

Fields:

Quantity

This is the quantity of this input required to make the selected batch size of the corresponding parent. Because of the ability to be able to calculate back to the final parent size from a given input size, it is possible to calculate the overall material requirements of a low level input to produce a given batch size of a final parent.

Level

This is the relative level of the parent (see Parent Item) to the chosen input. The input of the parent is level 0, the parent is level 1, the parent of the parent is level 2 etc.; each parent is indented one position.

Parent Item

All the parent items are displayed - not just the immediate.

St

Stockroom. This is the receiving stockroom of the input.

P

Parent Type. This is the type of the parent as configured in the Production Item Master file.

Quantity

This is the required quantity of the input needed to make the selected batch quantity of the parent. This may or may not include shrinkage - it depends on your Enquiry Type choice.

UOM

Unit Of Measure. This is the issuing unit of measure of the input from the stockroom.

Functions:

F16

Item Search. You can search the database for an item. For more information see Item Master Scan Window One (F16).

Inputs Where-Used Enquiry

This option displays where the item is used for all routes at this level - i.e., all routes one level.



11/MDE



Select Inputs Where-Used in the Enquiries list on the menu to display the first Input Where-Used Enquiry screen.

Input Where-Used Enquiry Screen 1



Select Inputs Where-Used in the Enquiries list on the menu to display the first Input Where-Used Enquiry screen.

Fields:

Input

Enter the input (component item) for which you wish to display where-used details. This enquiry is single level, and identifies all immediate parents of the item.

As At

Enter the control date for this enquiry. The effective start and stop dates of the input are compared with this control date. Parent routes not effective at this date are excluded.

Ignore Effectivity

You can view all parents regardless of the input effectivity by selecting the option.



Press **Enter** to display the second Input Where-Used Enquiry Screen.

Functions:

F16

Item Search. You can search the database for an item. For more information see Item Master Scan Window One (F16).

Input Where-Used Enquiry Screen 2



Press **Enter** on the first Input Where-Used Enquiry screen to display the second screen.

DB008	Z1 - GB Demonstration Company	USER GBJBAMS	5/12/95
Input Where-Used Enquiry			15:57:41
Input : RAM03		Raw material 3	
UOM : EA	Level 1	Effectivity Ignored	
Parent Item	Rte	Oper Description	Quantity Fix UOM
C0001	1	10 Operation 10	2.000 EA
MS001	1	10 Operation 10	2.000 EA
MS002	1	10 Operation 10	2.000 EA
MS003	1	10 Operation 10	2.000 EA
MS005	1	10 Operation 10	2.000 EA
MS001	2	10 Operation 10	2.000 EA
MS002	2	10 Operation 10	2.000 EA
MS002	3	10 Operation 10	2.000 EA
Input.....: <u>RAM03</u> As at.: <u>5/12/95</u> 1 1=Ignore Effectivity			
F3=Exit F4=Prompt F16=Item search			
23-15 <u>SP</u> MW KS IM II KENB20A PET166S2			

Fields:

Level

This indicates the lowest level in any structure or work order at which the input currently exists.

Route Code

This is the route code of the parent which calls up this input.

Operation

This is the sequence number in the parent route at which the input is issued.

Quantity

This is the quantity required of the input used at the specified operation to make the standard lot size of the parent route.

Unit Of Measure

This is the production unit of measure of the parent route.



Note: The lower part of the screen can be used to select another input.

Functions:

F16

Item Search. You can search the database for an item. For more information see Item Master Scan Window One (F16).

Shift Profiles Enquiry



12/MDE



Select Shift Profiles in the Enquiries list on the
Production Definition Enquiries & Reports menu.

Shift Profile Enquiry Screen 1

The first Shift Profile Enquiry screen is displayed containing the Shift Profile Code field. Enter the required shift profile code.



Press **Enter** on the first Shift Profile Enquiry screen to display the second screen.

Shift Profile Enquiry Screen 2



Press **Enter** on the first Shift Profile Enquiry screen to display the second screen.

DB141	Z1 - GB Demonstration Company	USER GBJBAMS	5/12/95 15:03:22		
Shift Profile Enquiry					
Profile Code... R0					
Description.... Shift Profile for 10 Hours As At... 0/00/00					
No.	Start Time	Finish Time	Effective From Date	Effective To Date	Comment
1	7:00	13:00	0/00/00	99/99/99	6 Hours
2	13:00	19:00	0/00/00	99/99/99	6 Hours
F3=Exit F12=Previous PRINT=Report					
06-60 SF MW KS IM II KENB20A PET166S2					

Fields:

As At

You can enter the effectivity date in this field.

Labour Grades Enquiry



13/MDE



Select Labour Grades in the Enquiries list on the menu to display the first Labour Grade Enquiry screen.

Labour Grade Enquiry Screen 1



Select Labour Grades in the Enquiries list on the menu to display the first Labour Grade Enquiry screen.

Fields:

Labour Grade

Enter a labour grade code.



Press **Enter** on the first Labour Grade Enquiry screen to display the second screen.

Labour Grade Enquiry Screen 2



Press **Enter** on the first Labour Grade Enquiry screen to display the second screen.

GB254	Z1 - GB Demonstration Company	User	GBJBAMS	5/12/95
				15:19:27
Labour Grade Enquiry				
Labour Grade... A1				
Description.... Mechanics				
Effective Date.. 0/00/00				
Expiry Date.... 99/99/99				
F3=Exit F12=Previous F20=Grade Rates				
01-02	SP	MM	KS	IM II KENB20A PET166S2

Fields:

Labour Grade

This field is displayed for your information only and cannot be amended.

Description

This field is displayed for your information only and cannot be amended.

Effective Date

This field is displayed for your information only and cannot be amended.

Expiry Date

This field is displayed for your information only and cannot be amended.

Functions:

F20

Grade Rates. For more information see Labour Grade Rate Maintenance Screen (F20).

Subcontractors Enquiry



14/MDE



Select Subcontractors in the Enquiries list on the menu to display the first Subcontractor Enquiry screen.

Subcontractor Enquiry Screen 1



Select Subcontractors in the Enquiries list on the menu to display the first Subcontractor Enquiry screen.

DB287	Z1 - GB Demonstration Company	User	GBJBAMS	5/12/95
Subcontractor Enquiry				15:44:51
Item.....?.. _____				
Route.....?.. _				
Operation.....?.. ____				
Subcontractor.....?.. _____				
F3=Exit F4=Prompt F16=Supplier Enquiry				
05-24	SP	MW	KS	IM II KENB20A PET166S2

Fields:

Item

Enter parent item for which a production route has been defined, and on which at least one operation has been flagged as subcontracted.

Route

Enter the route on which an operation has been flagged as subcontracted.

Operation

Enter the operation sequence defined as subcontract.

Subcontractor

Enter subcontractor to display.



Press **Enter** on the first Subcontractor Enquiry screen to display the second screen.

Functions:

F16



*Note: Before selecting **F16=Supplier Enquiry**, ensure that there are entries in the Item, Route and Operation fields.*

Supplier Enquiry. To search for a supplier to be entered in the Subcontractor field first select **F16=Supplier Enquiry**. The Supplier Search window is displayed

containing the Search Word field. Enter a word in this field and press Enter. The Supplier Selection window is displayed. For more information see Supplier Selection Window.

Subcontractor Enquiry Screen 2



Press **Enter** on the first Subcontractor Enquiry screen to display the second screen.

The second Subcontractor Enquiry screen is displayed containing the same fields as the second Subcontractor Maintenance screen.

Item Report



21/MDE

A report can be generated which contains details of the current setting of the Item Master file.



Select Items in the Reports list on the menu to display the Production Data Item Master Report Selection screen.

```
DB019P          Z1 - GB Demonstration Company  USER GBJBAMS  5/12/95
                                     14:58:19

Production data  -  Item master report selection

To produce a report showing a range of Items key in BOTH fields.
To produce a report for a specific Item key in the FROM field.
To produce a report for all Items leave BOTH fields blank.

Item range:      From...?...  █
                To.....?...

Print production details..  _  1=Yes

Print costing details..... 1  0/blank = Print no Costs
                                1 = Standard Costs only
                                2 = Entered Cost Set Range only
                                3 = Standard and Entered Cost Set Range
                                4 = All Costs

Cost set range: From.....
                To.....

F3=Exit  F4=Prompt  F10=Cost presentation

09-30    SP      MW      KS      IM      II  KENB20A  PET166S2
```

Fields:

Item Range From/To

Enter item codes in the From and To fields to report a range of items. Enter an item code in the From field to report one item. Leave both fields blank to report all the items.

Print Production Details

This option is given to include item details as entered via Production Details Maintenance in addition to costing information.

0 (or blank) - No. Exclude production costs from the report.

1 - Yes. Include all current production data for the item in the report.

Print Costing Details

The report may be run using a combination of standard and/or non standard cost sets.

0 (or blank) - Print No Costs.

1 - Standard Costs Only. For standard costs to be reported.

2 - Entered Cost Set Range Only. For a cost set range, defined in the Cost Set Range From/To fields, to be reported.

3 - Standard And Entered Cost Set Range. For standard costs and a cost set range, defined in the Cost Set Range From/To fields, to be reported.

4 - All Costs. For all costs to be reported.

Cost Set Range From/To

If non standard cost set(s) are required enter a From and To range; this is mandatory for non standard cost set only report. Enter the same cost set in the From and To fields to use one set only. Standard costs cannot be requested.

Functions:

F18

Cost Presentation. You can select the order in which cost elements appear on this report. Select this function to display the Cost Presentation window.



Press **Enter** to generate the report.

Cost Centre Report

22/MDE

This report gives details of the current setting of the Cost Centre file.



Select Cost Centres in the Reports list on the menu to display the Cost Centre Report screen.

DB024P	Z1 - GB Demonstration Company	USER GBJBAMS	5/12/95
15:01:14			
Production Data - Cost Centre Report Selection.			
To produce a report showing a range of Cost Centres key in BOTH fields.			
To produce a report for a specific Cost Centre key in the FROM field.			
To produce a report for all Cost Centres leave BOTH fields blank.			
From		To	
Select....?..			
F3=Exit F4=Prompt			
15-27	SR	ML	KS
IM	II	KENB20A	PET166S2

Fields:

Select From/To

Enter cost centre codes in the From and To fields to report a range of cost centres.
Enter a cost centre code in the From field to report one cost centre. Leave both fields blank to report all the cost centres.



Press **Enter** to generate the report.

Work Station Report



23/MDE



Select Work Stations in the Reports list on the menu to display the Work Station Report Selection screen.

```
DB009P          Z1 - GB Demonstration Company    USER GBJBAMS    5/12/95
                                           15:07:11

Production Data  -  Work Station Report Selection

To produce a report showing a range of Work Stations key in BOTH fields.
To produce a report for a specific Work Station key in the FROM field.
To produce a report for all Work Stations leave BOTH fields blank.

                From          To
Select....?..  _____  _____
Sequence..... _ (1=Cost Centre 2=Department 3=Work Station)
Type..... _ (1=Detail 2=Summary)

F3=Exit F4=Prompt

14-27  SF  MW  KS  IM  II  KENB20A  PET166S2
```

Fields:

Select From/To

Enter work station codes in the From and To fields to report a range of work stations. Enter a work station code in the From field to report one work station. Leave both fields blank to report all the work stations.

Sequence

Enter:

- 1 - Cost Centre. To sequence work stations within cost centre.
- 2 - Department. To sequence work stations within department.
- 3 - Work Station. To sequence work stations on their own.

Type

Enter:

- 1 - Detail. To report full details of each work station.
- 2 - Summary. To report department, cost centre and shop calendar details for each work station.



Press **Enter** to generate the report.

Work Centre Report

1...
2...

24/MDE



Select Work Centres in the Reports list on the menu to display the Work Centre Report Selection screen.

DB026P	Z1 - GB Demonstration Company	USER GBJBAMS	5/12/95
			15:10:25
Production Data - Work Centre Report Selection			
To produce a report showing a range of Work Centres key in BOTH fields.			
To produce a report for a specific Work Centre key in the FROM field.			
To produce a report for all Work Centres leave BOTH fields blank.			
		From	To
Select....?..		_____	_____
F3=Exit F4=Prompt			
15-27	SR	ML	KS
IM	II	KENB20A	PET166S2

Fields:

Select From/To

Enter work centre codes in the From and To fields to report a range of work centres. Enter a work centre code in the From field to report one work centre. Leave both fields blank to report all the work centres.



Press **Enter** to generate the report.

Routes/Structures Report

A report can be generated which contains information about the route/structure of selected items. The report displays whether or not the route is a planning route.



25/MDE



Select Routes/Structures in the Reports list on the menu to display the Route/Structure Report Selection screen.

```

DB010P          E3 - Enterprise-Adv-with MPL      USER GBJBAJFW  13/02/98
                                           14:24:22

Route/Structure Report Selection

Print Items In The Range From.?.  (blank for first)
                               To.?.  (blank for last)

Print Route.....?. 
OR Print All Routes.....  1

Use Group Route..... 
Process Group.....?. 

Quantity.....  (Zero assumes Economic order qty)

Include Shrinkage.....  0

Effective As At..... 13/02/98

Ignore Effectivity.....  0
Include Input References.....  0

0=No 1=Yes
F3=Exit F4=Prompt

-----
5-35 SR MW KS CL IM DM II EDN400R KB PET165S2
  
```

Fields:

Print Items In The Range From/To

Enter the range of parent items that you want in the report. Leaving both blank prints all parents.

Complete one or the other of the next two entries:

Print Route

Enter the code of the single route you want included in the report.

Or Print All Routes

Enter 1 for all routes to be included.

Use Group Route

If the parent item is a co-product on a process group, the process route for the group may be used instead of the item's own route. The route used is that previously entered.

Process Group

Enter the item code for the process group required.

Quantity

Enter the quantity that you want the single level explosion based on; the material requirements are calculated on this basis. Leave blank for the EOQ configured in parent/route maintenance.

Include Shrinkage

You can optionally base the material requirements on any planned shrinkage configured at operation or input level on the selected routes.

0 - To ignore shrinkage.

1 - To include shrinkage; in this case the effect on material requirements is seen.

Effective As At

Enter the date to be used to trap the effective component configuration of the single level item structure. This field defaults to the current date.

Ignore Effectivity

Enter 1 if the effectivity date is to be ignored. The default is 0.

Include Input Reference

0 - Do not include input reference details on the report. This is the default.

1 - Enter this to include any input reference information that may exist.



Note. For more detailed information about input references, see Routes/Structures.



Press **Enter** to generate the report.

Text Report



26/MDE



Select Text in the Reports list on the menu to display the Text Report Select Parameters screen.

TX005	Z1 - GB Demonstration Company	USER GBJBAMS	5/12/95
Text Report - Select Parameters			14:42:54
Major Type	_____		
Sub-Type	_____	(Blank for all)	
From File Key	_____	(Blank for First Key)	
To File Key	_____	(Blank for Last Key)	
F3=Exit F4=Prompt			
04-20	SR	MM	KS IM II KENB20A PET166S2

Fields:

Major Type

Enter the text major text type you want to report on.

Sub-Type

Enter the text sub-type you want to report on. If you leave this field blank, it defaults to all sub-types.

From File Key

Enter the first in the range of item codes, cost centre codes, work centre codes etc. that you want to report on. If you leave this field blank, it defaults to the First Key.

To File Key

Enter the last in the range of item codes, cost centre codes, work centre codes etc. that you want to report on. If you leave this field blank, it defaults to the Last Key.



Press **Enter** to generate the report.

Indented Inputs Report

1... 27/MDE **2...**

This report prints a fully indented input list for selected parent items.

It is possible to explode through all identified structure levels to produce a complete list for all selected parent items. Additional selection and control criteria can be used to provide different views of the indented list.



Select Indented Inputs in the Reports list on the menu to display the Indented Inputs Report screen.

DB074	Z1 - GB Demonstration Company	USER GBJBAMS	5/12/95 15:56:09
Indented Inputs Report			
From Item.....?	_____	(Blank for start of file)	
To Item.....?	_____	(Blank for end of file)	
Process Group..?	_____		
Route	_____ / _____	or type 'ALL' for all Routes	
Component Route...	1	(1=Planning 2=Costing 3=Entered route)	
Batch Quantity....	_____	(Blank for Economic Order Qty)	
Costing Method....	3	(1=Standard 2=Entered Cost Set 3=No Costing)	
Cost Set.....	_____		
Inc.shrinkage....	1	(1=Yes)	
Material Costs....	1	(1=Production 2=Inventory)	
Operation summary.	1	(1=Yes)	
As at	5/12/95		
Ignore effectivity	_	(1=Yes)	
F3=Exit F4=Prompt F18=Cost presentation			
06-20	SP	MW	KS IM II KENB20A PET166S2

Fields:

From/To Item

Enter the range of parent items required in the report. Leave blank for all.

Process Group

Enter the process group to be used.

Route

Enter the route code to be used for the first level explosion of input items and the calculation of this level production costs for the selected products.

To select all routes, tab to the next prompt and enter ALL.

Batch Quantity

Enter the batch quantity to be costed. If left blank, the EOQ configured for each selected item/route is used.

The batch quantity determines all lower level input usage, and be used to amortise fixed costs against when developing a unit cost for all selected items. Fixed costs are:

Set-up

Fixed time, operation, labour and machine costs

Fixed user configured costs

Fixed overheads.

Costing Method

Enter :

- 1 - To base costs on standard rates.
- 2 - To base costs on current rates.
- 3 - For no costing.

Inc Shrinkage

Include Shrinkage. Enter 1 to include shrinkage in material requirements, otherwise leave blank.

Material Costs

You can enter the following options:

- 1 - To use Production costs (as above).
- 2 - To use the cost set in Inventory

Operation Summary

Enter 1 to include operation details on the report.

As At

Enter the date to be used to capture the configuration of the item. Only items effective at the selected date are selected and exploded. This field defaults to the current date.

Ignore Effectivity

Enter 1 to ignore the As at date and include all inputs regardless of effectivity; otherwise leave blank.

Functions:

F18

Cost Presentation. You can select the order in which cost elements appear on this report. For more information see Cost Presentation Window (F18).



Press **Enter** to generate the report.

Inputs Where-Used Report

1...
2...

28/MDE



Select Inputs Where-Used in the Reports list on the menu to display the Inputs Where-Used Report screen.

DB012P	Z1 - GB Demonstration Company	USER GBJBAMS	5/12/95 15:58:04
Inputs Where-Used Report			
From item.....?..	█	(Blank for start of file)	
To item.....?..		(Blank for end of file)	
Route	?	or type 'ALL' for all Routes	
As at date.....	5/12/95		
Ignore effectivity..		(1=Ignore effectivity)	
F3=Exit F4=Prompt			
05-23	SF	MW	KS IM II KENB20A PET166S2

Fields:

From/To Item

Enter the range of input items to be included in the report. Leave both blank for all items.

Route

Enter the route code you wish the system to use when imploding the selecting items to identify their parents. Only parents with this route configured are extracted and reported on. Alternatively, tab to the next field to select all routes.

As At Date

Enter an effective date to control the selection of parents of the selected input items. Only routes where an input is effective on the entered date are imploded and the parents reported on. The date defaults to the current date.

Ignore Effectivity

Enter 1 to ignore the As At date. All where-used relationships are included, otherwise leave blank.



Press **Enter** to generate the report.

Shift Profiles Report



29/MDE



Select Shift Profiles in the Reports list on the menu to display the Shift Profile Report Selection screen.

DB142	Z1 - GB Demonstration Company	USER GBJBAMS	5/12/95
Shift Profile Report Selection			15:04:03
Shift Profile Code: From...?... (Blank for start)			
To.....?... (Blank for end)			
As At Date..... <u>0/00/00</u>			
Print Where Used?..... (1=Yes)			
F3=Exit F4=Prompt F8=Submit Job			
07-44	SF	MM	KS
IM	II	KENB20A	PET166S2

Fields:

Shift Profile Code From/To

Enter the range of codes required.

As At Date

Enter the required date. Blank assumes current date.

Print Where-Used

The option is given to include or exclude where-used details.

0 - To exclude where-used details.

1 - To include where-used details.



Press **F8=Submit Job** to generate the report.

Labour Grades Report



30/MDE



Select Labour Grades in the Reports list on the menu.

This submits the report immediately and returns you to the menu.

Subcontractors Report



31/MDE



Select Subcontractors in the Reports list on the menu.

This submits the report immediately and returns you to the menu.

Company Profile Report



32/MDE



Select Company Profile in the Reports list on the menu.

The report produces a listing of the current settings for the company currently being processed.

Work Station/Centre Where-Used Report

1... **2...** 33/MDE

This report prints details of routes that use the specified work station/work centre.

It identifies where work station and work centre are configured in item route operations. This report allows you to access the operational impact of changing a work station or work centre.



Select Work Station/Centre Where-Used in the Reports list on the menu to display the Production Data Work Station/Centre Where-Used Selection screen.

```
DB032P          Z1 - GB Demonstration Company  USER GBJBAMS   5/12/95
                                     16:01:27
Production Data  -  Work Station/Centre Where Used Selection

To produce a report for a range of Work Stations/Centres key in BOTH fields.
To produce a report for a specific Work Station/Centre key in the FROM field.
To produce a report for all Work Stations/Centres leave BOTH fields blank.

                From          To
Select....?..  █             █
Sequence..... _ (1=Work Station 2=Work Centre)

F3=Exit  F4=Prompt
15-27    SF      MW      KS      IM      II  KENB20A  PET166S2
```

Fields:

Select From/To

Enter a work station/centre range.

Sequence

Sequence the report by work station or work centre.



Press **Enter** to generate the report.

Item Substitute Report

34/MDE

This report prints out items together with valid substitutes as defined in Production Details Maintenance. Only items with designated substitutes are included on the report.



Select Item Substitutes in the Reports list on the menu to display the Substitute Items Report screen.

DB682	Z1 - GB Demonstration Company	USER GBJBAMS	5/12/95 14:58:55
Substitute Items Report			
Print Items From.....?.. █			
Print Items To.....?.. _____			
Planner.....?.. _____			
F3=Exit F4=Prompt F8=Submit			
05-28 SF MK KS IM II KENB20A PET166S2			

Fields:

Print Items From/To

Enter an item range in the From and To fields.

Planner

Enter a planner.



Press **F8=Submit** to generate the report.