

-
-
-
-
-

Chapter 1

Maintenance



Creating Styles And Materials

Each style and material that you set up in Style requires two sets of data:

- Inventory details.
- Production details.

Inventory Details

Inventory details define how you purchase, manufacture, sell, cost, analyse, stock issue or control a style or material within Style applications. For a style, you can then set up production details.

Style Production reviews only those fields or flag settings which have a direct impact on the production process.



Note: You can define inventory details for both styles and materials from either the Style Inventory Management module or the Style Production Definition Management module.

Production Details

Production details define how styles and materials are provisioned, scheduled for production, forecast and costed by Style Production applications.

You must set up inventory details beforehand.

Style/Material Details

**1/P1M**

Use this option to create and maintain styles and materials.

For a description of this option, refer to the Style/Part/Product Maintenance option in Style Distribution (Inventory Management).

Full Product Details



2/P1M



To display the Maintain Production Details At Full Product screen, select Full Product Details from the menu.

Use this option to define production details for styles and costing details for materials for a particular style, route and cost set.

Production Details

Production details relating to styles that may be maintained are:

- Major sequence. This field groups together items, so that they can be planned and scheduled together.
- Minor sequence. This field determines the sequence in which a machine processes items.

You may amend these fields and view the effect on planning functions. You can also amend them to set minor production sequences within a major sequence for individual variants of a style.

Costing Details

Costing details which may be maintained are:

- Material cost.
- User cost elements 1 - 4.

These costs relate specifically to materials. Style assigns material costs automatically to the correct cost element, depending on whether the material is a fabric, trim or packaging.



Tip: Care should be taken when entering user-defined costs if landed costs are transferred from Style Inventory Management via the *Purchased Items Re-Cost* function; to ensure that these entries are not overwritten.

DS002		ZS - Style Demonstration Co.		User GBJBAMS		29/02/96 15:11:19	
Maintain Production Details at Full Product							
Style/Material Group.....?		■					
Route.....?		-					
Cost Set.....?		_____					
Default:				Maintain Default Rule (1=Yes) (1=All) (0=No) (0=Zero/Blank only)			
Major Sequence.....		_____		0		0	
Minor Sequence.....		_____		0		0	
Material Cost.....		_____		0		0	
User 1.....		_____		0		0	
User 2.....		_____		0		0	
User 3.....		_____		0		0	
User 4.....		_____		0		0	
F3=Exit F4=Prompt							
05-36		SF		MW		KS IM II KENB20A PET166S2	

Fields:

Style/Material Group

If maintaining production details, enter a style. If maintaining costing details, enter a material.

Route

Enter a route for the style or material.

Cost Set

Enter a cost set. Leave blank to imply standard costs.

Default

Enter the default value against the relevant category.

Maintain

This field determines whether to allow maintenance of individual style variants. Enter one of the following:

0 - No. Allow the value in the Default field to be changed for individual style variants.

1 - Yes. Do not allow the value in the Default field to be changed for individual style variants.

Default Rule

This field determines whether how Style uses the value entered in the Default field. Enter one of the following:

0 - Blank only. Set currently unvalued variants only to the value held in the Default field.

1 - All. Set all variants to the value held in the Default field.



On selection, the system will open maintenance windows displaying current settings for each style variant, in accordance with these parameter

and values.

Critical Resources

**20/P1M**

If you intend to use sourcing rule 1 (critical resource) within a multi-plant MPS run, then critical resources are mandatory.

A critical resource can be an activity, labour or machine duration and defined in any appropriate unit of measure.

You can define the capacity at one of the following levels:

- 1 - Default standard capacity.
- 2 - Default capacity profile.
- 3 - Daily capacity profiles, one per day of the week.

A tolerance percentage can be recorded which will allow the total capacity to be overloaded for a single order.



Note: The use of standard, default profile and daily profiles works in the same way for critical resources, as for the definition of capacity for machines.

Critical Resources Maintenance Screen 1



To display this screen, select Critical Resources from the menu.

Use this screen to enter the resource code you wish to create or maintain.

Fields:

Resource Code

Enter up to 2 alphanumeric characters.

Based On Code

To base a new resource code on an existing resource code, enter an existing resource code in this field.

Otherwise, leave this field blank.



To display Critical Resources Maintenance screen 2, press **Enter** from this screen.

Critical Resources Maintenance Screen 2



To display this screen, press **Enter** from Critical Resources Maintenance screen 1.

Use this screen to add or amend information about the critical resource.

DB095

Style Distribution Demo Company

USER QASTYLE

17/09/96
16:52:31

Critical Resources Maintenance

Resource Code...: ST

Description..... █

Capacity Basis Code.....?. _

Standard Capacity..... .000

Capacity UOM.....?. _

Tolerance Percentage..... _0

Profile Code (Default)..?. _

F3=Exit

F4=Prompt

F12=Previous

F20=Daily Capacity

06-19

SC

MK

KS

IM

II

KENB20A

PET166S2

Fields:

Description

Enter a description of the critical resource (mandatory).

Capacity Basis Code

There is a mandatory requirement to enter a capacity basis code. However, the field itself is for memorandum use only, but may be used to differentiate between different types of resource, for example, time, units, space, cost etc.

Codes are defined on the Style Inventory Management, descriptions file, against type CBCD.

Standard Capacity

Defines the standard capacity available per working day for the resource.

Alternatively, a default or specific resource capacity profiles may be defined using **F20=Daily Capacity**

Capacity UOM

Indicates the unit of measure for the standard capacity.

Codes are defined on the Style Inventory Management, descriptions file, against type UNIT

Tolerance Percentage

This percentage is used during the MPS run to allow the resource to be overloaded if an order exceeds the available capacity by less than the value entered here.

This is the only time that this tolerance will be used. It is not used to expand the standard available capacity.

Profile Code (Default)

A default profile may be entered, rather than entering a standard capacity in the Standard Capacity field. In addition, daily profiles may be applied via **F20=Daily Capacity**

Functions:

F20

Daily Capacity. Opens the Daily Capacity window, from which you can define different capacity profiles for any day of the week.

Daily Capacity Window

 To display this window, select **F20=Daily Capacity** from Critical Resources Maintenance screen 2.

Use this window to define capacity on a daily basis.

DB095

Style Distribution Demo Company

USER QASTVLE

18/09/96
9:39:07

Critical Resources Maintenance

Resource Code...: ST

Description..... Standard Critical Resource

Capacity Basis Code.....?. **1**

Resource Daily Capacity Maintenance

Profile Code

Default..... **ST** Style MSP Resource Profile

Monday..... —

Tuesday..... —

Wednesday... —

Thursday.... —

Friday..... —

Saturday.... —

Sunday..... —

F4=Prompt F8=Update F12=Previous

F3=Exit F4=Prompt F12=Previous F20=Daily Capacity

12-18 **SA** **MA** KS IM II KENB20A PET166S2

Fields:

Profile Code

A default profile code may be entered for use on days on which a specific code is not entered. Specific codes may be entered for specific days of the week.

Codes must have been defined via the Resource Capacity Profiles Maintenance function.

Resource Capacity Profiles



21/P1M

Resource capacity profiles are designed to provide more flexibility when defining capacities of critical resources. They are optional.

You can define effectivity dates with a specified capacity per day. You can attach those dates to critical resources as a default, or variable per day of the week.

Resource Capacity Profiles Maintenance

Screen 1



To display this screen, select Resource Capacity Profiles from the menu.

Use this screen to enter a capacity profile code.

Fields:

Profile Code

Enter a maximum 2 character code to create or maintain. Press **F8=Add** to create a profile after entering a unique code.

Based On Profile

If creating a new profile and details are to be based on an existing profile, enter the code of the existing profile here. The existing profile details will be copied to the new code, and may be maintained. Leave blank to create a profile from scratch, or maintain an existing profile.



To display Resource Capacity Profiles Maintenance screen 2, enter a new profile code and select **F8=Add**. Alternatively, enter an existing profile code and press **Enter**.

Cost Centres



30/P1M



To display the Cost Centre Maintenance screen, select Cost Centres from the menu.

Use this option to create and maintain cost centres.

You can use cost centres to define standard and current costs for:

- Set up labour time. Rates are entered as a cost per hour.
- Run labour time. Rates are entered as a cost per hour.
- Run machine time. Rates are entered as a cost per hour.
- Overheads. You can define up to two separate overhead costs (overhead 1 and overhead 2), based on an hourly rate or value or fixed charge for overhead 2. You can choose from 6 different recovery methods based on operation time or cost, and 4 methods based on material quantity.



Note: You can overwrite cost centre rates for individual operators by setting up labour skill rates under the Labour Skills option.

Machines

A cost centre may be assigned to any number of machines.

Cost centres define the cost rates to be applied at particular points in the production process, as each operation must be linked to a machine. This structure enables you to develop style unit costs, and to record actual costs in production.

Assigning a cost centre to a machine is optional. However, if you wish to derive any costs at the operation other than material costs, subcontract and user-defined costs, a cost centre is mandatory.

Departments

Cost centres may be linked to departments for performance analysis.

Material costs

Material costs are not influenced by cost centre definitions and are not discussed here.

Production costs

Production costs rely on the accurate determination of:

- Labour time.
- Machine time.
- Overheads.

Labour time

Labour time comprises set up time and run time and is influenced for costing purposes by team size.

Standard Operation Labour Time							
Op.	Set Up Labour			Run Labour			Labour Time
	Hours	Team Size	Time	Hours	Team Size	Time	
10	1.0000	2	2.0000	2.0000	3	6.0000	8.0000
20	0.5000	3	1.5000	1.5000	4	6.0000	7.5000
30	0.5000	4	2.0000	2.5655	5	12.8275	14.8275
	2.0000		5.5000	6.0655		24.8275	30.3275

For example, if the operation machine duration is 8 hours, but this requires 12 full time operators, then the cost is not simply 8 hours operator time but 8 x 12 hours operator time.

Machine time

Machine time is run time only.

Standard Operation Machine Time						
Op.				Run Machine		Machine Time
				Hours		
10				2.0000		2.0000
				0		
20				1.5000		1.5000
				0		
30				2.5600		2.5600
				0		
				6.0600		6.0600
				0		

Machine time is simply the amount of time a machine is in use.

Standard Operation Costs										
Op	Set Up			Run Labour			Run Machine			Total
	Hourly Rate	Labour Time	Cost	Hourly Rate	Labour Time	Cost	Hourly Rate	Machine Time	Cost	Total Cost
	3.7800	Hrs		4.5000	Hrs		5.4500	Hrs		
							0			

10	2.0000	7.5600	6.0000	27.0000	2.0000	10.9000	45.4600
20	1.5000	5.6700	6.0000	27.0000	1.5000	8.1750	40.8450
30	2.0000	7.5600	12.8275	57.7238	2.5600	13.9520	79.2358
	5.5000	20.7900	24.8275	111.7238	6.0600	33.0270	165.5408

Combined, this gives the total cost of the operation, with a total labour cost that can be extracted, if required.

Overheads

Overheads are slightly different and may be based on:

- Percentage of machine or labour or total cost.
- Rate per machine or labour time.
- Fixed cost.

These overheads may be set against standard and current costs.

Overhead Reference Data						
Op.	Labour Time	Labour Cost	Machine Time	Machine Cost	Total Time	Total Cost
10	8.0000	34.5600	2.0000	10.9000	10.0000	45.4600
20	7.5000	32.6700	1.5000	8.1750	9.0000	40.8450
30	14.8275	65.2838	2.5600	13.9520	17.3875	79.2358
	30.3275	132.5138	6.0600	33.0270	36.3875	165.5408
Time/Cost Overhead Recovery Methods						
A	B	C	D	E	F	
% of Machine Cost	% of Labour Cost	Rate x Machine Time	Rate x Labour Time	% of Total Cost	Rate x Total Time	Fixed
10.00%	10.00%	£2.45	£5.67	10.00%	£2.11	£9.00
1.09	3.46	4.90	45.36	4.55	21.10	9.00
0.82	3.27	3.68	42.53	4.08	18.99	9.00
1.40	6.53	6.27	84.07	7.92	36.69	9.00
3.30	13.25	14.85	171.96	16.55	76.78	27.00

There are several additional rates which may have specialist uses based on fabric, trim and packaging costs, but these are not covered here.

All cost components are then entered into the style cost elements at operational level:

- Fabric.
- Trim.
- Packaging.
- Labour via cost centre.
- Machine via cost centre.
- Set up via cost centre.
- Subcontract.
- Variable overhead 1 via cost centre.
- *Variable overhead 2 via cost centre.
- *Fixed overhead via cost centre.

* Mutually exclusive

The entry of cost centre rates and recovery methods therefore provides a vital input to the costing process.

DB013		ZS - Style Demonstration Co.		USER GBJBAMS		5/03/96	
						12:26:06	
Cost Centre Maintenance							
Cost Centre... ELF01							
Description... Elfin cost centre 1							
Department.... ELFIN							
		Standard		Current			
Machine rate/hr.		2.70000		3.40000			
Labour rate/hr.		3.55000		4.23000			
Setting rate/hr.		3.33000		2.78900			
O/H 1 method...?	E			E			
O/H 1 rate.....		5.00000		5.00000			
O/H 2 method...?	A			A			
O/H 2 rate.....		5.00000		6.00000			
O/H 2 value.....		.00000		.00000			
F3=Exit F4=Prompt F11=Delete Cost Centre				F12=Previous F21=Text			
06-18 S2 MW KS IM II KENB20A PET166S2							

Fields:

Cost Centre

Enter a maximum 5 character, alphanumeric code to create or maintain.

Base On Cost Centre

If creating a new cost centre and details are to be based on an existing cost centre, enter the code of the existing cost centre here. The existing cost centre details

will be copied to the new code, and may be maintained. Leave blank to create a cost centre from scratch, or maintain an existing cost centre.

Description

Enter a description for the cost centre. Use F21 to extend the description if required.

Department

This is an analysis group for cost centres. The code can be set to represent, for example, a functional department, a production line or a site.

Any code entered must have been fully defined via the Departments option.

Codes are held on the parameter file against type DEPT.

Machine Rate

Hourly cost rate for running machines in this cost centre.

Labour Rate

Hourly labour charge rate for this cost centre.

Set Up Rate

Hourly labour rate for setting up machines in this cost centre.

Overhead Recovery Methods

The variable overhead recovery methods available are :

A - % of machine cost.

B - % of labour cost (set up + run labour).

C - Cost rate/hour x machine run time.

D - Cost rate/hour x (set up + run labour time).

E - % of total cost (set up + run labour + machine).

F - Cost rate/hour x (set up + run labour time + machine time).

I - Cost rate per trim + packaging unit.

J - % of total trim + packaging value.

K - Cost rate per fabric unit.

L - % of total fabric value.

M - Cost rate per product unit.

X - % of subcontract cost.

Y - % of subcontract + fabric cost.

Z - % of trim + packaging + subcontract cost.



Note: For methods I and K, the rate is applied to the number of units specified in the Quantity Per field on the style route definition; irrespective of the actual 'material' quantity required. This method is not normally used with 'real' material items, but to pick up special costs such as utility

charges.

Rate Or %

The system will prompt for a rate or percentage, depending on the recovery method chosen.

Value (Fixed Charge)



Note: This field is only applicable to overhead 2.

This field allows entry of a fixed overhead recovery method. This value will not vary with production volumes or time expended, and will be amortised over the costing route batch size when generating style unit costs.

Functions:

F21

Add additional descriptive text.

Calendars



31/P1M

Use this option to set up or maintain a production calendar. Style Production Planning uses the calendar to establish operation schedules and material requirement dates.

You can:

- Identify working and non-working week days.
- Specify holidays and shutdown periods.
- Incorporate effectivity and year start dates.

Production calendars can be assigned specifically to:

- Company Profile. Default calendar for all applications.
- Machines. Define a specific calendar for an individual machine. If not specified, the Company Profile default calendar is used.
- Labour profiles. Define a specific calendar for a labour profile. If not specified, the Company Profile default calendar is used.
- Teams. Define a specific calendar for an individual team. If not specified, the Company Profile default calendar is used.



Tip: To mirror different working profiles, define a number of calendars.

Guidelines

1. Begin by defining a default calendar for scheduling work that does not require a special calendar. You should enter this default calendar on the Style Production Company Profile.
2. Within each calendar, create records for individual years. These should be consecutive. Begin each year on a Monday. For example: calendar 01 1996 could start on 01/01/96 and calendar 01 1997 could start on 30/12/96.
3. Calendars may start and end at any point within a year. That is, start and end dates for calendars 01 - 04 need not be the same.
4. Style assigns each week in the calendar a production week code. This code has the format nnYY where nn is the week number within the year, and YY the year. For example, 3296 indicates production week 32 in 1996. You will see this code displayed on screens and printed out on reports.

Examples

Listed below are examples of sample calendars:

- A calendar defined as a 7 day working week for 365 days a year with no holidays.
- A calendar constrained by a 5 day working week, factory shutdown and regular maintenance schedules.

- A calendar that plans for Saturday working during a peak season.
- A calendar that is specific to a particular machine or work centre that operates a different working week to the rest of the production facility.

Calendar Maintenance Screen 1



To display Calendar Maintenance screen 1, select Calendars from the menu.

Use this screen to create or maintain a production calendar.

Existing calendars are displayed. You can define a new calendar from scratch. Alternatively, base a new calendar on an existing calendar already defined for that year.

CA002		ZS - Style Demonstration Co.		USER GBJBAMS		27/02/96 16:19:15	
Calendar Maintenance				Default calendar: 01			
Sel	Code	Year	Days	Working Days	Year Start		
■	01	95	364	260	2/01/95		
-	01	96	364	260	1/01/96		
-	02	95	364	208	2/01/95		
-	03	95	364	252	2/01/95		
-	04	95	364	186	2/01/95		
1=Select 4=Delete 6=Print							
Enter Calendar code: __				and Year: __		Based on Calendar __	
F3=Exit							
06-04		S	MW	KS	IM	II	KENB20A PET166S2

Fields:

Maintenance

Sel(Ect)

To work with an existing calendar enter a selection option in this field, against the appropriate calendar code.

1 - Maintain a calendar definition.

4 - Delete a calendar.

6 - Print the calendar.

Creation

Calendar Code

Enter a unique (within year), 2 character, alphanumeric calendar code. The same code can be used to produce consecutive calendars in different years. Ensure that you define at minimum the company default calendar specified on the Company Profile.

Year Number

Enter the last two digits of the year for which the calendar is to be created.



Note: Calendars should be defined well in advance to ensure that the planning process is not disrupted by a lack of calendar data in a future period.

Base On Calendar

Optionally, enter an existing calendar code to base a new calendar definition on. After selection, you will be presented with the 'base on' calendar details for review.



*Note: When creating a new calendar from an existing definition, ensure that you select the Working Week Template Maintenance option (**F18**), and confirm by selecting the **F8** option, even if there is no requirement to change details.*



Enter 1 in the Sel field on Calendar Maintenance screen 1 to display Calendar Maintenance screen 2.

Calendar Maintenance Screen 2 (Option 1)



Enter 1 in the Sel field on Calendar Maintenance screen 1 to display Calendar Maintenance screen 2.

Use this screen to specify holidays and shutdown periods.

The standard week shown is the default working week template defined on the Company Profile. It is used in the absence of any other definition for this calendar, in this year.

```
CA0002                ZS - Style Demonstration Co.        USER GBJBAMS      27/02/96  
                                          16:19:15
```

Calendar Maintenance		Default calendar: 01										
Calendar Code 01												
Year 95	Start Date	■ <u>20195</u>		Standard Week:		M	T	W	T	F	S	S
Holidays											1	1
From	To											
_____	_____											
_____	_____											
_____	_____											
_____	_____											
_____	_____											
_____	_____											
_____	_____											
_____	_____											
_____	_____											
_____	_____											
_____	_____											
_____	_____											

F3=Exit F8=Update F12=Previous F18=Maintain Week Templates

05-30	Sf	MW	KS	IM	II	KENB20A	PET166S2
-------	-----------	----	----	----	----	---------	----------

Fields:

Start Date

Enter the start date of this calendar. The date must be a MONDAY and may commence at any point in a year.

Holidays

Enter the start and end dates for any holiday/shutdown periods.



Select **F18=Maintain Week Templates** on Calendar Maintenance screen 2 to display Calendar Maintenance screen 3.

Calendar Maintenance Screen 3



Select **F18=Maintain Week Templates** on Calendar Maintenance screen 2 to display Calendar Maintenance screen 3.

Use this screen to enter alternative templates for specifying the pattern of working and non-working days in a week. These alternatives may be dated to override the default template for specific periods of the year or to override for the whole of the year.

For example, you can:

- Plan for Saturday working during a peak season.
- Create a calendar for a specific machine or work centre operating a different working week to the rest of the factory.

```

CA002                ZS - Style Demonstration Co.          USER GBJBAMS      27/02/96
                                                16:19:15

Calendar Maintenance          Default calendar: 01
Calendar Code 01
Year 95          Start Date 20195          Standard Week:  M  T  W  T  F  S  S
                                                1  1

Enter up to five week templates for this year with effective dates.

MTWTFSS          From Date          To Date

____
____
____
____
____

____
____
____
____
____

____
____
____
____
____

F8=Update week templates          F12=Previous
05-30          S2          MW          KS          IM          II          KENB20A          PET166S2

```

Fields:

Start Date

Enter the start date of this calendar. The date must be a MONDAY and may commence at any point in a year.

MTWTFSS

Weekly working pattern template. Enter a weekly working pattern template. A blank signifies a working day, a non blank position signifies a non-working day.



Note: When creating a new calendar from an existing definition, you must confirm the working week pattern before generating the new details. That is, select F8 even if the templates are unchanged. otherwise the template will not take effect in the new calendar.

From Date

Enter the effective start date of the corresponding working week template. This date should be a MONDAY.

To Date

Enter the effective stop date of the corresponding working week template. This date should be a SUNDAY.

Shift Profiles



32/P1M



To display Shift Profile Maintenance screen 1,
select Shift Profiles from the menu.

A shift profile describes a pattern of shifts over the course of a single day. The profile comprises a list of shift numbers with associated start and finish times and an optional description. In addition, effectivity dates can be specified to reflect planned changes to the shift pattern.

The profile provides the information necessary to calculate time availability and duration times for scheduling and capacity planning.

You may use a shift profile to create the following:

- **Machines.** From the Machines option, you can choose whether or not to use a shift profile to define capacity. You can assign a shift profile to a machine in one of the following ways:
 - Designate a default profile to be used for every working day.
 - On a day by day basis, assign various shift profiles to each working day.
 - As a compromise, define a default profile for most working days, together with a specific profile for each non-standard day. For example, you might require a different profile on Friday to reflect an early finish time.
- **Labour profiles.** From the Labour Profiles option, use a shift profile to indicate a working pattern for the profile. A shift profile is mandatory.
- **Teams.** From the Teams option, use a shift profile to indicate a working pattern for the team. A shift profile is mandatory.

Shift Profile Maintenance Screen 1



To display Shift Profile Maintenance screen 1, select Shift Profiles from the menu.



Tip: Use this option rather than Maintain Parameter File to create and maintain all shift profiles.

Fields:

Shift Profile Code

Enter a 2 character numeric code to create or maintain.

Shift profile codes and their descriptions may also be created via Parameter File Maintenance; however, Shift Profile Maintenance must then be used to add start and end times, and effectivity definitions, as codes are not available for use until such details have been defined. Codes created here are displayed when the parameter file is reviewed.

If you enter a code which has only been defined via Parameter File Maintenance, the system will display the message 'No details defined for this code, press F8 to add'

Codes are held on the parameter file, against type CSHF.

Based On Profile

If the shift definitions of a new profile are to be based on an existing profile, enter the code of the existing profile here. The existing profile details will be copied to the new code, and may be maintained.

Leave blank to create a new profile code from scratch, or maintain an existing profile.



Press **Enter** on Shift Profile Maintenance screen 1 to display Shift Profile Maintenance screen 2.

Shift Profile Maintenance Screen 2



Press **Enter** on Shift Profile Maintenance screen 1 to display Shift Profile Maintenance screen 2.

DB140 ZS - Style Demonstration Co. USER GBJBAMS 27/02/96
16:21:48

Shift Profile Maintenance

Profile Code... 01

Description.... Day Shift

4=	Start	Finish	Effective	Effective		
Del	No.	Time	Time	From Date	To Date	Comment
-	1	0:00	9:30	2/01/95	99/99/99	
-	2	9:45	12:00	2/01/95	99/99/99	
-	3	12:30	14:30	2/01/95	99/99/99	
-	4	14:45	16:30	2/01/95	99/99/99	
-		0:00	0:00	0/00/00	99/99/99	
-		0:00	0:00	0/00/00	99/99/99	
-		0:00	0:00	0/00/00	99/99/99	
-		0:00	0:00	0/00/00	99/99/99	
-		0:00	0:00	0/00/00	99/99/99	
-		0:00	0:00	0/00/00	99/99/99	
-		0:00	0:00	0/00/00	99/99/99	
-		0:00	0:00	0/00/00	99/99/99	
-		0:00	0:00	0/00/00	99/99/99	
-		0:00	0:00	0/00/00	99/99/99	

F3=Exit F5=Refresh F8=Update F12=Previous

06-19 **S** MW KS IM II KENB20A PET166S2

Fields:

Description

Enter or maintain a description for the profile.

4=Del

Entry of a 4 in this column allows deletion of the associated shift definition details.

No.

Enter a number to identify each shift. Shifts must be ordered in time sequence. This field can be used to identify the shift number or to resequence to enable insertions.



Note: Shift numbers are prompted for during certain booking and transaction routines; in order to identify the time at which a particular event occurred. This is especially useful for transactions which do not prompt for a time, and for work bookings reported in elapsed rather than start, finish time

Start And Finish Times



Note: Do not include a colon when entering time. For example, type 0900 not 09:00 to display 09:00.

Effective Date Range

Enter the date on which the shift definition becomes effective, and ceases to be effective. If effectivity control is not applicable, accept the displayed defaults. Shifts that overlap in time cannot be effective on the same date.

Comment

Can be used to identify the shift, or indicate why a new shift pattern is being introduced on the defined effective date.

Departments



33/P1M



To display Department Maintenance screen 1,
select Departments from the menu.

A department is a collection of labour skills that are grouped together to analyse capacity requirements and average performance.

A department may be assigned to one or more of the following:

- Machines. All WIP inventory bookings must be made to a machine or department.
- Labour profiles. This is used to link departments to machines to establish labour requirements; a labour profile can be assigned to a route operation.
- Operators. When you use the Operators option, you must enter a department code to establish who is to bear the cost of an operator.

Style uses departments to work out labour capacity and load. Because labour skills belong to a department, Style states capacity against a department.

Department Maintenance Screen 1



To display Department Maintenance screen 1, select Departments from the menu.

Fields:

Department

Enter a maximum 6 character code to create or maintain.



To display Department Maintenance screen 2, press **Enter** on Department Maintenance screen 1.

Department Maintenance Screen 2



To display Department Maintenance screen 2,
press **Enter** on Department Maintenance screen
1.

DS001	ZS - Style Demonstration Co.	User GBJBAMS	27/02/96 16:25:27
Department Maintenance			
Department ELFIN			
Description..... <u>Elfin boot group</u>			
Absenteeism Rate..... <u>10.00</u>			
Utilisation %..... <u>10.00</u>			
Average Performance... <u>.00</u>			
Standard Hours/Day.... <u>8.00</u>			
F3=Exit F12=Previous F11=Delete			
07-25 S2 MW KS IM II KENB20A PET166S2			

Fields:

Description

Enter a description of the department.

Absenteeism Rate

This is a percentage used to reduce the expected capacity of the department due to unavailability (absenteeism) of operators. It effectively reduces the standard hours per day.

Utilisation %

This percentage affects the hours per day available from the department.

Average Performance

This is the average performance of the department, entered as a percentage.

Standard Hours/Day

This is the standard number of hours per day available from the department; prior to taking into account the above factors.

Machines


34/P1M

Use this option to create and maintain machines. Use each machine definition to represent either one machine or a number of machines of the same type.

Style uses the information that you enter for machines to ascertain:

- Product costs.
- Capacity requirements.
- Scheduled dates for production.
- Actual production costs.

Links

A machine is the lowest level of hard resource. You can link a machine directly to one or more of the following:

- Organisational Model. This is mandatory.
- Production calendar. A specific production calendar may be defined for the machine if the standard calendar is not applicable. Otherwise, the standard calendar defined on the Company Profile is used.
- Department. Group machines into departments for performance analysis.
- Shift profile. Define the days, and number of hours per day, that the machine is available for work.
- Cost centre. Define the cost rates incurred by work carried out at the machine. If a cost centre is not specified, no costs other than material, subcontract and user defined costs can be calculated.

Prerequisites

Before creating a machine, ensure that you have previously defined the following information:

Information	Option
Department	Departments
Organisational Model	Organisational Models
WIP location	Inventory Management Company Profile (Style Inventory Management)
Floorstock location	Inventory Management Company Profile (Style Inventory Management) Floorstock location can be the same as WIP location.

Cost Centre	Cost Centres To generate costs for the machine, you must enter a cost centre. However, this is not necessary for subcontract operation machines.
-------------	--

Machine Maintenance Screen 1



To display Machine Maintenance screen 1, select Machines from the menu.

Fields:

Machine

Enter a maximum 6 character code to create or maintain.

Based On Profile

If creating a new machine and details are to be based on an existing machine, enter the code of the existing machine here. The existing machine details will be copied to the new code, and may be maintained. Leave blank to create a machine from scratch, or maintain an existing machine.

Machine Maintenance Screen 2

DB001		Style Distribution Demo Company		USER QASTYLE		17/09/96	
						16:14:35	
Machine Maintenance							
Machine..... GOLD							
Description... GOLD Machine				Org.Model...?.. ST			
Calendar Code...?.. 96		Department.....?.. M					
Wip Location...?.. W1		Floor Stock Location...?.. F1					
Foreman.....		Queue Time.		Std. Efficiency 99.000 %			
	Max Length	Std Length	Max Capacity	Std Capacity			
Shift 1.....	8.0	8.0	8.0000	8.0000			
Shift 2.....							
Shift 3.....							
Duration Calculation Basis (Default)...?.. Machine Time +Setting Time							
Shift Profile (Default).....?..							
Default Shift Profile Capacity Factor....				Max... .00			
				Std... .00			
Cost Centre... GOLD (?)							
F3=Exit F4=Prompt F8=Update F11=Delete machine F12=Previous							
F20=Profile F21=Text							
06-18 SF MW KS IM II KENB20A PET166S2							

Fields:

Description

Enter a description of the machine or resource.

Organisational Model

Enter the specific Organisational Model to which the machine belongs.



Note: All operations on a route must be attached to a single Organisational Model. That is, one plant or line or route.

Calendar Code

Machine production calendar. If this machine requires a specific calendar, enter the appropriate code. The calendar will be used to schedule all work routed through this machine.

Blank - Use default calendar on Company Profile.

Department

Enter a department code that represents a functional or organisational grouping for this machine.

This can provide for the basis of additional analysis and reporting of machine activity. Production order and actual labour and machine times may be booked to a department. Entry is mandatory.

During booking routines, if a machine is entered, but no department specified, the system will assume, default to, and display the department entered here.

Codes are held on the parameter file, against type DEPT but defined via the Departments option.

WIP Location

To indicate the work-in-progress (WIP) location for this machine, enter a stockroom defined under the Style Inventory Management Company Profile. This field is required for tracking WIP inventory and is therefore mandatory.

Floor Stock Location

This is the location to which materials with a Movement Type Policy of 3 (issue to floor stock) are initially 'issued' or reserved. They are then consumed, when appropriate, as a consequence of production order or operator booking.

The location must be a stockroom defined to Style Inventory Management. Entry is mandatory.



Tip: Enter the same stockroom code as specified in the WIP Location field if no special floor stock locations have been created or are required.

Foreman

This field indicates the supervisor responsible for this machine. An entry is not validated and will only appear on the Machine Production List enquiry.

Queue Time

This field indicates the average queue time associated with this machine. It is expressed in hours. Scheduling will use this value when calculating operation start and finish dates. It represents an element of inter-operational transit time. WIP will be increased to allow for this additional production time.

Std Efficiency %

Standard efficiency factor. This figure represents the expected efficiency for the machine. To indicate 100% efficiency leave blank; to indicate an under efficiency enter a value between 1 - 99; to indicate over efficient enter a value between 101 - 999.

Machine Load Reviews will optionally apply this factor to standard capacity when making comparisons with scheduled loads, depending on the review capacity basis chosen when making an enquiry:

If comparison with standard effective capacity is required, the system will calculate standard effective capacity as (standard capacity x standard efficiency factor).

If comparison with standard capacity is required, the unmodified standard capacity will be used.



Note: This factor will not be included on cost calculations for styles made on this machine. If machine efficiency has significant impact on cost, this should be accounted for in the overhead rates associated with this particular machine and defined on the linked cost centre.

Max. Length

Maximum daily shift length(s). Enter up to 3 maximum (theoretical) shift lengths, which may all be different. If not entered, the system will default to one shift of 8 hours.

Std Length

Standard daily shift length(s). Enter up to 3 standard (expected) shift lengths, which may all be different. If not entered, the system will default to the maximum shift length (if defined) or else to one shift of 8 hours.

The expected shift length determines the length of the working day for scheduling calculations and is thus a determinant of lead time. This value represents an agreed working day length and as such is the basis of all operational planning.

Max Capacity

Maximum capacity per shift. Indicates the theoretical maximum hours that could be output by this machine.



Note: This is different to the maximum daily shift length in that this machine may represent multiple production resources, for example, a group of machines.

The field can also be used to indicate available working time including overtime and weekends, over and above the standard shift. It indicates how much extra machine capacity is available to meet the load.

You can define a maximum capacity for each shift, or a total daily capacity for the machine. If not entered, the system will default to the maximum shift length (if defined) or else to one shift of 8 hours.

Std Capacity

Standard capacity per shift. Indicates the standard hours that could be output by this machine.



Note: This is different to the standard daily shift length in that this machine may represent multiple production resources, for example, a group of machines.

It is used when comparing standard or standard effective capacity with scheduled load to identify capacity imbalances. You can define a standard capacity for each shift, or a total daily capacity for the machine. If not entered, the system will default to a shift length (if defined) or else to one shift of 8 hours.

Duration Calculation Basis (Default)

This field identifies the default machine duration basis code, which is utilised in the subsequent calculation of operation lead time.

This calculation is based on combinations of the set up labour, run labour and run machine times defined at each operation. The longest time element, or critical path activity, on the operation should be used to determine the lead time.

Duration basis codes may be set at the following levels:

- Operation. Each operation may be allocated a code. If a code is not entered the machine default will be used. If the machine default does not exist, the Company Profile default will be used.

- Machine (default). A default code may be entered against each machine definition. This will override the Company Profile default, and will be the default prompted on operations using the machine.
- Company profile (default). This will be the default code used if not overridden elsewhere.

Blank - Use Company Profile default. The default code description is displayed for reference.

0 - Set up labour.

1 - Set up labour + run machine.

2 - Set up labour + run labour.

3 - Set up labour + run labour + run machine.

4 - Set up labour + (greater of run labour or run machine).

Codes are defined on the parameter file, against type DUCT.

Default Shift Profile

Shift Profile (Default)

If a shift profile code is entered here, then the shift pattern associated with this code will be used on any day where a specific shift pattern is not found.

If a shift pattern is not found, and the default is not defined or does not exist, the number of hours available in a day will be the total of the three shift lengths entered above.



Note: If left blank on creation, and F20 used to create a shift/capacity profile, and a default profile is entered, the default will automatically be displayed here; likewise, any standard and maximum capacity factors defined will be automatically displayed.

Max

Default shift profile (Maximum) capacity factor; that is, the number of physical machines available. The total number of hours defined on the default profile will be multiplied by this factor to give the maximum capacity for the shifts.

Std

Default shift profile (Standard) capacity factor. The total number of hours defined on the default profile will be multiplied by this factor to give the standard capacity for the shifts.

Cost Centre

Enter a cost centre to provide cost rates for work carried out at this machine. Machine, labour, set up and overhead rates defined in the nominated cost centre will be applied to establish actual and standard costs for styles produced at this machine.

Actual costs may alternatively be calculated by booking work by operator or team.

Left blank, the system will display the error message 'Warning - no costs will be generated if left blank' and **F22** must be pressed to continue.



Note: You must leave this field blank if you are defining a machine to be used on subcontract operations.

Functions:

F20

Displays shift/capacity profile.

F21

Enable entry of text.

F22

Accept blank cost centre; only displayed when relevant.

Shift / Capacity Profile Maintenance Window (F20)

 This window is opened when **F20=Profile** is pressed on the Machine Maintenance screen.

You can create a shift profile to define the shift patterns of a particular day or work area. This screen allows you to specify which shift profile is to be used for each day of the week for this machine.

The capacity factor fields, when multiplied by the total number of hours on the related shift profile, give the maximum and standard capacities for the machine on any given day.

DB001 ZS - Style Demonstration Co. USER GBJBAMS 27/02/96
16:26:06

Machine Maintenance

Machine..... ELF01

Description... Elfin preliminary work group

Calendar Code?... 01 Department.....?.. ELFIN

Wip Location...?.. E1 Floor Stock Location.?.. E2

Foreman..... MS Queue Time. 3.000 Std. Efficiency 100.000 %

Shift / Capacity Profile Maintenance

	Shift Profile	Maximum Capacity Factor	Standard Capacity Factor
Default.....	<u>01</u>	10.00	5.00
Monday.....	—	10.00	5.00
Tuesday.....	—	10.00	5.00
Wednesday...	—	10.00	5.00
Thursday....	—	10.00	5.00
Friday.....	<u>02</u>	5.00	5.00
Saturday....	—	.00	.00
Sunday.....	—	.00	.00

F4=Prompt F8=Update F11=Delete F12=Previous

F3=Exit F4=Prompt F8=Update F11=Delete machine F12=Previous

F20=Profile F21=Text

13-23 **Sf** MW KS IM II KENB20A PET166S2

Fields:

Shift Profile

Enter the shift profiles to define the shift patterns of each day. The default shift profile provides the shift pattern for any day which does not have one of its own specified. Any entry made will be displayed on the Machine Maintenance screen.

Maximum Capacity Factor

The number entered will be multiplied by the total number of hours defined in the related shift profile, which will be either the profile for the same day, or else the default profile. The result will be the maximum capacity for a machine for the particular day.

For example, if the maximum capacity is 3 machines working instead of the standard 2, then enter 3 in this field. Any entry will be displayed on the Machine Maintenance screen.

Standard Capacity Factor

The number entered in this field will be multiplied by the total number of hours defined in the related shift profile, which will be either the profile for the same day, or else the default profile. The result will be the standard capacity for this machine for a particular day.

For example, if the standard capacity is 2 machines working, then enter 2 in this field.

Any entry made will be displayed on the Machine Maintenance screen.

Work Centres

1...
2...

35/P1M

Use this option to group machines into work centres for capacity loading analysis. A machine may belong to more than one work centre.

Group machines together in a work centre to analyse capacity loading at a summary level. For example, if you link a series of machines to a work centre, you can:

- Consolidate the loading and individual rated capacity of the machines at work centre level.
- Assess the capacity requirements in summary.

By changing the definition of the work centre, you can quickly perform 'what-if' analyses of capacity adjustments and load spreading.

Capacity planning performs its loading calculations at individual machine level. Therefore, you can modify the work centre without having to regenerate the capacity plan.

Example

Consider a factory with four sets of machines that are currently used for:

Machine	Function
1	Body/sleeve sewing
2	Collar/cuff sewing
3	Body/sleeve knitting
4	Collar/cuff knitting

To aid planning, you could define the following work centres:

Work Centre	Machines
A	All machines, comprising 1,2,3,4
B	All body/sleeve, comprising 1,3
C	All collar/cuff, comprising 2,4
D	All sewing, comprising 1,2
E	All knitting, comprising 3,4

After review, you can then allocate individual machines to different work to balance the load.

Prerequisites

Before using this option, use the Machines option to set up machines.

Work Centre Maintenance Screen 1



To display this screen, select Work Centres from the menu.

Fields:

Work Centre

Enter up to 5 alphanumeric characters.

Based On Work Centre

To base a new work centre on an existing work centre, enter an existing work centre in this field.

Otherwise, leave this field blank.



To display Work Centre Maintenance screen 2, press **Enter** from this screen.

Work Centre Maintenance Screen 2



To display this screen, press **Enter** from Work Centre Maintenance screen 1.

DB002		ZS - Style Demonstration Co.		USER GBJBAMS		27/02/96	
						16:30:59	
Work Centre Maintenance							
Work Centre ELFIN Description _____							
Machine	Description		Machine	Description			
ELFC	Elfin subcontracting						
ELF01	Elfin preliminary work group						
ELF02	Cut, form and assemble						
ELF03	Packing and despatch						
F3=Exit F4=Prompt F8=Update Work Centre							
F12=Previous F11=Delete Work Centre F21=Text							
07-03 MW KS IM II KENB20A PET166S2							

Fields:

Description

Enter a description of the work centre.



Tip: To enter a more detailed description, select **F21=Text**.

Machine

Specify the machines you wish to group together.



If you group together machines that are linked to more than one department, then this program issues a warning.



To book work by work centre rather than machine effectively, ensure that you assign all machines in the work centre to the same WIP location.

Bundle Ticket Types



36/P1M

Use bundle tickets to track work-in-progress along the production route. If you define a route for which parallel processing of operations is a pre-requisite, then bundle tickets are mandatory.

If the Automatic Bundle Tracking At Order Release field on Maintain Company Profile Screen 5 (option 1/P1U) is set to 2, Style creates bundle tickets automatically.

Printing formats are user-defined and may include bar-code labels or box end labels if required.



Note: The bundle ticket type entered at operation level must be consistent with the reporting level of the operation on the route.

Prerequisites

Before creating a bundle ticket type, ensure that you have previously defined the following information:

Information	Option
Search Family	Search Family Codes
Bundle Ticket Document Type	Maintain Parameter File (BDTP parameter)

Maintain Bundle Ticket Type Screen

-  To display the Maintain Bundle Ticket Type screen, select Bundle Ticket Types from the menu.

Use this screen to enter the bundle ticket type you wish to create or maintain.

Fields:

Bundle Ticket Type

Enter a maximum 3 character code to create or maintain.

-  To display the Maintain Bundle Ticket screen, press **Enter** from the Maintain Bundle Ticket Type screen.

Maintain Bundle Ticket Screen



To display this screen, press **Enter** from the Maintain Bundle Ticket Type screen.

Use this screen to enter details about the bundle ticket type, including search family and document type.



*Note: If you wish to mix style variants in one bundle, you must select **F18=Characteristics Mix**.*

DS191	ZS - Style Demonstration Co.	USER GBJBAMS	29/02/96
			16:33:26
Maintain Bundle Ticket		*Update	
Bundle Ticket Type.....?. BTA			
Description.....	Button Bundle		
Search Family.....?.	C/S	Colour & Size	
Bundle Quantity.....	48.000	UOM.....?.	EA
Bundle Quantity Variance.....	23.000		
Final Bundle Policy.....?.	0		
Document Type.....?.	4	Non-barcoded - A4 layout	
Ticket for Finished Goods Receipt ..	0	(1=Yes)	
Finished Goods-Default Bundle Qty...	0	(1=Yes)	
Barcodes on Ticket.....	0	(1=Yes)	
No. of labels per Bundle.....	0		
Parallel Ticket Type.....	1	(1=Yes)	
F3=Exit F4=Prompt F11=Delete F12=Previous F18=Characteristics Mix 07-39 SF MW KS IM II KENB20A PET166S2			

Fields:

Description

The bundle ticket description (mandatory).

Search Family

This field is mandatory. The search family specifies which dimensions determine mixing rules. For example, styles set up as colour only require colour only bundles.



Warning: When you link a bundle ticket, you link the ticket to an operation against a style. Therefore, the Search Family you enter here must match the Search Family set up for the Style via the Style/Material Details option.

Bundle Quantity

Enter the standard bundle quantity for the bundle ticket (mandatory). This value is used as default when using the Automatic Bundle Creation method.

UOM

Bundle ticket unit of measure (mandatory). The unit of measure for the default bundle quantity.

Codes are defined on the Style Inventory Management descriptions file, against type UNIT.

Bundle Quantity Variance

Enter the maximum quantity variance (tolerance) allowed, above or below the bundle quantity. This quantity determines the minimum and maximum quantities allowed on the final bundle operation when automatically creating bundles.



Note: Bundle quantity variance is only used on the final bundle created and is only used if the Final Bundle Policy flag for the bundle ticket type is set to 0 (bundle quantity). Bundle quantity variance must always be less than half of the bundle quantity.

Final Bundle Policy

This field determines the quantity of the final bundle on an order when automatically creating bundles. Enter one of the following:

0 - Change last bundle by variance (bundle quantity).

1 - Use quantity left after last bundle (remaining quantity).

Codes are defined on the parameter file, against type FRBO.

Use of this field is best illustrated with a couple of worked examples:

Example 1	
Final bundle policy	0 (bundle quantity)
Production order qty	64 pieces
Bundle qty	12 pieces
Bundle qty variance	0 pieces
The system would create 6 bundles of 12 pieces	

Example 2	
Final bundle policy	0 (bundle quantity)
Production order qty	64 pieces
Bundle qty	12 pieces
Bundle qty variance	5 pieces
The system would create 4 bundles of 12 pieces and 1 bundle of 16 pieces	

Example 3	
Final bundle policy	1 (remaining quantity)
Production order qty	64 pieces
Bundle qty	12 pieces
Bundle qty variance	0 pieces
The system would create 5 bundles of 12 pieces and 1 bundle of 4 pieces	

Document Type

This field defines the physical format of the printed bundle ticket document (mandatory).

Codes are defined on the parameter file, against type BDTP.

Ticket For Finished Goods Receipt?

This is a memorandum field only. This specifies whether a bar-coded stub will be printed on the bundle ticket for receipt of the styles into finished stock.

0 - No. A stub will not be printed (default).

1 - Yes. A stub will be printed.

Finished Goods-Default Bundle Qty

This is a memorandum field only. This specifies whether the bar-coded stub printed on the bundle ticket for the finished goods receipt will use the bundle quantity as the default or not.

0 - No. Do not use the bundle quantity by default (default).

1 - Yes. Use the bundle quantity by default.

Barcodes On Tickets

This parameter defines whether or not the operation stub on the bundle ticket will contain a barcode or not. This will be the barcode representation of the unique identifier for the stub - bundle number/operation sequence. The numeric version will always be printed.

0 - No. Do not print barcode (default).

1 - Yes. Print barcode.

Number Of Labels Per Bundle

This is a memorandum field only. This is the number of bar-coded 'box end' labels that will be printed for each bundle.

Parallel Ticket Type

Specify whether the bundle ticket can be processed in parallel with another bundle ticket. Enter one of the following:

0 - No. Do not allow parallel processing (default).

1 - Yes. Allow parallel processing.

For example, the knitwear industry uses parallel processing to knit materials (eg front, back and sleeves) for a garment. Each material is knitted on a different set of machines and can be ready for making up at the same time. To make parallel processing function, you would allocate different bundle ticket types to the front, backs, sleeves and collar.

Parallel Processing				
Bundle ticket type	Type A	Type B	Type C	Type D
Activity	Knit fronts	Knit backs	Knit sleeves	Knit collar
Duration	4 weeks	4 weeks	4 weeks	1 week
<u>Operations</u>	10 Issue	40 Issue	70 Issue	100 Issue
	20 Knit	50 Knit	80 Knit	110 Knit
	30 Bag	60 Bag	90 Bag	120 Bag
Type E				
Make Up				
130 Bundle up				

You may wish to schedule the operations so that all the materials are ready simultaneously for Make Up. Therefore, in the above example, you would not want to start Type A bundles until 3 weeks into the production cycle.

The Make Up point is the focal point. Preceding operations can be back scheduled from the Make Up point. The operations that follow can be scheduled forward from the Make Up point.

If you set this field to Parallel, one production order can control the whole process and schedule the operations in parallel.



Select **F18=Characteristics Mix** on the Maintain Bundle Ticket screen to display the Characteristic Mix Rules window.

Functions:

F18

Characteristics Mix. If you wish to mix style variants within the bundle, select this function to open the Characteristic Mix Rules window.

Labour Skills



37/P1M

Use this option to define the labour skills that your company requires. You can specify the dates when different labour skill rates are effective.

Load is calculated at labour skill level.

Optionally, you can override cost centre rates for individual labour skills by entering standard hourly rates of pay for use in costing.

A labour skill is the lowest level of soft resource and may be assigned directly to:

- Labour profiles.
- Operators.

Labour profiles

A labour profile is made up of the labour skills of a team of core skill members. By assigning a labour profile to an operation, you can indicate the percentage of time someone with that skill level requires to complete the work.



Note: You can also create Labour skills via the Labour Profiles option.

Operators

To indicate an operator's specific skills, use the Operators option to assign a labour skill to an operator. You can assign more than one labour skill to an operator, but not in concurrent effectivity periods.

Labour Skill Maintenance Screen 1



To display this screen, select Labour Skills from the menu.

Use this screen to enter a labour skill.

Fields:

Labour Skill

Enter up to 2 alphanumeric characters.



To display Labour Skill Maintenance screen 2, press **Enter** from this screen.

Labour Skill Maintenance Screen 2



To display this screen, press **Enter** from Labour Skill Maintenance screen 1.

Use this screen to enter a description and effectivity dates.

DB251	ZS - Style Demonstration Co.	User	GBJBAMS	27/02/96
				16:33:05
Labour Skill Maintenance				*Update
Labour Skill... E2				
Description.... <u>Leather cutting</u>				
Start date..... <u>12/03/94</u>				
End date..... <u>3/03/96</u>				
F3=Exit F11=Delete F12=Previous F20=Skill Rates				
07-20 MW KS IM II KENB20A PET166S2				

Fields:

Description

Enter a description of the skill.

Start Date

The skill will be considered live from this date. The date defaults to 0/00/00, implying the skill is immediately effective.

End Date

The skill will be considered unavailable on this date. The date defaults to 99/99/99 implying unlimited effectivity. It cannot be earlier than the start date.



Tip: The date range determines the period for which skill rates may be maintained.

Functions:

F20

Skill Rates. Display Labour Skill Maintenance screen 3, from which you can define one or more pay rates for the labour skill.

Labour Skill Maintenance Screen 3 (F20)



To display this screen, select **F20=Skill Rates** from Labour Skill Maintenance screen 2.

Use this screen to set up multiple pay rates for the labour skill. These rates are controlled by effectivity dates so new rates can be planned in and out through time. Only one rate can be effective on a particular date.



Warning: Enter labour skill rates only if you wish to override the cost centre rates.

DB260	ZS - Style Demonstration Co.		User	GBJBAMS	27/02/96
16:33:15					
Labour Skill Rate Maintenance					
Labour Skill... E2					
Description.... Leather cutting					
Start Date..... 12/03/94					
End Date..... 3/03/96					
	Start	End	Labour	Rate	
■	1/04/94	1/12/94		2.89000	
-	2/12/94	4/04/95		3.15000	
-	5/05/95	12/10/95		4.00000	
-	13/10/95	1/03/96		5.67000	
-	0/00/00	0/00/00		.00000	
-	0/00/00	0/00/00		.00000	+
2=Select 4=Delete					
F3=Exit F12=Previous					
14-04	SF	MM	KS	IM	II KENB20A PET166S2

Fields:

Select

Select one of the following options:

2 - Select. Display the Labour Skill Rate Maintenance window, from which you can maintain a labour skill rate.

4 - Delete. Delete a labour skill rate.



Tip: To maintain or delete multiple detail lines, enter 2 or 4 respectively against several lines.

Labour Skill Rate Maintenance Window (Option 2)



To display this window, enter 2 in the Select field on Labour Skill Maintenance screen 3.

Use this window to set up a labour skill rate for this labour skill. Enter the hourly rates and the dates when this skill rate takes effect.

DB260 ZS - Style Demonstration Co. User GBJBAMS 27/02/96
16:33:15

Labour Skill Rate Maintenance

Labour Skill... E2

Description.... Leather cutt

Start Date..... 12/03/94

End Date..... 3/03/96

	Start	End	Labour Rate
2	1/04/94	1/12/94	2.89000
-	2/12/94	4/04/95	3.15000
-	5/05/95	12/10/95	4.00000
-	13/10/95	1/03/96	5.67800
-	0/00/00	0/00/00	.00000
-	0/00/00	0/00/00	.00000

2=Select 4=Delete
F3=Exit F12=Previous

08-57 **S2** MW KS IM II KENB20A PET166S2

Fields:

Start Date

Enter a date to specify when the rate will come into force. This date must be greater or equal to the previous rate end date in the list. It also must be within the effective date range of the labour skill. If left blank, this date will default to 0/00/00 implying immediate effectivity.

End Date

Enter a date to define the day on which the rate becomes unavailable. It MUST NOT be less than the effective start date for the rate and it MUST be less or equal to the next effective start date for a rate in the list. It must not be outside the effective dates of the labour skill.

If left blank it defaults to 99/99/99 implying no end date.

Standard Rate

Enter the hourly rate chargeable for the skill in the defined period. The rate must be positive and non-zero.

Labour Profiles


38/P1M

Use this option to create and maintain labour profiles. From this option, you can also create labour skills.

A labour profile defines a number of different skills that a company requires to perform a multi-faceted operation. The relative involvement of each skill can be specified.

For example, the profile may require one person to carry out the operation and another person to act as supervisor.

You can vary the time spent by each labour skill. For example, an operation may require 100% of an operator's time. However, for a supervisor who is supervising 20 people simultaneously, you would only require 5% for a single labour profile.

Profiles can be attached to individual operations on route/BOMs, to be used in scheduling and capacity planning functions.

A labour profile may be linked directly to one or more of the following:

- Shift Profile. Mandatory.
- Production calendar. Memo use only. A specific calendar may be defined for the labour profile if the standard calendar is not applicable.
- Department. Labour profiles may be grouped by department for performance analysis and capacity requirements planning.
- Labour skills. Identifies the skills required to carry out the tasks.

Prerequisites

Before creating a labour profile, ensure that you have previously defined the following information:

Information	Option
Calendar	Maintain Company Profile (company default)
	Calendars (production calendar)
Shift Profile	Shift Profiles
Department	Departments

You must enter at least one labour skill, but this can be done from the Labour Skill Rate Maintenance window under this option.

Labour Profile Maintenance Screen 1

 To display this screen, select Labour Profiles from the menu.

Use this screen to enter a labour profile.

Fields:

Labour Profile

Enter a maximum 2 character code to create or maintain.

Based On Profile

If creating a labour profile and details are to be based on an existing labour profile, enter the code of the existing labour profile here. The existing labour profile details will be copied to the new code, and may be maintained. Leave blank to create a labour profile from scratch, or maintain an existing labour profile.



Note: When maintaining a labour profile, the system will prompt at the S(elect) field and await selection of, or addition of, a labour skill (previous fields can however still be maintained); when creating, it will prompt first in the Description field.



Press **Enter** on Labour Profile Maintenance screen 1 to display Labour Profile Maintenance screen 2.

Labour Profile Maintenance Screen 2



Press **Enter** on Labour Profile Maintenance screen 1 to display Labour Profile Maintenance screen 2.

Use this screen to enter a description, calendar, shift profile and department for the labour profile.

```

DS700                ZS - Style Demonstration Co.        USER GBJBAMS    27/02/96
                                                16:34:47

Labour Profile Maintenance

Labour profile...: E1
Description.....: Elfin production group
Calendar.....?: 01          Shift Profile...?: 01
Department...?: ELFIN          Standard Efficiency.: 110.000 %

Labour Skills included:
S Skill Description          Qty  Time%   From    To
- E1 Engineer                5    100    0/00/00 99/99/99
- E2 Leather cutting         1     50    0/00/00 99/99/99
- L1 Sewing Operator 1        1     5     0/00/00 99/99/99
- S1 Supervisor              2     5     0/00/00 99/99/99

2=Maintain  4=Delete
F3=Exit     F4=Prompt  F11=Delete Labour Profile  F12=Previous
F20=Add Labour Skill  F8=Update Labour Profile

12-04      SE      MW      KS      IM      II  KENB20A  PET166S2
  
```

Fields:

Description

Enter or maintain a labour profile description.

Calendar

Labour profile production calendar. If this labour profile requires a different calendar, enter the appropriate calendar code.

The system will display, and use as default, the calendar defined on the Company Profile.

Shift Profile

Specify the shift profile that will be used when scheduling work for this labour profile; the shift pattern of the shift profile will be used. (Mandatory.)

Department

You can associate a labour profile with a department. This will allow capacity loading views by labour department as well as by labour skill. An entry is mandatory.

Standard Efficiency

Standard efficiency factor. This figure represents the expected average efficiency for the labour profile.

To indicate 100% efficiency leave blank; to indicate an under efficiency enter a value between 1 - 99.

To indicate over efficient enter a value between 101 - 999.



Note: This factor will not be included on cost calculations for styles made using this profile.

Labour Skills Included

S

Select. Enter one of the following:

2 - Maintain. Display the Labour Profile Labour Skill Details window, from which you can amend labour skill details.

4 - Delete. Display the Labour Profile Labour Skill Details window, from which you can select **F11=Delete** to delete the labour skill.

Functions:

F20

Add Labour Skill. Display the Labour Profile Labour Skill Details window, from which you can add a labour skill to the skill mix.

Labour Profile Labour Skill Details Window (F20)

➡ To display this window, select **F20=Add Labour Skill** from Labour Profile Maintenance screen 2.

➡ To display this window, enter 2 or 4 in the Select field on Labour Profile Maintenance screen 2.

Use this window to define labour skills for the labour profile.

```

DS700          ZS - Style Demonstration Co.      USER GBJBAMS      27/02/96
                                           16:34:47

Labour Profile Maintenance

Labour profile...: E1
Description.....: Elfin production group
Calendar.....?: 01          Shift Profile...?: 01
Department...?: ELFIN      Standard Efficiency.: 110.000 %

Labour Skills inclu
S Skill Descripti
2 E1 Engineer
- E2 Leather cu
- L1 Sewing Ope
- S1 Supervisor

2=Maintain  4=Delete
F3=Exit    F4=Prompt
F20=Add Labour Skill

15-43  SF      MW      KS      IM      II  KENB20A  PET166S2

Labour Profile - Labour Skill Details
UPDATE

Labour Skill.?: E1
Engineer
No. Required...: 5
% Time Required: 100
Effective From.: 0/00/00
Effective To...: 99/99/99

F8=Update  F11=Delete  F12=Previous
F11=Delete Labour Profile  F12=Previous
F8=Update Labour Profile
  
```

Fields:

Labour Skill

Enter a labour skill set up under the Labour Skills option.

Alternatively, enter a new labour skill. By pressing **Enter**, you display the Labour Skill Maintenance window which provides a quick route into the Labour Skills option. Use the window to add a new labour skill.

Number Required

Enter the standard number of people with this labour skill who will work in this labour profile. This figure will be used to calculate standard labour costs and labour load requirements in capacity routines.

% Time Required

Enter in the standard percentage of time that this labour skill is required to work in this labour profile. This figure will be used to calculate standard labour costs and labour load requirements in capacity routines.

Effective Date Range

This is the effective date range during which the labour skill will be considered active. Capacity planning functions will include the labour skill if the control date is not earlier than the 'From Date' and less than the 'To Date'.



To display Labour Skill Maintenance screen 2, enter a new labour skill in the Labour Skill field and press **Enter**.

Operators

**39/P1M**

Use this option to identify an employee as a Style Production operator. When making a production transaction booking, the operator role allows you to specify who did the work.

Using effectivity dates, you can set up one or more pay rates to record production activity costs.



Tip: Alternatively, specify a labour skill rate that you have already set up under the Labour Skills option.

Prerequisites

You must have already set up the following:

- Department. Identifies who is responsible for meeting the cost of the operator. Use the Departments option.



Tip: Group operators into teams, so that you make team bookings rather than individual operator bookings. To do this, use the Teams option instead to create operators and group them into teams.



Note: An operator can have one skill only at any one time.

Operator Maintenance Screen 1

-  To display Operator Maintenance screen 1, select Operators from the menu.

Fields:

Operator Code

Enter a maximum 9 character, alphanumeric code to create or maintain.

-  To display Operator Maintenance screen 2, press **Enter** on Operator Maintenance screen 1.

Operator Maintenance Screen 2



To display Operator Maintenance screen 2, press **Enter** on Operator Maintenance screen 1.

DB271	ZS - Style Demonstration Co.	User	GBJBAMS	5/03/96
Operator Maintenance				15:28:14
Operator Code..... MS0001				
Name.....	Mike Summers			
Start Date.....	0/00/00			
End Date.....	99/99/99			
F3=Exit F11=Delete F12=Previous F20=Operator Rates				
08-21	SA	MW	KS	IM II KENB20A PET166S2

Fields:

Name

Enter the operator's name.

Start Date

Enter the date which defines the first date that the operator can perform work. The date defaults to 0/00/00, implying the operator is immediately effective.

End Date

Enter the date on which the operator becomes unavailable for performing work. If left blank it will default to 99/99/99. It cannot be earlier than the start date.



Press **Enter** to validate the data you have entered.

Functions:

F20

Operator Rates. Display the Operator Rates Maintenance screen, from which you can specify pay rates for the operator.

Operator Rates Maintenance Screen (F20)

Use this screen to specify pay rates for the operator. Multiple rates can be set up by specifying effectivity dates. Alternatively, pay rates can be defaulted to a labour skill rate rather than defined explicitly for the operator.



Select **F20=Operator Rates** on Operator Maintenance screen 2 to display the Operator Rates Maintenance screen.

DB272		ZS - Style Demonstration Co.		USER GBJBAMS		5/03/96 15:28:29	
Operator Rates Maintenance							
Operator Code...?		MS0001					
Name.....		Mike Summers					
Start Date.....		0/00/00					
End Date.....		99/99/99					
	Start	End	Labour Rate	Labour Skill	Department		
-	1/06/95	12/07/95	9.78000				
-	13/07/95	12/09/95	7.66000	S1	CLOTH		
-	0/00/00	0/00/00	.00000				
-	0/00/00	0/00/00	.00000				
-	0/00/00	0/00/00	.00000				
-	0/00/00	0/00/00	.00000				
-	0/00/00	0/00/00	.00000				
-	0/00/00	0/00/00	.00000				
+							
2=Select 4=Delete							
F3=Exit F12=Previous							
13-04 SF MW KS IM II KENB20A PET166S2							

Fields:

(Select)

Select one of the following options:

2 - Maintain an operator rate.

4 - Delete an operator rate.



Tip: Multiple detail lines can be maintained and/or deleted by selecting more than one item.



Enter 2 in the Select field on the Operator Rates Maintenance screen to display the Update/Add Operator Rates window.

Update/Add Operator Rates Window (Option 2)



Enter 2 in the Select field on the Operator Rates Maintenance screen to display the Update/Add Operator Rates window.

DB272		ZS - Style Demonstration Co.		USER GBJBAMS		5/03/96 15:28:29	
Operator Rates Maintenance							
Update/Add Operator Rates Start Date..... 13/07/95 End Date..... 12/09/95 Labour Rate..... 7.66000 Labour Skill..... S1 Department Code... CLOTH F4=Prompt F12=Previous F8=Update							
Operator Code...?	MS0001						
Name.....	Mike Sum						
Start Date.....	0/00/00						
End Date.....	99/99/99						
	<u>Start</u>	<u>End</u>					
-	1/06/95	12/07/95		9.78000			
2	13/07/95	12/09/95		7.66000	S1	CLOTH	
-	0/00/00	0/00/00		.00000			
-	0/00/00	0/00/00		.00000			
-	0/00/00	0/00/00		.00000			
-	0/00/00	0/00/00		.00000			
-	0/00/00	0/00/00		.00000			+
2=Select 4=Delete F3=Exit F12=Previous							
05-56 SF MW KS IM II KENB20A PET166S2							

Fields:

Start Date

Enter the first date the rate will be effective for the operator. It must not overlap with any other range of dates for which a rate is effective. It must fall within the operator's own effective date range.

It defaults to 0/00/00 to imply immediate effectivity.

End Date

Enter the date on which the rate will become ineffective for the operator. It must not overlap with any other range of dates for which a rate is effective. It must fall within the operator's own effective date range.

It defaults to 99/99/99, implying that the operator will always be available.

Labour Rate

Enter the operator rate in force for the period. This is an optional field. If left blank a valid labour skill must be entered in the Labour Skill field and the system will use the effective rate for the skill in this period.

Labour Skill

Enter a labour skill to identify the operator's abilities, and optionally, the pay rate for this operator in this period.

An operator may be assigned more than one labour skill by using effectivity dates; but only one skill may be effective on any one day.

This is an optional field. If left blank a valid standard rate must be entered in the Standard Rate field and the system will use the effective rate for this period.

Department Code

Enter the labour department that will bear the charge for this operator in this period. Departments are set up under the Departments option.

Teams

**40/P1M**

To display Team Master Maintenance screen 1, select Teams from the menu.

Use this option to define operator teams.

A team is a logical grouping of operators who between them can perform a range of skills. During production, you can book in work carried out by an operator or a team. You can also request production reporting by team. Style uses teams for costing.

To indicate where the team works, you must give the team a calendar and a shift profile.

You can assign one operator to one team or several teams.

Prerequisites

You must have already set up the following:

- Calendar. Identifies any specific working pattern for the team. Use the Calendars option to create a calendar.
- Shift Profile. Identifies the working pattern for the team. Use the Shift Profiles option to create a shift profile.

Team Master Maintenance Screen 1



To display Team Master Maintenance screen 1,
select Teams from the menu.

Fields:

Team Code

Enter a maximum 5 character, alphanumeric code to create or maintain.



To display Team Master Maintenance screen 2,
press **Enter** on Team Master Maintenance
screen 1.

Team Master Maintenance Screen 2

 To display Team Master Maintenance screen 2, press **Enter** on Team Master Maintenance screen 1.

DB291

ZS - Style Demonstration Co.

User GBJBAMS

5/03/96

Team Master Maintenance

15:29:25

*Update

Team Code..... HAND1

Description..... MATERIAL HANDLING TEAM

Shift Profile.?. 01

Calendar Code.?. 02

F3=Exit

F4=Prompt

F11=Delete

F12=Previous

F20=Team Details

07-21



MW

KS

IM

II

KENB20A

PET166S2

Fields:

Description

Enter a description for the team.

Shift Profile

Enter a shift profile code to define the working pattern for the team. An entry is mandatory.

Calendar Code

If this team requires a calendar different to that set on the Company Profile, enter the appropriate calendar code.

Blank - Use the calendar held on the Company Profile. The code and description will be displayed subsequently.

 To display the Team Details Maintenance screen, select **F20=Team Details** on Team Master Maintenance screen 2.

Functions:

F20

Team Details. Enter or maintain members of the team.

Team Details Maintenance Screen (F20)



To display the Team Details Maintenance screen, select **F20=Team Details** on Team Master Maintenance screen 2.

DB293	ZS - Style Demonstration Co.	GBJBAMS	5/03/96 15:30:20
Team Details Maintenance			
Team Code..... HAND1			
Description..... MATERIAL HANDLING TEAM			
Shift Profile... 01 Day Shift			
Calendar Code... 02			
	Operator	Start	End
-	RK	0/00/00	99/99/99
-	SL1	0/00/00	99/99/99
-		0/00/00	0/00/00
-		0/00/00	0/00/00
-		0/00/00	0/00/00
-		0/00/00	0/00/00
+			
2=Select 4=Delete			
F3=Exit		F12=Previous	
14-04		MW	KS IM II KENB20A PET166S2

Fields:

(Select)

The following options are available:

- 2 - Select an operator to maintain, or a blank line to add an operator.
- 4 - Select an operator to remove from the team.



Enter 2 in the Select field on the Team Details Maintenance screen to display the Team Detail Maintenance window.

Team Detail Maintenance Window (Option 2)

 Enter 2 in the Select field on the Team Details Maintenance screen to display the Team Detail Maintenance window.

DB293 ZS - Style Demonstration Co. GBJBAMS 5/03/96
15:30:20

Team Details Maintenance

Team Code..... HAND1

Description..... MATERIAL HANDLING TEAM

Shift Profile... 01 Day Shift

Calendar Code... 02

	Operator	Start	End
2	RK	0/00/00	99/99/99
-	SL1	0/00/00	99/99/99
-		0/00/00	0/00/00
-		0/00/00	0/00/00
-		0/00/00	0/00/00
-		0/00/00	0/00/00

Team Detail Maintenance

Operator.....?.. RK

Start Date..... 0/00/00

End Date..... 0/00/00

F8=Add Operator F12=Previous

2=Select 4=Delete

F3=Exit F12=Previous

11-64 SF MW KS IM II KENB20A PET166S2

Fields:

Operator

Enter an operator code to add to the team.

Start Date

Enter the first date the operator will be a member of the team. It must not overlap with any other range of dates for which a rate is effective. It must fall within the operator's own effective date range. The default is 0/00/00, implying immediate effectivity.

End Date

Enter the first date on which the operator will not be a member of the team. It must not overlap with any other range of dates for which a rate is effective. It must fall within the operator's own effective date range. The default is 99/99/99, implying unlimited effectivity.

 Press **Enter** on the Team Detail Maintenance window to add the operator to the team and display the Team Details Maintenance screen.

Functions:

F8

Add Operator. Create operator details for a new member of the team who has not been defined via Operator Maintenance. This function key displays Operator Maintenance screen 2 under the Operators option.

Text Types

**50/P1M**

To display Text Type Maintenance screen 1,
select Text Types from the menu.

Style Production allows you define text to associate certain system functions. Here you can define the text categories you wish to build text for. Each function can have multiple text types, although only one text type combination can be used interactively with the function at any point in time. You define the active text type combination for the function in the Company Profile.

Each major type can be sub-divided into minor or sub-types. These can represent different logical or operational groupings of textual information.

All recorded text can be enquired on or listed using the text management facilities.

Text Type Maintenance Screen 1



To display Text Type Maintenance screen 1,
select Text Types from the menu.

TX001	ZS - Style Demonstration Co.	USER GBJBAMS	5/03/96 15:30:59
Text Type Maintenance			
Type	Text Description		
BILL	MAJOR : BILL OF MATERIAL		
CSTC	MAJOR : COST CENTRE		
ITEM	MAJOR : ITEM CODE		
MACH	MAJOR : MACHINE		
OPER	MAJOR : OPERATION		
PROD	MAJOR : PRODUCTION ORDERS		
WKCT	MAJOR : WORK CENTRE		
Enter Text Type to Maintain or Add:-			
Major Type		Sub-type	(Optional)
F3=Exit F4=Prompt F17=Display Sub-types			
21-15  MW KS IM II KENB20A PET166S2			

Fields:

Major Text Type

Enter a major text type to create or maintain. This represents a major category of text, which can be linked to system entities.

The text accessed by the system is determined by the major and sub-types defined in the Company Profile. You can have different bodies of text for a particular system entity (for example, item), but one set only is considered to be the operational text.



Note: If you are creating a new text type, begin by entering a major text type. Initially, do not enter a text sub-type.

Text Sub-Type

Enter a text sub-type to create or maintain. This represents a sub-division of the major text type. Text can be managed in these separate categories.



To display Text Type Maintenance screen 2 where you can enter a description, press **Enter** on Text Type Maintenance screen 1.

Functions:

F17

Display Sub-types. View all the sub-types currently defined for the selected major type. Displays Text Type Maintenance screen 3.

Text Type Maintenance Screen 2



To display Text Type Maintenance screen 2,
press **Enter** on Text Type Maintenance screen 1.

Use this screen to type in or modify a description for the text type.

Fields:

Text Description

Enter a meaningful description.



To display Text Type Maintenance screen 1,
press **Enter** on Text Type Maintenance screen 2.

Text Type Maintenance Screen 3 (F17)



To display Text Type Maintenance screen 3,
select **F17=Display Sub-types** on Text Type
Maintenance screen 1.

This screen shows all sub-types currently defined for the selected major type.

These can represent logical groupings of text relating to the system function. For
example, Production Details Maintenance can have text relating to planning
information in one sub-type category, and text relating to item costs in another.

TX001	ZS - Style Demonstration Co.	USER GBJBAMS	5/03/96 15:31:26
Text Type Maintenance		Major type PROD - MAJOR : PRODUCTION ORDERS	
Sub-type	Description		
W01	MINOR :		
Enter Sub-type To maintain or add █			
F4=Prompt		F12=Previous	
21-40	Sf	MW	KS IM II KENB20A PET166S2

Fields:

Text Sub-Type

Enter a text sub-type to create or maintain. This represents a sub-division of the
major text type. Text can be managed in these separate categories.



To display Text Type Maintenance screen 4,
press **Enter** on Text Type Maintenance screen 3.

Text Type Maintenance Screen 4

 To display Text Type Maintenance screen 4, press **Enter** on Text Type Maintenance screen 3.

Use this screen to define the Minor categories associated with the text.

TX001

ZS - Style Demonstration Co.

USER GBJBAMS

5/03/96
15:31:26

Text Type Maintenance

Sub-type

Description

Major type

W01

MINOR :

PROD - MAJOR : PRODUCTION ORDERS

Text sub-type

W01

* AMENDMENT

Sub-type description

MINOR :

F11=Delete sub-type

F12=Previous

F13=Re-select major type

21-26



MW

KS

IM

II

KENB20A

PET166S2

Fields:

Sub-Type Description

Enter a description for this category of text.

Functions:

F13

Reselect the major type.

Text Maintenance



51/P1M



To display Text Maintenance screen 1, select
Text Maintenance from the menu.

Use this option to maintain entered text. The window illustrated is displayed when you press **F4**.

There are various system functions that use the text entered. For instance, any text relating to an operation on a route is copied to the equivalent operation on an actual order which is created from that route.

Text Maintenance Screen 1



To display Text Maintenance screen 1, select Text Maintenance from the menu.

TX003		ZS - Style Demonstration Co.		USER GBJBAMS		5/03/96	
Text Maintenance						15:32:31	
Major Type...?..		PROD					
Sub-Type....?..		W01					
File Key....?..		?					

Select Text Key		
		More: +
- PROD W01		1 21/07/95
- PROD W01 W000078		9 15/03/95
- PROD W01 W000125		1 17/03/95
- PROD W01 W000175		1 6/04/95
- PROD W01 W000176		1 6/04/95
- PROD W01 W000229		1 18/04/95
- PROD W01 W000230		1 18/04/95
- PROD W01 W000231		1 18/04/95
- PROD W01 W000232		1 18/04/95
- PROD W01 W000233		1 18/04/95
- PROD W01 W000254		1 19/04/95

F3=Exit		F4=Prompt	
11-33	SP	MW	KS IM II KENB20A PET166S2

Fields:

Major Type

Enter the text entity key you wish to create or maintain text for.

This key will identify members of certain categories of system entity.

- Items.
- Routes/Bills of Materials.
- Operations within routes.
- Machines.
- Work Centres.
- Cost Centres.
- Production Orders.

Sub-Type

Enter the text sub-type for the major type you wish to enquire on.

File Key

Enter the major text type you wish to enquire on.



To display Text Maintenance screen 2, press **Enter** on Text Maintenance screen 1.

Text Maintenance Screen 2



To display Text Maintenance screen 2, press
Enter on Text Maintenance screen 1.

TX002		ZS - Style Demonstration Co.		USER GBJBAMS		5/03/96		
Text Maintenance		Last Change Date: 15/03/95		No. of Lines: 9		15:33:28		
Key: W000078		Type: PROD - W01 - MINOR :						
Line	1	10	20	30	40	50	60	70
1	This is text							
2								
3								
4								
5	Line 5							
6								
7								
8								
9	Line 9							
10								
11								
12								
Position at line no. ____								
Insert ____ lines after line no. ____								
Delete lines - from ____ to ____								
F12=Previous								
F8=Return & Update Text								
07-10								
MW								
KS								
IM								
II								
KENB20A								
PET166S2								

Fields:

Deletion From

The first line at which the deletion will take place.

Deletion To

All lines from the from number, up to and including the target line will be deleted.

Insert Line Number

This specifies the line number after which to insert blank lines.

Insert Number Of Lines

This allows you to add several blank lines to the text file. Fresh text may then be added.

Text

Enter text as required in free format mode, and extra lines may be inserted or existing lines deleted using the fields at the bottom of the screen.

Position At

Enter the line number at which to position the top of the screen.