

-
-
-
-
-

Chapter 1

Maintenance



Advanced Shipping Maintenance Procedures

This section defines the Advanced Shipping File Maintenance procedures. It covers all the options that allow you to maintain the system parameters.

Defaults are held at company, customer / delivery sequence, and contract levels. When new customer defaults are created they are defaulted from the company level. When new contract defaults are created they are defaulted from the customer / delivery sequence level.


Customer / Delivery Point Defaults

1...
2...

1/STASM

Customer defaults are held at customer / delivery sequence level. In general, whenever customer defaults are created the corresponding company parameters are used as default values. Company default parameters **MUST** exist in the company profile before any customer parameters can be maintained.

Advanced Shipping Customer defaults are entered via the Customer Defaults screen. This option navigates through up to four possible input screens, which are linked together as follows:



Customer Defaults Screen



Selecting the Customer/Delivery point Defaults option from the menu to display the Customer Defaults screen.

```
AS015          Distribution V3 -> V3 Financials      User GBJBAPH2      16/02/96
                                                    14:29:15

Customer Defaults

Customer .....?.  NH001  000

F3=Exit  F4=Prompt

05-22      Sf      MW      KS      IM      II  KENB20A  PET007S1
```



Fields:

Customer

Enter the required customer code.



Press **Enter** to display the Customer Contract Defaults screen.



A successful **F8=Update** will return to the Customer Selection screen.

Enter the consignee country code.

Mode Of Transport

Enter the mode of transport. This field is mandatory.

Volume UOM

Enter the cube unit of measure to be used for calculating volume.

Default Pack Type

Enter the default pack type.

Default Pallet Type

Enter the default pallet type.

Transmit ANS1X12 856s

This field indicates whether 856 ASNs are transmitted. The following options are available:

0 = No. The system will continue to send European ASNs.

1 = Yes. The system will send 856 ASNs.

Default ASN Map Sequence & 856 Hierarchical Levels

Enter a sequence number. The system displays the default set up on the Company ASN and Pack Details Defaults screen in the Company Profile Maintenance section. The default can be overridden.



Press **Enter** to validate the screen.

Functions:

F8

This saves any changes made up to this point and returns to the customer selection screen.

F14

This displays the ASN Map and Sequences Hierarchies window which allows you to add and amend hierarchical options.

F21

This displays the Additional Address Codes window which allows additional address codes to be associated with the customer.

ASN Map And Sequences Hierarchies Window (F14)

This screen allows you to add and amend hierarchical options. The default sequence of '00' must be created on the Company ASN & Pack Details Defaults screen in the Company Profile Maintenance option in order for the system to send 856 ASNs correctly.



Select **F14=ASN Map Seq & Hierarchies** on the Customer Defaults ASN & Pack Details screen to display the ASN Map Sequences And Hierarchies window.

AS030 ST - Style Test & QA Company User GBJBARWZ 12/11/97 9:46:30

Advanced Shipment Notices Customer Defaults - ASN & Pack Details
Customer ... JLA 000 Archimbaud Ltd

Consignee ...? CONSAIL Carrier code.....? PARCEL POST

Final
Add.De
Consig
Mode o
Volume
Default
Default
Transm

ASN Map Sequences and Hierarchies

Sel	Seq?	ASN Map Sequence Description	Hierarchy?
	default		S I Q I E

1=Select 4=Delete
F4=Prompt F6=Add F12=Previous

Default ASN map sequence & 856 hierarchical levels...?

F3=Exit F4=Prompt F8=Update F12=Previous F14=ASN Map Seqs & Hierarchies
F21=Additional address codes

11-27 SP MW KS CL IM DM II STUD140 KB PET179S1

Fields:

Sel

Select. The following options are available:

- 1 - Select. Selects a hierarchy option.
- 4 - Delete. Deletes a hierarchy option.

Seq

Sequence. Enter the sequence number to be associated with the hierarchy option.

ASN Map and Sequence Description

This is a free field, enter the description.

Hierarchy

Enter the hierarchy agreed with the customer. Levels T,O,I,P can be arranged in any order.



Press Enter to validate the selection and return to the Customer Defaults ASN and Pack Details Screen

Functions:

F6

Add. This displays blank record lines in the window to allow you to add more data.


```

AS040                      Distribution V3 -> V3 Financials      User GBJBAPH2      16/02/96
                                                                14:31:31

Advanced Shipping Customer Defaults - ASN & Pack Details Defaults
Additional Address Codes

Customer ... NH001          000      Northern Motor Spares Limited

Consignee ..?. GEE01          Carrier Code.....?. CARR01
Final Deliv.?.                           Freight Forwarder?.                     
Add.Dest....?.                     

Type Code ?                      Address Code ?
                                                      
                                                      
                                                      
                                                      
                                                      
                                                      
                                                      
+

F3=Exit  F4=Prompt  F8=Update  F12=Previous

00-17    SF          MW          KS          IM          II  KENB20A  PET087S1

```

This is the freight forwarder code displayed from the previous screen.

Add Dest

This is an additional destination code number displayed from the previous screen.

Type Code

Enter the name and address type code for the specific entry you want to make.

Address Code

Enter the address code for the entry you want to make.



Warning: You cannot have more than one of each type code. If you enter a type code you must also enter an address code.



These values are maintained to allow the relevant details to be captured during the creation of the Advanced Shipment Notification.



Press **F8=Update** to save the details.

Pack Types



2/STASM

Products may be supplied in customer specified packaging, which in turn, may be loaded onto pallets. The ability to define the relationships between customer / item / pack / pallet will support the semi-automatic calculation of the requisite packaging and therefore reduce the time and effort involved in operator entry of the details.

Pack and pallet in their generic terms mean the two most outer shipping containers, for example this may be boxes in a crate. It is possible that a single container may be used as a 'pack' for one item and a 'pallet' for another. In this case it needs to be set up as both as if it were two different containers.

All weights are considered to be in the unit of measure defined on the Style Advanced Shipment Notices company profile.

All quantities are considered to be in the contract unit of measurement (which is taken from the Item Master Issue unit of measure at contract set-up).

Pack Type Maintenance Selection Screen



Select Pack Type from the menu to display the Pack Type Maintenance screen.

```
AS060          Distribution V3 -> V3 Financials    User GJBAPH2    16/02/96
                                           14:35:38
Advanced Shipping Pack Type Maintenance
Pack type.....?... ____

F3=Exit  F4=Prompt

05-23    SF    MW    KS    IM    II    KENB20A    PET007S1
```

Fields:

Pack Type

Enter a pack type. The **F4=Prompt** key is available.



Press **Enter** to continue.

Pack Type Maintenance Details Screen

This screen is displayed if you have made a valid selection on the Pack Type Maintenance Selection screen. From this screen you can define, modify, or delete pack type definitions. A pack type will define any kind of container or packaging used for delivery of an item to a customer, and may be used to calculate consignment weights and volumes.

AS060	ST - Style Test & QA Company	User GBJBARW2	12/11/97 9:51:59
Advanced Shipping Pack Type Maintenance			
Pack type.....	BOX <u>Standard Box</u>		
Tare weight.....	<u>1.000</u>		
Capacity weight.....	<u>999999.999</u>		
Volume.....	<u>1.000</u>	Volume UoM.....	EA Each
Length.....	<u>12.000</u>	Length UoM.....?	<u>BX</u> Box of
Depth.....	<u>12.000</u>		
Width.....	<u>12.000</u>		
Pack cost.....	<u>20.00000</u>		
Deposit value.....	<u>.00000</u>	Returnable.....	<u>0</u> (0/1)
Pack supplier.....?		Item.....?	
Comments.....			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F13=856 Container Defaults F23=Language Descriptions			
5-27	<u>SA</u>	MW KS CL IM DM II	STUD140 KB PET179S1

Fields:

Pack Type

The system will display the pack type code entered on the previous screen. Enter a description for this pack type.

Tare Weight

Enter the tare weight. This is the empty weight of the pack. This field is mandatory.

Capacity Weight

Enter the capacity weight. This is the maximum weight the pack can safely contain.

Volume

Enter the gross volume of the pack. This field is mandatory.

Volume UOM

The volume unit of measurement from the Company defaults is displayed.

Length

Enter the length of the pack. This field is mandatory.

Depth

Enter the depth of the pack. This field is mandatory.

Width

Enter the width of the pack. This field is mandatory.

Length UOM

Enter the Unit of Measurement for the length of the package. This field is mandatory. The **F4=Prompt** key is available.

Pack Cost

Optionally enter the cost of the packaging..

Deposit Value

Optionally enter the deposit value if this is a returnable package.

Returnable

This is where you identify if the pack is returnable.

0 - The pack is non returnable.

1 - The pack is returnable. You must also enter an item number in the item field. The item number must be a valid code from the Inventory Item file.

Pack Supplier

Enter a valid Accounts Payable supplier for the pack supplier. This field is optional. The **F4=Prompt** key is available.

Item

If the pack is defined in Inventory Management, enter the item reference number. This field is optional, unless the returnable field is set to 1, in which case it becomes mandatory. The **F4=Prompt** key is available.

Comments

Enter any free format comments relating to this pack type.



Press **F8=Update** to save this new information to the file.

Functions:

F11

This function key deletes the current pack type definition. You will not be able to delete the pack details if the pack is defined on any customer / item / pack / pallet records.

F13

Container Details

F23

Language Descriptions.


```

AS060                               Distribution V3 -> V3 Financials 3F User GBJBA1MS      9/07/96
                                           14:38:19

Advanced Shipping Pack Type Maintenance

Multi-lingual Descriptions Maintenance

Pac  Code..... BX1
     Description.. ROVER BOX TYPE ROVBX1

Tar
Cap  Language (?)  Description
      █           _____
Vol  _____  Cubic metre
      _____
Len  _____  Metre
Dep  _____
Wid  _____
      _____
Pac  _____
Dep  _____
Pac  _____  (0/1)
Com  _____

F4=Prompt  F8=Update  F12=Previous

F3=Exit  F4=Prompt  F8=Update  F11=Delete  F12=Previous
F23=Language Descriptions
09-11      SA      MW      KS      IM      II  KENB20A  PET08751

```

Pack Type Maintenance Container Detail Window

This window is displayed to enable container details to be entered or amended. The screen is displayed by using the **F13= Container Details** function key on the Pack type Maintenance Details screen.

AS060 ST - Style Test & QA Company User GBJBARW2 12/11/97 9:54:35

Advanced Shipping Pack Type Maintenance

Pack type..... BOX Standard Box

UCC 128 Packaging Type Code.....? 123456

UCC 128 Manufacturer Code.....

UCC Container Code.....

Shipper's Container Code.....

Carrier's Container Code.....

Deposit value..... 00000 Returnable..... 0 (0/1)

Pack supplier.....?.. Item.....?..

Comments.....

F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous
F13=856 Container Defaults F23=Language Descriptions

9-41 SA MW KS CL IM DM II STUD140 KB PET179S1

Fields:

UCC 128 Packaging Type Code

This is the code given to the specific UCC standard packaging type.

UCC128 Manufacturer Code

This is the UCC standard code used by the manufacturer.

UCC Container Code

This is the UCC standard code for the container.

Shippers Container Code

The code given to the container by the Shipper. This is a free format field.

Carriers Container Code

The code used by the carrier for the container. This is a free format field.

Pallet Types

1...
2...

3/STASM

Products may be supplied in customer specified packaging, which in turn, may be loaded onto pallets. The ability to define the relationships between customer / item / pack / pallet will support the semi-automatic calculation of the requisite packaging and therefore reduce the time and effort involved in operator entry of the details.

Pack and pallet in their generic terms mean the two most outer shipping containers, for example this may be boxes in a crate. It is possible that a single container may be used as a 'pack' for one item and a 'pallet' for another. In this case it needs to be set up as both as if it were two different containers.

All weights are considered to be in the unit of measure defined on the Style Advanced Shipment Notices company profile.

All quantities are considered to be in the contract unit of measurement (which is taken from the Item Master Issue unit of measure at contract set-up).

Pallet Type Maintenance Selection Screen



Select Pallet Type from the menu to display the Pallet Type Maintenance screen.

```
AS065          Distribution V3 -> V3 Financials    User GBJBAPH2    16/02/96
                                                    14:37:05
Advanced Shipping Pallet Type Maintenance
Pallet type.....?.. █

F3=Exit  F4=Prompt
05-23    SF    MW    KS    IM    II    KENB20A    PET007S1
```

Fields:

Pallet Type

Enter a pallet type. The **F4=Prompt** key is available.



Press **Enter** to continue.

Pallet Type Maintenance Details Screen

This screen is displayed if you have entered a valid pallet type on the Pallet Type Maintenance Selection screen. From this screen you can define, modify, or delete pallet type definitions. A pallet type will define any kind of container or packaging used for delivery of an item to a customer, and may be used to calculate consignment weights and volumes.

AS065	ST - Style Test & QA Company	User GBJBARW2	12/11/97 9:58:25
Advanced Shipping Pallet Type Maintenance			
Pallet type PAL <u>Standard Pallet</u>			
Tare weight..... <u>10.000</u>			
Capacity weight..... <u>999999.999</u>			
Volume..... <u>10.000</u>		Volume UoM..... EA Each	
Length..... <u>10.000</u>		Length UoM.....?.. BX Box of	
Depth..... <u>10.000</u>			
Width..... <u>10.000</u>			
Pallet cost..... <u>.00000</u>		Returnable..... 0 (0/1)	
Deposit value..... <u>.00000</u>		Controlled pallet..... 0 (0/1)	
Pallet supplier..?..		Item.....?..	
Comments.....			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			
F13=856 Container Defaults			
5-28 <u>SA</u> MW KS CL IM DM II STUD140 KB PET179S1			

Fields:

Pallet Type

The system will display the pack type code entered on the previous page. Enter a pallet description of up to 30 characters. This field is mandatory.

Tare Weight

Enter the tare weight. This is the empty weight of the pallet. This field is mandatory.

Capacity Weight

Enter the capacity weight. This is the maximum weight the pallet can safely hold.

Volume

Enter the gross volume of the pallet. This field is mandatory.

Volume UOM

The Volume unit of measurement from the company defaults will be displayed.

Length

Enter the length of the pallet. This field is mandatory.

Depth

Enter the depth of the pallet. This field is mandatory.

Width

Enter the width of the pallet. This field is mandatory.

Length UOM

Enter the unit of measurement for the length of the pallet. This field is mandatory.
The **F4=Prompt** key is available.

Pallet Cost

Optionally enter the cost price of the pallet.

Returnable

This is where you identify if the pallet is returnable.

0 - The pallet is non returnable. This is the default.

1 - The pallet is returnable. You must also enter an item number in the item field.

Deposit Value

Enter the deposit value of the pallet if this is a returnable item.

Controlled Pallet

This flag determines whether the pallet is controlled.

1 - A controlled pallet.

0 - The pallet is not to be controlled.

Pallet Supplier

Enter a valid Accounts Payable supplier for the pallet supplier. This field is optional. The **F4=Prompt** key is available.

Item

If the pallet is defined in Inventory Management, enter the item reference number. This field is optional, unless the returnable field is set to 1, in which case it becomes mandatory. The **F4=Prompt** key is available.

Comments

Enter any free format comments relating to this pallet type.



Press **F8=Update** to update the files with the new information.

Functions:

F11

This function key deletes the current pallet type definition. You will not be able to delete the pallet details if the pallet is defined on any customer / item / pack / pallet records.

F13

856 Container Details.

Customer / Item / Pack / Pallet Relationships



4/STASM

This function allows you to uniquely define the relationship between an item, and its pack type and pallet type for a specific customer. Only one such customer / item record may exist to enable automatic calculation of packing information during Advanced Shipment Notification processing.



Tip: When a relationship is first defined, as many values as possible are defaulted automatically from the customer ASN / Pack defaults. See Customer / Delivery Point Defaults.

Customer / Item / Pack / Pallet Maintenance Screen 1



Select the Customer / Item / Pack / Pallet Maintenance option. You can manually enter a customer / item combination if known, or use the prompt facility.

```
AS070          Distribution V3 -> V3 Financials    User GBJBAPH2    16/02/96
                                                    14:38:37

Customer/Item/Pack/Pallet Maintenance

Customer ..... ? █
Item ..... ? _____

F3=Exit  F4=Prompt

05-20    S2    MW    KS    IM    II    KENB20A    PET007S1
```

Fields:

Customer

Enter the customer code.

Item


Enter the item code. A prompt is available.



You can set up a record per customer. It is not mandatory to enter an item.



Press **Enter** to display the second Customer / Item / Pack / Pallet Maintenance screen.

**Fields:**

This is the customer code and description displayed from the previous screen.

This is the item code and description displayed from the previous screen.

Enter the pack type code. This field is mandatory.

Enter the pallet type code. This field is mandatory.

Enter the customers item reference. This field is optional.

Enter the reference by which the customer identifies a pack. This value is optional.

Customer Pallet Ref

Enter the reference by which the customer identifies a pallet. This value is optional.

Pallet Stackability

Enter the maximum number of pallets which can be stacked one on top of the other. This must be greater than zero. This field is mandatory.

Pack Material Item

Enter an item number of an additional piece of packaging material, for example a divider. This field is optional.

Maximum Packs Per Layer

Enter the maximum number of packs required to complete a layer on the specified pallet.

Minimum Layers

Enter the minimum number of layers which have to be on a pallet. This number must be between 1 and less than or equal to the maximum number of layers. This field is mandatory.

Maximum Layers

Enter the maximum number of layers allowed on a pallet. The default is 1. This must be greater than or equal to the minimum number of layers. This field is mandatory.

Maximum Items / Pack

Enter the maximum number of this item in this pack. This number must be greater than zero. This field is mandatory.



Note: If pack rounding is switched on for a particular contract, this quantity will be used in the pack rounding calculation.

Add Pack And Pallet Volume

Enter 1 to combine the volumes when calculating consignment volume, else enter 0.

Comments

This is a free format field. Enter any comments required for this particular item / pack / pallet relationship.



Press **F8=Update** to update the files. The Additional Cust / Item / Pack Data window is displayed when you are setting up an customer/item/pack relationship for the first time. The first Customer / Item / Pack Pallet Maintenance screen is displayed when the customer / item / pack relationship already exists.

ASN Names and Addresses Maintenance

1...
2...

5/STASM

The transmission of Advanced Shipment Notification data may demand, depending on customer and / or EDI message standard, the inclusion of additional name and address information, either coded or in full. The system has been defined in a flexible manner to support the current and future requirements in this area. The emphasis within Advanced Shipping has been to ensure all anticipated business data requirements are stored within the application. The transformation of that business data in to the various EDI Interface file formats is done within the EDI Application Interface functions.

Name and Address Selection Screen



Select the ASN Names and Addresses option from the menu to display the Name and Address Maintenance screen.

AS075	Distribution V3 -> V3 Financials	User GBJBAPH2	16/02/96
Name and Address Maintenance			14:43:02
Type code.....?.. _____			
Address code.....?.. _____			
F3=Exit F4=Prompt			
05-23	SE	MW	KS IM II KENB20A PET007S1

Fields:

Type Code

Enter an address type code.

Address Code

Enter an address code.



Press **Enter** to continue.

Name and Address Maintenance Details Screen

This screen is displayed when you entered a valid type code and / or address code on the Name and Address Selection screen. The contents of this screen identify alternative addresses for the customer. An internal ID field allows for an additional code which identifies the address type by some alternative code, for example one which has been mutually agreed between the consignee and consignor.

AS075		Distribution V3 -> V3 Financials 3F User GBJBA1MS		9/07/96	
				14:47:12	
Name and Address Maintenance					
Type code.....	CARR	Transport Carrier Company			
Address code.....	CARR01				
Name.....	CARRIER 01				
Address line 1.....	15 High Street				
Address line 2.....	Freemantle Green				
Address line 3.....	Dingle Wood				
Address line 4.....	Oldsbury				
Address line 5.....	West Midlands				
Post code.....	OL4 9IN				
Telephone number....	0121-555-5555	Extension number...	5555		
Fax number.....	0121-444-4444	Internal ID.....	FJDK		
Telex number.....	023934 4940	Teletext number....	394		
Contact name.....	Mr Fred Brown				
Department code....	G123				
Comments.....					
F3=Exit F8=Update F11=Delete F12=Previous F23=Language Descriptions					
18-27 SA MW KS IM II KENB20A PET087S1					

Fields:

Type Code

This is the address type code entered on the previous screen.

Address Code

This is the address code entered on the previous screen.

Name

Enter the name. This field is mandatory.

Address Line 1

Enter the first line of the required address. This field is mandatory.

Address Line 2

Enter the second line of the required address.

Address Line 3

Enter the third line of the required address.

Address Line 4

Enter the fourth line of the required address.

Post Code

Enter the post code.

Telephone Number

Enter the telephone number required.

Extension Number

Enter the internal extension number required.

Fax Number

Enter the fax number required.

Internal ID

Enter a suitable Internal ID code.

The internal ID field allows for an additional code which identifies the address type by some alternative code, for example one which has been mutually agreed between the consignee and consignor.

Telex Number

Enter the required telex number.

Teletext Number

Enter the required teletext number.

Contact Name

Enter the contact name as required.

Department Code

Enter the department code for the contact as required.

Comments

This is a free format field. Enter any required comments.



Press **F8=Update** to update the file.

Functions:

F23

Language Descriptions.

Name and Address Maintenance Multi Lingual Descriptions Maintenance Window (F23)

This window is displayed to enable a different language text to be entered or amended.

 This screen is accessed by pressing **F23=language Descriptions** from the Name and Address Detail screen.

AS075

Distribution V3 -> V3 Financials 3F User GBJBA1MS

9/07/96
14:47:12

Name and Address Maintenance

Multi-lingual Descriptions Maintenance

Code..... CARR

Description.. CARRIER 01

Language (?)	Description
---	_____
---	_____
---	_____
---	_____
---	_____
---	_____
---	_____
---	_____
---	_____
---	_____
---	_____

F4=Prompt F8=Update F12=Previous

F3=Exit F8=Update F11=Delete F12=Previous F23=Language Descriptions

09-11 SA MW KS IM II KENB20A PET087S1

Fields:

Language

Enter the language code to maintain.

Description

Enter a descriptive name in the language selected.

 Press **F8=Update** to save the language details.

