

-
-
-
-
-

Chapter 2

Processing



Style Advanced Shipment Notice Processing

Style provides an Advanced Shipment Notices management process which moves from Consignment Build through to Invoicing and encompasses the following:

- Consignment notes.
- Allocation / pricing / pick note initiation / despatching using Style Sales Order Processing.
- A pack creation and weight calculation.
- Production of advanced shipment notification (ASN) records.

Build and Maintain Consignments



1/STASP

This option allows you to create new consignments and maintain existing consignments.

Consignment Maintenance Screen



Select Build and Maintain Consignments from the menu to display the Consignment Maintenance screen.



This screen is also available if you select **F14=Consignments** from the Confirmation of Packing screen in Style Sales Order Processing.

AS200	ST - Style Test & QA Company	User GBJBARW2	12/11/97 11:41:30
ASN Consignment Maintenance			
Customer.....?.. █			
OR			
Consignment no...?..			
F3=Exit F4=Prompt F6=Add Consignment F15=Order Summary			
9-24 SP MW KS CL TM DM II STUD140 KB PET179S1			

Fields:

Customer

Enter the customer code. This field can be used to qualify a prompt on Consignment Number.



If you complete Customer and press **Enter**, the system will take you to the consignment selection screen.

OR



Completion of Customer plus **F6=Add New Consignment** will create a new consignment and display the Consignment Header Screen in Add Mode.

Consignment Number

When this is entered, any entry in the other fields is ignored. This option will take the user in to the Consignment Header Maintenance screen.



Press **Enter** to go to the Consignment Header, or to consignment selection screen, depending upon what you have entered.

Functions:

F6

Add New Consignment. This displays the Consignment Header screen in Add Mode.

F15

Order Summary.



Note: You cannot maintain a despatched or cancelled Consignment.

Consignment Selection Screen



This screen is displayed when you enter a customer and select Enter on the Consignment Maintenance screen.

```

AS200                      ST - Style Test & QA Company      User GBJBARW2      12/11/97
                           ASN Consignment Select            11:48:31

Customer.....: A11      000  House of Fraser

Sel Consign.  Description                               Despatch
Number                                              Date

■ 00001006                                12/09/97
- 00001008                                15/09/97
- 00001009                                15/09/97
- 00001010                                15/09/97
- 00001012                                16/09/97
- 00001013                                19/09/97

                                                    Bottom

1=Select Consignment
F3=Exit F6=Add Consignment F12=Previous

```



Select the consignment number required by placing a 1 against it. The Consignment Header Screen is then displayed.

Consignment Header Screen (F6)



This screen is displayed by pressing **F6=Add New Consignment** on the Consignment Maintenance - Selection Screen, or **Enter** from Consignment Maintenance - Selection Screen.

```

AS205                ST - Style Test & QA Company      User GBJBARW2    12/11/97
                                                           11:58:13
ASN Consignment Header Maintenance          *** AMEND MODE ***

Consignment number.. 00001006
Customer..... A11          000          House of Fraser
                                           Head Office
Mode of transport....?.. A          Freight line
Despatch date..... 12/09/97          Despatch time..... 0:00
Est. arrival date... 12/09/97          Est. arrival time.. 0:00

Supplier code.....
Plant number.....?..
Final delivery point..?.. A11 FDEL CODE          A11 FDEL Code
Additional dest. code.?.. A11 ADES CODE          A11 ADES Name
Freight forwarder.....?.. A11 FFWD CODE          A11 FFWD CODE
Carrier code.....?.. PARCEL POST          Parcel Post
Vehicle registration....
Trailer reference.....
ASN map sequence & 856 hierarchical levels..?.. PP S O P

F3=Exit F4=Prompt F8=Update F11=Cancel consignment F12=Previous
F15=Order summary F16=Complete Consignment

5-46  SA MW KS CL IM DM II STUD140 KB PET179S1
  
```

Fields:

Customer

Customer details will display from those previously entered.

Mode Of Transport

Enter the mode of transport. This field is mandatory.

Despatch Date

The system defaults to the value previously entered and can be amended.

Despatch Time

The system defaults to the customer default (optional), and can be amended.

Est. Arrival Date

Enter the estimated arrival date for this consignment. This defaults to despatch date plus shipping lead time.

Est. Arrival Time

Enter the estimated arrival time for this consignment.

Supplier Code

The system displays the value from Customer Defaults.

Plant Number

Enter a valid plant number. This field is optional and will default to the customer default on file for that type of address code, if a customer default exists.

Final Delivery Point

Enter a valid final delivery point code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Additional Destination

Enter a valid additional destination code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Freight Forwarder

Enter a valid freight forwarder code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Carrier Code

Enter a valid carrier code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Vehicle Registration

Enter the vehicle registration number transporting this consignment. This field is optional.

Trailer Reference

Enter the trailer reference number of the transport container for this consignment. This field is optional.

ASN Map Sequence & 856 Hierarchical Level

Enter the hierarchical level sequence code.

This field is displayed when the customer has been set up to send 856 ASNs. The default code defined on the Customer Defaults ASN And Pack Details screen in the maintenance section is displayed. It can be overridden to the allowed values for this customer.



Press **Enter** to validate & redisplay the screen.
Then press **F8=Update**.

Functions:



*Note: In ADD Mode the Function Keys are restricted to **F3**, **F4**, **F8** and **F12**.*



*Note: Function keys other than **F8**, **F11** and **F4** will warn the user if they have made amendments to the screen but not saved them via **F8=Update**.*

F8

Creates / Maintains Consignment Header record

F11

Deletes the consignment. This function will only be possible for consignments set to a status 'new' i.e. those which have no requirements attached.

F15

Displays the Order Summary screen.

F16

Complete the Consignment.



This function is only possible for consignments that have been fully packed using the Confirmation of Packing function within Sales Order Processing.

ASN Consignment Selection Criteria Screen (F8)



This screen is displayed when you select
F8=Update on the Consignment Header Screen.

It is used to select the criteria for the consignment you wish to complete.

AS200	ST - Style Test & QA Company	User GBJBARW2	20/01/98 10:58:45
ASN Consignment - Selection Criteria			
Consignment Number..... 00001006			
Customer Number..... A11 000			
Delivery Date Range..... (From) (To)			
Ship with reference.....			
F3=Exit F12=Previous F14=Outstanding Orders F15=Outstanding Despatch Notes			
9-28 SA MW KS CL IM DM II STUD140 KB PET179S1			

Fields:

Consignment Number

Enter the number of the consignment.

Customer Number

The customer number and sequence code will be displayed.

Delivery Date Range

Enter the required date range that you wish the consignment to cover.

Shipping Reference

This is the reference for the consignment.



Press **Enter** to validate the entries, then select
F14=Outstanding Orders or **F15=Outstanding
Despatch notes** to attach to the consignment.

Outstanding Orders Screen (F14)



This screen is displayed when you select
F14=Outstanding Orders on the consignment
selection Criteria screen.

The screen is used to attach any outstanding orders (within the specified date range) to the consignment. It may also be used to delete orders.

```

AS200                ST - Style Test & QA Company      User GBJBARW2    20/01/98
                                           11:03:00
ASN Consignment Maintenance
Consignment Number..... 00001006
Customer Number..... All      000
Despatch Date..... 12/09/97      Despatch Time.....:

Sel Order/      Cust.Order Reference  Delivery  Ship with      Status
Pick Note
■ 0001322
- 0001356
- 0001357
- 0001373
- 0001502
- 0001503
- 0001504
- 0001978      CPE
                4/02/97
                5/02/97
                5/02/97
                6/02/97
                28/02/97
                28/02/97
                28/02/97
                28/02/97

More...

1=Add to consignment 4=Remove from consignment
F3=Exit F8=Update F12=Previous
12-2      SP      MW      KS CL IM DM II      STUD140 KB PET179S1
  
```

Fields:

Sel

You have the option to select the pick note(s) for the order with either:

- 1 to add them to the consignment, or
- 4 to delete them from the consignment.



Press **Enter** to validate the selections and show
the status of the pick notes, then select
F8=Update to update the details.

Consignment Order Summary Screen (F15)

This screen is displayed after pressing **F15=Order Summary** from the Consignment Header screen. It is accessible for outstanding consignments only. It displays previously entered header information plus details from the item records which have this consignment reference.

AS212	ST - Style Test & QA Company	User GBJBARW2	20/01/98 11:06:49
ASN Consignment Order Summary			
Consignment Number .. 00001006		Status: Open	
Customer All		House of Fraser Head Office	
Supplier Code		Despatch Time ..	
Despatch Date 12/09/97			
Order/ Pick Note No.	Cust. Order Reference	Delivery Required	Ship with Reference
0001322 -		4/02/97	
0001356 -		5/02/97	
0001357 -		5/02/97	
F3=Exit F12=Previous			
1-1 SA MW KS CL IM DM II STUD140 KB PET179S1			

ASN Maintenance And Send



2/STASP

This option allows you to maintain, cancel or send ASNs. The ASN contains information relating to shipments or consignments.



Select ASN Maintenance And Send on the menu to display the ASN Maintenance And Send screen.

ASN Maintenance and Send Selection Screen

This option allows you to maintain, send and cancel ANSI12 856 ASNs. It is only available if your system is set up to transmit this type of ASN.



Select ANSI12 856 Maintenance And Send on the menu to display the ANSI12 856 ASN Maintenance And Send screen.

ASN Maintenance And Send Screen

This screen allows you to send and maintain ANSI12 856 ASN. Consignments that have been completed but not sent as an 856 ASN will automatically be shown on this screen.



Select ANSI12 856 Maintenance And Send on the menu to display the Maintenance And Send screen.

```
AS400          ST - Style Test & QA Company    User GBJBARW2    12/11/97
ASN Maintenance & Send                          12:12:37

Position to : Customer ....?.  █
Consignment .?.  █
Desp. Date & Time Sts

S Customer    Consignment
A11          000 House of Fraser
-            00001001 PARCELS****          5/09/97 :00 R
-            00001002                5/09/97 :00 R
-            00001003                5/09/97 :00 R
-            00001004                8/09/97 :00 R
-            00001005 AAAA            12/09/97 :00 R
-            00001007 JJ              12/09/97 :00 R

1=Maintain Details 2=Send 856 4=Cancel 856 Pre-Send
F3=Exit F4=Prompt F5=Refresh F8=Transmit 856s
F14=Consignments by Item F16=Select all '2'

5-68  SA MW KS CL IM DM II STUD140 KB PET179S1
```

Fields:

Position To Customer

Enter the customer code to display consignments starting from a particular customer. The list of customers is displayed alphabetically starting from that customer.

Position To Consignment

Enter the consignment number to display a list of consignments starting from the specified number.

S

Select. Enter an option to perform the following tasks:

- 1 - Maintain Details. Displays the 856 Maintenance Header Screen which allows you to add and amend the header details for a selected ASN.
- 2 - Send 856. Selects a consignment to be actioned when **F8=Transmit 856s** is selected.
- 4 - Cancel 856 Pre-Send. Removes an 856 ASN from the list displayed on the screen. When you cancel an 856 ASN the status is updated to Not Sent. You can resend an 856 ASN with a Not Sent status.

-  Enter 1 in the select field and press **Enter** to display the 856 Maintenance Header screen.
-  Select **F14=Consignments By Item** to display the Consignments By Item window.

Functions:

F6

Add A Manual 856. This option allows you to create a manual 856 ASN from a consignment.



Note: A manual 856 ASN is a memo document only and does not update inventory, schedules or invoices. It is your responsibility to make the necessary adjustments.

F8

Transmit 856s. Sends all 856 ASNs marked with a 2 in the select field.

F14

Consignments By Item. Allows you to enter an item code, which on display the previous screen, only lists consignments related to the specified item.

F16

Select All '2'. Automatically applies option 2 (Send 856) to all consignments on the screen, which are then activated when **F8=Transmit 856s** is selected.

Maintenance Header Screen (Option 1)

This screen allows you to enter and amend data for a selected 856 ASN.



Enter 1 in the select field on the ASN Maintenance And Send screen and press **Enter** to display the Maintenance Header screen.

AS410		ST - Style Test & QA Company		User GBJBARW2		12/11/97	
						12:14:53	
ASN Maintenance - Header							
Consignment number...		00001001		PARCELS****			
Customer.....		A11		000		House of Fraser	
						Head Office	
Mode of transport.....?		A				Freight line	
Despatch date.....		5/09/97				Despatch time.....	
Est. arrival date....		5/09/97				Est. arrival time..	
						0:00	
						0:00	
Supplier code.....?							
Plant number.....?							
Final delivery point...?		A11 FDEL CODE				A11 FDEL Code	
Additional dest. code...?		A11 ADES CODE				A11 ADES Name	
Freight forwarder.....?		A11 FFWD CODE				A11 FFWD CODE	
Carrier code.....?		PARCEL POST				Parcel Post	
Vehicle registration....							
Trailer reference.....							
ASN map sequence & 856 hierarchical levels....						S T O I P	
F3=Exit F4=Prompt F8=Update F10=Additional 856 Details F12=Previous F14=Weights & Totals F15=Items F21=Name & Addresses F22=856 Text							
5-43		SA		MW		KS CL IM DM II	
						STUD140 KB PET179S1	

Fields

Mode Of Transport

Enter the mode of transport for the consignment. This field is mandatory. The **F4=Prompt** key is available.

Despatch Date

Enter the date of despatch.

Despatch Time

Enter the time of despatch using the 24 hour clock.

Est Arrival Date

Enter the estimated arrival date. This date must be the same as or later than the despatch date.

Est Arrival Time

Enter the estimated arrival time using the 24 hour clock.

Supplier Code

The system displays the value entered in the Customer Contract Defaults screen in the Maintenance option if you are in Add mode (F6), otherwise it will be returned from the consignment header.

Plant Number

This field is optional and will default to the customer default on file for that type of address code, if a customer default exists.

Final Delivery Point

Final delivery point code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Additional Dest.Code

Additional destination code. This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Freight Forwarder

This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Carrier Code

This field is optional and will default to the customer default on file for that type of address code, if customer default exists.

Vehicle Registration

Enter the registration number of the vehicle transporting this consignment. This field is optional.

Trailer Reference

Enter the trailer reference number of the transport container for this consignment. This field is optional.

ASN Map Sequence & 856 Hierarchical Levels

The system displays the sequence code which is entered when the consignment is created or amended.



Select **F8=Update** to update the data and display the ASN Maintenance And Send screen.



Note: Detailed field values will be returned from the consignment details unless it is a manual ASN in which case the details are returned from customer defaults.

Functions:

F10

Additional 856 Details. This function displays the Additional 856 Details window which allows you to select screens to add and amend additional 856 ASN data against a consignment.

F14

Weights & Totals. This function displays the 856 Maintenance Weights And Totals screen which allows you to overwrite the system calculated 856 ASN totals.

F15

Items. This function displays the first 856 Maintenance Item Summary screen which lists item details.

F21

Name & Addresses. This function displays the 856 Maintenance Names And Addresses screen which allows you to amend address details.

F22

856 Text. This displays the 856 Text window which allows you to enter free format text to be sent with an 856 ASN.

Additional 856 Details Window (F10)

This window allows you to send 856 ASN data over and above the essential common message data. From this menu you can select the screens which allow you to add further 856 ASN details.

All the additional 856 ASN details are optional, your trading relationship determines which additional details must be included.

The first five options from this window are appropriate to only one level of details. The remaining options are appropriate to more than one level.

The fields and their names have been included to match the names used by the 856 ASN message itself.



Select **F10=Additional 856 Details** on the 856 Maintenance Header Screen to display the Additional 856 Details window.

AS410 ST - Style Test & QA Company User GBJBARW2 12/11/97 12:16:33

ASN M

Consi
Custo
Mode
Despa
Est.

Suppl
Plant
Final
Addit
Freig
Carri
Vehic
Trail
ASN m

Additional 856 Details
Sel

- 1 Additional Shipment Level Details
- Additional Tare Level Details
- Additional Order Level Details
- Additional Pack Level Details
- Additional Item Level Details
- References
- Charges & Allowances
- Hazardous Materials
- Product/Service Identification
- Product Characteristics
- Subline Details
- UICS Product Marks/Package Specification

I=Select
F12=Previous

F3=Exit F4=Prompt F8=Update F10=Additional 856 Details F12=Previous
F14=Weights & Totals F15=Items F21=Name & Addresses F22=856 Text

6-10 SA MW KS CL IM DM II STUD140 KB PET179S1

Fields:

Sel

Select. Enter 1 against the required option. The following options are available:

Additional Shipment Level Details screen

Additional Tare Level Details which displays the 856 Additional Tare Container References screen.

Additional Order Level Details which displays the 856 Additional Order Level Details screen.

Additional Pack Level Details which displays the 856 Additional Pack Container References screen.

Additional Item Level Details which displays the 856 Additional Item Details window.

References which displays the 856 References screen.

Charges And Allowances which displays the 856 Charges And Allowances screen.

Hazardous Materials which displays the 856 Hazardous Materials screen.

Product/Service Identification which displays the Product/Service Identification screen.

Product Characteristics which displays the Product Characteristics screen.

Subline Details which displays the Subline Details screen.

VICS Product Marks/Package Specification screen.



Enter 1 in the Sel field to select the required option and display the associated screen.

856 Additional Shipment Level Details Screen

This screen allows you to add additional shipment details to be sent with an 856 ASN.



Enter 1 in the Sel field of the Additional Shipment Level Details option on the Additional 856 Details window to display the 856 Additional Shipment Level Details screen.

AS263		Version 3 Demonstration Company		User QA AUT01		14/07/97	
						11:28:18	
Advanced Shipping 856 Additional Shipment Level Details							
Shipment Number ...		00000001		Hierarchical Structure S T O I P			
Original Carrier ?		Type ?	Carrier Name			Status ?	
CARR01		—	Transport carrier company 01				
Carrier Location		—	Type ?	Mode ?	Service ?	Transit Time	Type ?
		—	3	—	—	0:00	—
1st After Original ?		Type ?	Carrier Name			Status ?	
Carrier Location		—	Type ?	Mode ?	Service ?	Transit Time	Type ?
		—	—	—	—	0:00	—
2nd After Original ?		Type ?	Carrier Name			Status ?	
Carrier Location		—	Type ?	Mode ?	Service ?	Transit Time	Type ?
		—	—	—	—	0:00	—
Equipment :		Type ?	—	Initial	Number		
F3=Exit F4=Prompt F8=Update F10=Transport Charges & Goods Title							
F12=Previous							
07-02		SA	ML	KS	IM	II	KENB20A PED201S2

Fields:

Original Carrier

Carrier Code. This is displayed from the 856 Maintenance Header screen and can be overridden.

Type

Enter the code for the carrier type.

Carrier Name

This is the carrier name that corresponds to the carrier type code.

Status

Enter the carrier status code.

Carrier Location

Enter the carrier location. This is a free format field.

Type

Enter the carrier location type code.

Mode

Mode of Transport. This is displayed from the 856 Maintenance Header screen and can be overridden.

Service

Carrier Service Level. Enter the carrier service level code.

Transit Time

Enter transit time.

Type

Enter the carrier transit time type.

1st After Original

The fields 1st After Original and 2nd After Original allow you to add additional carriers.

Equipment

Type

Equipment Type. Enter the equipment type code.

Initial

Enter the equipment initial. This is a free format field.

Number

Enter the equipment number. This is a free format field.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details window.

Functions:

F10

Transport Charges & Goods Title. This function allows you to enter and amend additional specific transport charges.

Transport Charges Window (F10)

This function allows you to enter and amend additional transport charges specific to the shipment.



Select **F10=Transport Charges & Goods Title**
on the 856 Additional Shipment Level Details
screen to display the Transport Charges window.

AS263		Version 3 Demonstration Company		User QAUT01	14/07/97
					11:28:18
Advanced Shipping 856 Additional Shipment Level Details					
Shipment Number ...		00000001		Hierarchical Structure S T O I P	
Transport Charges					
Origi	Payment Terms	P1	Cash		?
CARR0	Responsibility Location Type.?	01	Location type 1		
Carri	Location				ype ?
	Payment Terms Identification ?.				
	Payment Type Code				
1st A	Title of Goods				?
	Change Location Type				
Carri	Change Location				ype ?
	Premium Transport				
	Reason for use Code				
2nd A	Responsibility for Excess ...?				?
Carri	Authorisation for Excess				ype ?
F4=Prompt F12=Previous					
Equipment :	Type ?		Initial		Number
F3=Exit F4=Prompt F8=Update F10=Transport Charges & Goods Title					
F12=Previous					
06-42	SA	ML	KS	IM	11 KENB20A PED201S2

Fields:

Payment Terms

Enter the payment terms code.

Responsibility Location Type

Enter the code corresponding to the type of location of the party responsible for the transport charges.

Location

Enter the location. This is a free format field.

Payment Terms Identification

Enter the code corresponding to the payment terms identification.

Payment Type Code

Enter the code corresponding to the payment type.

Title Of Goods

Change Location Type

Enter the code corresponding to the type of carrier location.

Change Location

Enter text. This is a free format field.

Premium Transport

Reason For Use Code

Enter the code corresponding to the reason for using the premium transport.

Responsibility For Excess



Enter the code corresponding to the party responsible for the excess charges relating to the use of premium transport.

Authorisation For Excess

Enter the authorisation reference. This is a free format field.



Press **Enter** to validate the data and display the 856 Additional Shipment Level Details screen.



856 Additional Pack Container References Screen

This option allows you to enter additional pack container details, such as alternative pack container references.



Enter 1 in the Sel field of the Additional Pack Level Details option on the Additional 856 Details window to display the 856 Additional Pack Container References screen.

AS271	ST - Style Test & QA Company	User GBJBARW2	12/11/97 12:21:25
856 Additional Pack Container References			
Shipment Number ... 00001001		Hierarchical Structure S T O I P	
Int. Ref.	Typ	UCC Serial No.	Shipper's Reference
1 BOX			Carrier's Reference
Assigned Pack ID:		Size of Suppliers Units	UOM .?. _
2 BOX			
Assigned Pack ID:		Size of Suppliers Units	UOM .?. _
3 BOX			
Assigned Pack ID:		Size of Suppliers Units	UOM .?. _
4 BOX			
Assigned Pack ID:		Size of Suppliers Units	UOM .?. _
5 BOX			
Assigned Pack ID:		Size of Suppliers Units	UOM .?. _
6 BOX			
Assigned Pack ID:		Size of Suppliers Units	UOM .?. _
7 BOX			
Assigned Pack ID:		Size of Suppliers Units	UOM .?. _ +
F3=Exit F4=Prompt F8=Update F12=Previous F15=Show/Hide Additional Details			
8-16 SA MW KS CL IM DM II STUD140 KB PET179S1			

Fields:

UCC Serial No

Enter the UCC Standard Shipping serial number.

Shipper's Reference

Enter the shipper's reference. This is a free format field.

Carrier's Reference

Enter the carrier's reference. This is a free format field.

Assigned Pack ID

Enter the assigned pack ID. This is a free format field and is displayed when in **F15=Show /Hide Additional Details** is selected.

Size Of Suppliers Units

Enter the size of the suppliers units. This is a free format field and is displayed when **F15=Show/Hide Additional Details** is selected.

UOM

Enter the unit of measurement. This field is displayed when in **F15=Show/Hide Additional Details** is selected.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details window.

Functions:

F15

Show/Hide Additional Details. Select this function to toggle between Show and Hide Additional Details mode.

Additional 856 Item Details Window



Enter 1 in the Sel field of the Additional Item Level Details option on the Additional 856 Details window to display the Additional 856 Item Details window.

AS410 ST - Style Test & QA Company User GBJBARW2 12/11/97 12:16:33

ASN M

Consi

Custo

Mode

Despa

Est.

Suppl

Plant

Final

Addit

Freig

Carri

Vehic

Trail

ASN m

Additional 856 Item Details

Sel	Item	Description
1	K3	0016 Three Dimension NAVY
	K3	0027 Three Dimension RED

1=Select

F12=Previous

F3=Exit F4=Prompt F8=Update F10=Additional 856 Details F12=Previous
F14=Weights & Totals F15=Items F21=Name & Addresses F22=856 Text

7-11 SA MW KS CL IM DM II STUD140 KB PET179S1

Fields:

Sel

Select. The following options are available:

1 - Select. Enter 1 against the item you want to add additional 856 ASN details to.



Enter 1 in the Sel field and press **Enter** to display the 856 Additional Item Level Details screen.

856 Additional Item Level Details Screen



Enter 1 in the Sel field on the Additional 856 Item Details window and press **Enter** to display the 856 Additional Item Level Details screen.

AS267	ST - Style Test & QA Company	User GBJBARW2	12/11/97 12:23:21
856 Additional Item Level Details			
Shipment Number ... 00001001		Hierarchical Structure S T O I P	
Item	K3 0016	Three Dimension	NAVY
Size of Supplier Units in a Pack		UOM .?..	—
Number of Customer Selling Units per Pack ..		—	
Item Dimensions Unit of Measure		?.	—
Item Chemistry Unit of Measure		?.	—
Item Shipment Status		?.	—
Item Expiration Date		—	
<u>Premium Transport</u>			
Reason for use Code		?.	—
Responsibility for Excess		?.	—
Authorisation for Excess		—	
F3=Exit F4=Prompt F8=Update F9=Pack Type Summary F10=Measurements F12=Previous			
7-47	SA	MW KS CL IM DM II	STUD140 KB PET179S1

Fields:

Size Of Supplier Units In A Pack

Enter the size of supplier units in a pack.

This field must be filled when a value is entered in the UOM field.

UOM

Enter the unit of measurement code.

This field must be filled when a value is entered in the Size of Supplier Units In A Pack field.

Number Of Customer Selling Units Per Pack

Enter the number of customer selling units per pack.

Item Dimensions Unit Of Measure

Enter the item dimensions unit of measure code.

Item Chemistry Unit Of Measure

Enter the item chemistry unit of measure code.

Item Shipment Status

Enter the item shipment status code.

Item Expiration Date

Enter an item expiration date. This must be a valid future date.

Premium Transport

Reason For Use Code

Enter the code corresponding to the reason for using the premium transport.

Responsibility For Excess

Enter the code corresponding to the party responsible for the excess charges relating to the use of premium transport.

Authorisation For Excess

Enter the authorisation reference. This is a free format field.



Select **F8=Update** to validate the data you have entered and display the 856 Item Details select screen.

Functions:

F9

Pack Type Summary. This window allows you to add and maintain additional pack summary data. For further information, refer to the Company Items Default Pack Type Summary window in the Maintenance section.

F10

Measurements. This window allows you to add and maintain item measurement data. For further information, refer to the 856 Item Measurements Screen 2 in the Maintenance section.

856 References Screen

This screen allows you to add specific reference details to any level of the 856 ASN hierarchical structure. When the screen is first displayed, only the hierarchical structure fields in the top left hand corner are shown. For more information on setting up the hierarchical structure, refer to the Company ASN And Pack Details screen in the Maintenance section.

The system calculates the level that you want to add data to by a combination of identifiers. In order to add reference details to a specific level, you must enter a value in the levels above and including the level you require. The Shipment Number is automatically displayed. For example, when you want to enter details against the third level of the hierarchical structure, you must fill in the second and third level values and when you want to enter details against the fourth level, you must fill in the second, third and fourth level values.

When you have selected the level you require, press **Enter** and further fields are displayed.



Enter 1 in the Sel field of the References option on the Additional 856 Details window to display the 856 References screen.

AS265	ST - Style Test & QA Company	User GBJBARW2	12/11/97 12:24:54
856 References			
Shipment Number	00001001	Hierarchical Structure S T O I P	
Tare Reference ...?.			
Order/Contract ...?.			
Item			
Pack			
Pack Type			
Input for Order/Pack Type or Item/Pack Type References Only			
F3=Exit F4=Prompt F12=Previous			
5-23	SR	MW KS CL IM DM II	STUD140 KB PET179S1

Fields:

Shipment Number

The system automatically displays the shipment number.

Tare Reference

Enter the tare reference code.

Order/Contract

Enter order contract code.

Item

Enter the item code.

Pack

Enter the pack code.

Pack Type

Enter the pack type code. This code is only valid when the data being entered is at item or order level.

Sel

Select. The following options are available:

4 - Delete. Deletes a line.

Type

Enter the type code.

Reference

Enter the reference. This is a free format field.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details screen.

Functions:

F6

Add. This allows you to add a new line.

F14

Restart. This function ignores the data you have entered providing you have not select **F8=Update** and allows you to start again.

F15

Hide/Show Descriptions. Toggles between hiding/displaying the second line of the description.

Enter order contract code.

Item

Enter the item code.

Pack

Enter the pack code.

Sel

Select. The following options are available:

1 - More Details. Displays the 856 Charges And Allowances Additional Details window.

4 - Delete. Deletes a line.

Ind

Indicator. Enter an indicator code.

Type

Enter a type code.

Agency

Enter the agency code.

Code

Enter the charge code.

Amount

Enter the value. This is a free format field.



Select option 1 and press **Enter** on the 856 Charges And Allowances screen to display the 856 Charges And Allowances Additional Details window.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details screen.

Functions:

F6

Add. This allows you to add a new line.

F14

Restart. This function ignores the data you have entered providing you have not select **F8=Update** and allows you to start again.

856 Charges And Allowances Additional Details Window

This window allows you to enter additional charges and allowances data.



Select option 1 and press **Enter** on the 856 Charges And Allowances screen to display the 856 Charges And Allowances Additional Details window.

```
AS273                               Version 3 Demonstration Company   User QAUT01   18/07/97
                                      15:00:44

Advanced Shipping 856 Charges & Allowances
Shipment Number .... 00000001      Hierarchical Structure S T O I P
Tare Reference ..... 1
Order/Contract .....
Item
Pack
Sel 1
1
ASN 856 Charges & Allowances - Additional Details
Charge Percentage.....
Charge Percentage Based On .?. -
Charge Monetary Rate ..... UOM ? __
Charge Quantity .....
Free Quantity .....
Method of Handling Code ....?.
Reference .....
Option Number .....
Description .....
Allowance on Charge Number ...

F4=Prompt F12=Previous

1=More Details 4=Delete
F3=Exit F4=Prompt F6=Add F8=Update F12=Previous F14=Restart

09-40  SP MK KS IM II KENB20A PET178S2
```

Fields:

Charge Percentage

Enter the charge percentage value.

Charge Percentage Based On

Enter the charge percentage based on code.

Charge Monetary Rate

Enter the charge monetary rate code.

UOM

Enter the unit of measurement code.

Charge Quantity

Enter the charge quantity if the quantity the charge is based upon differs from the despatch quantity.

Free Quantity

Enter the quantity of free goods.

Method Of Handling Code

Enter the handling method code.

Reference

Enter a reference. This is a free format field.

Option Number

Enter an option number. This is a free format field.

Description

Enter a description. This is a free format field.

Allowance Or Charge

Enter an allowance or charge number. This is a free format field.



Press **Enter** to validate the data you have entered and display the 856 Charges And Allowances screen.

856 Hazardous Materials Screen

This screen allows you to add specific hazardous materials codes to any level of the 856 ASN hierarchical structure. When the screen is first displayed, only the hierarchical structure fields in the top left hand corner are shown. For more information on setting up the hierarchical structure, refer to the Company ASN And Pack Details screen in the Maintenance section.

The system calculates the level that you want to add data to by a combination of identifiers. The Shipment Number is automatically displayed as level one. In order to add hazardous materials code to a specific level, you must enter a value in the levels above and including the level you require. For example, when you want to enter details against the third level of the hierarchical structure, you must fill in the second and third level values and when you want to enter details against the fourth level, you must fill in the second, third and fourth level values.

When you have selected the level you require, press **Enter** and the remaining fields are displayed.



Enter 1 in the Sel field of the Hazardous Materials option on the Additional 856 Details window to display the 856 Hazardous Materials screen.

```
AS274                      Version 3 Demonstration Company   User QA AUT01   18/07/97
                                                                11:58:12

Advanced Shipping 856 Hazardous Materials
Shipment Number .... 00000001      Hierarchical Structure S T O I P
Tare Reference ..... 1
Order/Contract ..... 0000001
Item .....
Pack .....

Sel Qualifier and Class Code ?      Handling ?
- B ABCD FLAMMABLE AT 50 C AT 20,000 FT K1 k1
  DESCRIPTION : _____

4=Delete
F3=Exit  F4=Prompt  F6=Add  F8=Update  F12=Previous  F14=Restart

11-03  SF  MK  KS  IM  II  KENB20A  PET178S2
```

Fields:

Shipment Number

The system automatically displays the shipment number.

Tare Reference

Enter the tare reference code.

Order/Contract

Enter order contract code.

Item

Enter the item code.

Pack

Enter the pack code.

Sel

Select. The following options are available:

4 - Delete. Deletes a line.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details screen.

Functions:

F6

Add. This allows you to add a new line.

F14

Restart. This function ignores the data you have entered providing you have not select **F8=Update** and allows you to start again.

856 Product/Service Identification Screen

This screen allows you to add specific product/service identifiers to any level of the 856 ASN hierarchical structure. When the screen is first displayed, only the hierarchical structure fields in the top left hand corner are shown. For more information on setting up the hierarchical structure, refer to the Company ASN And Pack Details screen in the Maintenance section.

The system calculates the level that you want to add data to by a combination of identifiers. The Shipment Number is automatically displayed as level one. In order to add product/service identifiers to a specific level, you must enter a value in the levels above and including the level you require. For example, when you want to enter details against the third level of the hierarchical structure, you must fill in the second and third level values and when you want to enter details against the fourth level, you must fill in the second, third and fourth level values.

When you have selected the level you require, press **Enter** and the remaining fields are displayed.



Enter 1 in the Sel field of the Product/Service Identification option on the Additional 856 Details window to display the 856 Product/Service Identification screen.

AS275	Version 3 Demonstration Company	User QA AUT01	18/07/97 12:01:09
Advanced Shipping 856 Product/Service Identification			
Shipment Number	00000001	Hierarchical Structure S T O I P	
Tare Reference	1		
Order/Contract	00000001		
Item			
Pack			
Subline Id			
Sel Identifier Type ?		Identifier Code	
☒ BP Customer Item Code		<u>CCFD</u>	
4=Delete			
F3=Exit F4=Prompt F6=Add F8=Update F12=Previous F14=Restart			
12-03	SA	MK	KS IM II KENB20A PET178S2

Fields:

Shipment Number

The system automatically displays the shipment number.

Tare Reference

Enter the tare reference code.

Order/Contract

Enter order contract code.

Item

Enter the item code.

Pack

Enter the pack code.

Subline Id

Enter the subline identifier code.

Sel

Select. The following options are available:

4 - Delete. Deletes a line.

Identifier Type

Enter the identifier type code.

Identifier Code

Enter the identifier code which must be entered when the identifier type code has been added. This is a free format field.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details screen.

Functions:

F6

Add. This allows you to add a new line.

F14

Restart. This function ignores the data you have entered providing you have not select **F8=Update** and allows you to start again.

856 Product Characteristics Screen

This screen allows you to add specific product characteristics detail to any level of the 856 ASN hierarchical structure. When the screen is first displayed, only the hierarchical structure fields in the top left hand corner are shown. For more information on setting up the hierarchical structure, refer to the Company ASN And Pack Details screen in the Maintenance section.

The system calculates the level that you want to add data to by a combination of identifiers. The Shipment Number is automatically displayed as level one. In order to add reference details to a specific level, you must enter a value in the levels above and including the level you require. For example, when you want to enter details against the third level of the hierarchical structure, you must fill in the second and third level values, and when you want to enter details against the fourth level, you must fill in the second, third and fourth level values.

When you have selected the level you require, press **Enter** and the remaining fields are displayed.



Enter 1 in the Sel field of the Product Characteristics option on the Additional 856 Details window to display the 856 Product Characteristics screen.

AS276	Version 3 Demonstration Company	User QA AUT01	18/07/97
			12:03:51
Advanced Shipping 856 Product Characteristics			
Shipment Number	00000001	Hierarchical Structure S T O I P	
Tare Reference	1		
Order/Contract	00000001		
Item			
Pack			
Sel	Desc.	Type ?	Charac. Code ?
-	A	Fixed 15	A01 Coating
	Desc. :		Agency ?
			01 First Agen A001
			Description Code ?
			Position Code ? : _
4=Delete			
F3=Exit F4=Prompt F6=Add F8=Update F12=Previous F14=Restart			
11-03	SA	MK	KS
	IM	II	KENB20A PET178S2

Fields:

Shipment Number

The system automatically displays the shipment number.

Tare Reference

Enter the tare reference code.

Order/Contract

Enter order contract code.

Item

Enter the item code.

Pack

Enter the pack code.

Sel

Select. You can enter the following options:

4 - Delete. Deletes a line.

Desc Type

Enter the description type code.

Charac Code

Enter the character code.

Agency

Enter the agency code.

Description Code

Enter the description code. You must enter this code or the description in the Desc field.

Desc

Enter the description. You must enter the description or enter the code in the Description Code field.

Position Code

Enter the position code.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details screen.

F6

Add. This allows you to add a new line.

F14

Restart. This function ignores the data you have entered providing you have not selected **F8=Update** and allows you to start again.

856 Subline Details Screen

This screen allows you to add specific subline details to any level of the 856 ASN hierarchical structure. Subline information is normally added to the Pack or Item levels.

When the screen is first displayed, only the hierarchical structure fields in the top left hand corner are shown. For more information on setting up the hierarchical structure, refer to the Company ASN And Pack Details screen in the Maintenance section.

The system calculates the level that you want to add data to by a combination of identifiers. The Shipment Number is automatically displayed as level one. In order to add details to a specific level, you must enter a value in the levels above and including the level you require. For example, when you want to enter details against the third level of the hierarchical structure, you must fill in the second and third level values, and when you want to enter details against the fourth level, you must fill in the second, third and fourth level values.

When you have selected the level you require, press **Enter** and the remaining fields are displayed.



Enter 1 in the Sel field on the Additional 856 Details window to display the 856 Subline Details screen.

AS277	Version 3 Demonstration Company	User QAAUT01	18/07/97		
			12:08:00		
Advanced Shipping 856 Subline Details					
Shipment Number 00000001		Hierarchical Structure S T O I P			
Tare Reference 1					
Order/Contract					
Item					
Pack					
Sel	Subline Id	Rel. To Line ?	Despatch Qty	UOM ?	Unit Price
-	SUMMARY	B Both	10.000	BT Bottles o	25.00000
Price Basis ? : C Current		Rel. To Line Price ? : B Both			
1=Subline Identifiers 4=Delete					
F3=Exit F4=Prompt F6=Add F8=Update F12=Previous F14=Restart					
11-03	SA	MK	KS	IM	II KENB20A PET178S2

Fields:

Shipment Number

The system automatically displays the shipment number.

Tare Reference

Enter the tare reference code.

Order/Contract

Enter order contract code.

Item

Enter the item code.

Pack

Enter the pack code.

Sel

Select. The following options are available:

1 - Subline Identifiers. Displays the 856 Product/Service Identification screen which allows you to add up to ten identifiers to each subline.

4 - Delete. Deletes a line.

Subline Id

Enter the unique subline identifier. This field is mandatory.

Rel To Line

Relationship to line. Enter the relationship to line code.

Despatch Qty

Enter the quantity to despatch. This field is mandatory.

UOM

Enter the unit of measurement.

Unit Price

Enter the unit price. This is a free format field and is optional.

Price Basis Code

Enter the price basis code.

Rel To Line Price

Enter the relationship to line price code.



Enter 1 in the Sel field to display the 856 Product/Service Identification screen.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details screen.


Functions:

F6

Add. This allows you to add a new line.

F14

Restart. This function ignores the data you have entered providing you have not select **F8=Update** and allows you to start again.



4 - Delete. Deletes a line.

Identifier Type

Enter the identifier type code.

Identifier Code

Enter the identifier code. This is a free format field.



Note: Both fields must be filled.



Press **Enter** to validate the data and display the 856 Subline Details screen.

Functions:

F6

Add. This allows you to add a line.

F14

Restart. This function ignores the data you have entered providing you have not selected **F8=Update** and allows you to start again.

856 VICS Product Marks/Package Specifications Screen

This screen allows you to add specific product/package marks details to any level of the 856 ASN hierarchical structure. This information is normally added to item or pack levels.

When the screen is first displayed, only the hierarchical structure fields in the top left hand corner are shown. For more information on setting up the hierarchical structure, refer to the Company ASN And Pack Details screen in the Maintenance section.

The system calculates the level that you want to add data to by a combination of identifiers. The Shipment Number is automatically displayed as level one. In order to add product/package marks details to a specific level, you must enter a value in the levels above and including the level you require. For example, when you want to enter details against the third level of the hierarchical structure, you must fill in the second and third level values, and when you want to enter details against the fourth level, you must fill in the second, third and fourth level values.

When you have selected the level you require, press **Enter** and the remaining fields are displayed.



Enter 1 in the Sel field of the VICS Product Marks/Package Specification option on the Additional 856 Details window to display the 856 VICS Product Marks/Package Specifications screen.

AS278	Version 3 Demonstration Company	User QAUT01	18/07/97
			12:09:42
Advanced Shipping 856 VICS Product Marks/Package Specifications			
Shipment Number		00000001	Hierarchical Structure S T O I P
Tare Reference		1	
Order/Contract			
Item			
Pack			
Sel Product/Package Mark ?			
- AS		as	
4=Delete			
F3=Exit F4=Prompt F6=Add F8=Update F12=Previous F14=Restart			
11-03 SP MK KS IM II KENB20A PET178S2			

Fields:

Shipment Number

The system automatically displays the shipment number.

Tare Reference

Enter the tare reference code.

Order/Contract

Enter order contract code.

Item

Enter the item code.

Pack

Enter the pack code.

Sel

Select. The following options are available:

4 - Delete. Deletes a line.

Product/Package Mark

Enter the product/package mark code.



Select **F8=Update** to validate the data you have entered and display the Additional 856 Details screen.

Functions:

F6

Add. This function allows you to add a new line.

F14

Restart. This function ignores the data you have entered providing you have not select **F8=Update** and allows you to start again.

856 Maintenance Weights And Totals Screen (F14)

This screen will allow you to overwrite the system calculated 856 ASN totals (calculated from all the packs and pallets on the ASN). The system calculates and creates all pack & pallet records (into a work file) for the consignment. It then summarises Consignment Pack & Pallet Totals and allows user overrides of total figures.



Select **F14=Weights And Totals** on the 856 Maintenance Header screen to display the 856 Maintenance Weights And Totals screen.

AS415		Version 3 Demonstration Company		User QAAUT01	14/07/97
856 Maintenance - Weights & Totals					
Consignment Number .. 000000001		CHG QA STD 856			
Customer CG01 000		Automotive customer			
Despatch Date 11/06/97		31 Lenton Boulevard			
Weight UOM		Despatch time .. 0:00			
		Volume UOM			
Pallet Type	No. of Pallets	No. of Packs	Net Weight	Gross Weight	Volume
QAP	17	34	2.000	119.000	17.000
Calculated	17	34	2.000	119.000	17.000
Actual			2.000	119.000	17.000
Vehicle Capacity				0	0
Percentage Used				0	0
F3=Exit F12=Previous					
19-30	SF	MA	KS	IM	II KENB20A PED201S2

Fields:

Pallet Type

The pallet type for this contract is taken from the customer / item / pack / pallet details file.

No Of Pallets

The calculated number is based on the contract and customer / item / pack / pallet details file.

No Of Packs

The calculated number is based on the contract and customer / item / pack / pallet details file.

Net Weight

The calculated number is based on the contract and customer / item / pack / pallet details file.

Gross Weight

The calculated number is based on the contract and customer / item / pack / pallet details file.

Volume

The calculated number is based on the contract and customer / item / pack / pallet details file.

Calculated

Calculated Totals. This represents the system calculated totals for this consignment.

Actual

Actual Totals. These fields default to the system calculated values but may be overridden.

Vehicle Capacity

These fields default to the system calculated values but may be overridden.

Percentage Used

This is calculated by the system.



Press **Enter** to validate the screen and display the 856 Maintenance Header screen.

856 Maintenance Item Summary Screen (F15)

This screen displays the Items, Contracts, Lots, Despatch Quantities, Kanbans and Call Off/RAN references on an 856 ASN. There are two modes of operation for this screen. In restricted mode you cannot amend the item details themselves, this screen is used to select items to maintain packaging details.

In amend mode you can change all the details, including quantities. Such amendments can create data integrity issues - as you must put through separate amendments to invoice, stock, order and contract details. Access to amend mode is therefore controlled by a function key (**F9=Restricted Mode**) which has user level authority attached to it. In amend mode you can automatically regenerate packaging details. When you are in amend mode the system will display the following message on the screen - 'Changes will not update Invoice, stock, order or contract details'.



Select **F15=Items** on the 856 Maintenance Header screen to display the 856 Maintenance Item Summary screen.

```

AS420          ST - Style Test & QA Company      User GBJBARW2   12/11/97
                                           12:36:25

856 Maintenance - Item Summary

Consignment number .. 00001001      PARCELS****
Customer ..... All      000      House of Fraser
                                   Head Office
Despatch date ..... 5/09/97      Despatch time ..... 0:00

Sel Item      Order ?   Lot
  █ K3        0016
  - K3        0027

Despatch Qty   Kanban
      50.000
      50.000

1=Item pallet summary 2=856 Codes
F3=Exit F8=Verify details F12=Previous F15=Expand/summary

11-3      SP      MW      KS CL IM DM II      STUD140      KB      PET179S1
  
```

Fields:

Sel

Select. The following options are available:

- 1 - Item Pallet Summary. Displays the 856 Maintenance Item Pallet Summary screen.
- 2 - 856 Codes. Displays the 856 Additional Item Level Details screen.
- 4 - Delete. Deletes an item entry. This option is not available in restricted mode.

Item

The system displays the item code. The description is displayed below when **F15=Expand/Summary** is selected.

Contract

Enter the contract number.

Lot

Enter the lot number.

Despatch Qty

Enter the quantity to be despatched.

Kanban

Enter the Kanban reference code.



Press **Enter** to display the 856 Maintenance Header screen.


Functions:

F6

Add. This allows you to add a new line. The system will display a window with the input fields. Item, Order / Contract and Quantity are mandatory fields.

F15

Expand/Summary. This is a toggle switch which either shows or hides the second line of information.

**Fields:**

Select. The following options are available:

- 1 - Details. Displays the 856 Maintenance Pallet Details screen.
- 2 - 856 Codes. Displays the 856 Additional Tare Container References screen.
- 4 - Delete. Deletes a line.

Enter the unique tracking reference for this pallet.



F6

Add Pallet. This allows you to create a new pallet record, assigning the next pallet number, but allowing amendment. The pallet must be unique within a consignment. The input fields are displayed in a window.

Expand/Summarise. This toggles between displaying/hiding pallet descriptions.

F17

Consignment Pack Enquiry. This is an enquiry screen designed to provide details of pallets and packs on a consignment, when you are adding new packaging details.

856 Maintenance Pallet Details Screen (Option 1)

This screen allows you to maintain the pack range details associated with the selected pallet/item. You can maintain 'actual' weights, volumes, and quantities or select the range to amend.



Enter 1 in the Sel field on the 856 Maintenance Item Pallet Summary screen to display the 856 Maintenance Pallet Details screen.

```

AS435                      Version 3 Demonstration Company   User QAUT01   14/07/97
                                           13:14:01

856 Maintenance - Pallet Details

Consignment number .. 00000001      CHG QA STD 856
Customer ..... CG01      000      Automotive customer
                                           31 Lenton Boulevard
Despatch date ..... 11/06/97      Despatch time ..... 0:00
Pallet ..... 1      Pallet type ..... QAP
Item ..... CGQA1      Despatch Qty ..... 102.000
Contract ..... 00000001      Ref.
Lot .....

Sel From Pack   To Pack Type Net Wt      Gross Wt      Volume      Qty/Pack
-              1          2 QAB      1.000      1.000      1.000      3

1=Amend additional details  2=856 Codes  4=Delete
F3=Exit  F6=Add pack range  F8=Verify details  F12=Previous
F17=Consignment pack enquiry
      15-03      SA      MK      KS      IM      II  KENB20A  PED201S2
  
```

Fields:

Sel

Select. The following options are available:

1 - Amend Additional Details. Displays the 856 Maintenance Pack Details screen which allows you to maintain item and pack details associated with the selected pack.

2 - 856 Codes. Displays the 856 Additional Pack References screen.

4 - Delete. Deletes a pack range.

From/To Pack

The beginning and end pack numbers which have identical weight, volume etc.

Type

The pack type description from the pack file.

Net Wt

This displays the 'actual' net weight of the pack, and will be the same as the calculated net weight unless it has been manually overridden.

Gross Wt

This displays the 'actual' gross weight of the pack, and will be the same as the calculated gross weight unless it has been manually overridden.

Volume

This displays the 'actual' volume of the pack, and will be the same as the calculated volume unless it has been manually overridden.

Qty/Pack

Shows the quantity of the item in each pack.



Select **F8=Verify Details** to verify the data and display the No Discrepancies window or the Packaging Discrepancies screen.

Functions:

F6

Add Pack Range. This allows you to add additional item packs to the pallet. The 856 Maintenance Pack Details screen is displayed for you to enter the new details.

F8

Verify Details. This verifies that the total quantity assigned to the packs / pallets is equal to the quantity being despatched. When F8=Verify Details is selected either a window will be displayed confirming that there are no discrepancies, or the Packaging Discrepancies screen will be displayed. For more information, refer to the ASN Maintenance Packaging Discrepancies Screen in the Processing option.

F17

856 Maintenance Consignment Pack Enquiry. This is an enquiry screen designed to provide details of pallets and packs on a consignment, when you are adding new packaging details.

856 Maintenance Pack Details Screen (Option 1/F6)

This screen allows you to maintain the item and pack details associated with the selected pack. It is mainly display, but does allow update on some fields. This screen can be used for entering Pack Marks, Kanban details and amending Lots.



Enter option 1 in the Sel field on the 856 Maintenance Pallet Details screen to display the 856 Maintenance Pack Details screen.



Select **F6=Add Pack Range** to display the 856 Maintenance Pack Details screen.

AS440		ST - Style Test & QA Company		User GBJBARWZ		12/11/97 12:40:55	
856 Maintenance - Pack Details							
Customer	A11	000	House of Fraser				
Consignment Number ..	00001001		Head Office				
Item Reference	K3	0016	Contract Ref.				
Call Off Ref			Three Dimension NAVY 6				
Stockroom	?						
Lot No							
Rotation Date	0/00/00		Workstation				
Pallet Ref	1		Pallet Type				
Packs	1	to 1	PAL Standard Pal				
Pack Quantity	10		Pack Type				
Pack Gross Wt (Calc)...	1.000		BOX Standard Box				
Pack Net Wt (Calc)...	.000		Pack Gross Wt (Act)...				
Pack Volume (Calc)...	1.000		20.000				
Pack Marks			Pack Net Wt (Act)...				
Kanban Card Ref			20.000				
			Pack Volume (Act)...				
			1.000				
F3=Exit F4=Prompt F12=Previous F17=Consignment Pack Details							
10-24 SP MW KS CL IM DM II STUD140 KB PET179S1							

Fields:

Call Off Ref

This is the call off reference number.

Stockroom

This is the stockroom code for the item.

Lot No

This is the lot number for the item.

Rotation Date

This is the rotation date for the item.

Workstation

This is the workstation which generated the pallet details.

Pallet Ref

This is the pallet reference number which is a unique identifier for the pallet.

Pallet Type

This is the pallet type code.

Packs

These are the pack reference numbers for the packs in this pallet. These are unique identifiers for each pack.

Pack Type

This is the pack type code used to describe the way in which the item is packed. The **F4=Prompt** key is available.

Pack Quantity

This is the number of items in a pack.

Pack Gross Wt (Calc)

This is the calculated gross weight of the pack.

Pack Gross Wt (Act)

This is the actual gross weight of the pack.

Pack Net Wt (Calc)

This is the calculated net weight of the pack.

Pack Net Wt (Act)

This is the actual net weight of the pack.

Pack Volume (Calc)

This is the calculated pack volume.

Pack Volume (Act)

This is the actual pack volume.

Pack Marks

This identifies particular groups of packs in a consignment.

Kanban Card Ref

This is the Kanban reference card code.



Press Enter to update the data and display the 856 Maintenance Pallet Details screen.

Functions:

F17

Consignment Pack Details screen. Select this function to display pallet and pack details for a consignment on the 856 Maintenance Consignment Pack Enquiry screen.

856 Maintenance Consignment Pack Enquiry Screen (F17)

This is an enquiry screen designed to provide pallet and pack details for a consignment when you are adding new packaging information.

-  Select **F17=Consignment Pack Details** on the 856 Maintenance Pack Details screen to display the 856 Maintenance Consignment Pack Enquiry screen.
-  Select **F17=Consignment Pack Enquiry** on either the 856 Maintenance Item Pallet Summary or 856 Maintenance Pallet Details screens to display the 856 Maintenance Consignment Pack Enquiry screen.

AS470	ST - Style Test & QA Company	User GBJBARW2	12/11/97
			12:41:41
856 Maintenance - Consignment Pack Enquiry			
Consignment		00001001	PARCELS****
Last Pallet Number Used ..		5	Last Pack Number Used .. 10
Pallet Type	Pallet Reference	Pack Type	From Pack To Item Pack Lot
PAL	1	BOX	1 1 K3 0016
PAL	2	BOX	2 2 K3 0016
PAL	3	BOX	3 3 K3 0016
PAL	4	BOX	4 4 K3 0016
PAL	5	BOX	5 5 K3 0016
PAL	5	BOX	6 6 K3 0027
PAL	5	BOX	7 7 K3 0027
PAL	5	BOX	8 8 K3 0027
PAL	5	BOX	9 9 K3 0027
PAL	5	BOX	10 10 K3 0027
F12=Previous			
1-1	SA	MW	KS CL IM DM II STUD140 KB PET179S1

Fields:

Pallet Type

This field is for your information only and cannot be amended.

Pallet Reference

This field is for your information only and cannot be amended.

Pack Type

This field is for your information only and cannot be amended.

From Pack

This field is for your information only and cannot be amended.

To Pack

This field is for your information only and cannot be amended.

Pack

This field is for your information only and cannot be amended.

Lot

This field is for your information only and cannot be amended.



Press **F12=Previous** to display the previous screen.


```
AS425                               Version 3 Demonstration Company   User QA AUT01    14/07/97  
                                     14:19:38
```

BSE Maintenance - Name and Addresses

```
Consignment Number .. 00000001      CHG QA STD BSE  
Customer ..... CG01          000 Automotive customer
```

Sel Type Code ?		Address Code ?	Override
<u>1</u>	CGEE Consignee (Delivery Customer)	CGEE01	
-	PLNO Plant Number	PLN001	
-	FDEL Final Delivery Point	FDEL01	
-	ADES Additional Destination Details	ADES01	
-	FFWD Freight Forwarder	FFWD01	
-	CARR Transport Carrier Company	CARR01	

+
1=Details 4>Delete
F3=Exit F4=Prompt F12=Previous

Selections have been abandoned by pressing F12

2-63

Override

This field displays a + when the code has been overridden.



Enter 1 in the Sel field on the first 856 Maintenance Name And Addresses screen and press **Enter** to display the second screen.

856 Maintenance Name And Addresses Screen 2 (Option 1)

This screen displays full details for a selected code, and allows you to make changes to the name and address as required.



Enter 1 in the Sel field on the first 856 Maintenance Name And Addresses screen and press **Enter** to display the second screen.

AS425	Version 3 Demonstration Company	User QAUT01	14/07/97 14:21:19
856 Maintenance - Name and Addresses			
Consignment	00000001	CHG QA STD 856	
Despatch Date	11/06/97	Despatch Time	:00
Type code.....	CGEE	Consignee (Delivery Customer)	
Address code.....	CGEE01		
Name.....	Consignee (delivery customer) 01		
Address line 1.....	line1		
Address line 2.....	line2		
Address line 3.....	line3		
Address line 4.....	line4		
Address line 5.....	line5		
Post code.....		Country Code?	
Telephone number....		Extension number...	
Fax number.....		Internal ID.....	
Telex number.....		Teletext number....	
Contact name.....			
Department code.....			
Comments.....			
F3=Exit F4=Prompt F12=Previous			
08-23	SE	ML	KS IM II KENB20A PED201S2

Fields:

Type Code

This is the address type code which was entered previously.

Address Code

This is the address code which was entered previously.

Name

Enter the name. This field is mandatory.

Address Line 1

Enter the first line of the required address. This field is mandatory.

Address Line 2

Enter the second line of the required address.

Address Line 3

Enter the third line of the required address.

Address Line 4

Enter the fourth line of the required address.

Address Line 5

Enter the fifth line of the required address.

Post Code

Enter the post code.

Country Code

Enter the country code.

Telephone Number

Enter the telephone number required.

Extension Number

Enter the internal extension number required.

Fax Number

Enter the fax number required.

Internal ID

Enter a suitable Internal ID code.

The internal ID field allows for an additional code which identifies the address type by some alternative code, for example one which has been mutually agreed between the consignee and consignor.

Telex Number

Enter the required telex number.

Teletext Number

Enter the required teletext number.

Contact Name

Enter the contact name as required.

Department Code

Enter the department code for the contact as required.

Comments

This is a free format field. Enter any required comments.



Press **Enter** to validate the screen, then press **Enter** again to save the new details after saving the new details and display the previous screen.

856 Text Window (F22)

This window allows you to maintain external text each 856 ASN consignment.



Select **F22=856 Text** on the 856 Maintenance Header screen to display the 856 Text window.

AS410		Version 3 Demonstration Company		User QAAUT01	14/07/97
					14:45:35
Advanced Shipping 856 Maintenance - Header					
Consignment number... 00000001		CHG QA STD 856			
Customer..... CG01		000	Automotive customer		
		31 Lenton Boulevard			
		Road			
Mode of transport.....?.. 3					
Despatch date..... 11/06/97					
Est. arrival date.... 23/07/97					
Supplier code.....?..					
Plant number.....?.. PLN001					
Final delivery point..?.. FDEL01					
Additional dest. code.?.. ADES01					
Freight forwarder.....?.. FFWD01					
Carrier code.....?.. CARR01					
Vehicle registration.....					
Trailer reference.....					
ASN map sequence & 856 hierarchic					

Lin	External Text
1	
2	
3	
4	
5	
6	

Position to	Insert	after
Delete	from	

F5=Refresh F8=Update F12=Previous

F3=Exit F4=Prompt F8=Update F10=Additional 856 Details F12=Previous
 F14=Weights & Totals F15=Items F21=Name & Addresses F22=856 Text
 12-42 S2 MK KS IM II KENB20A PED201S2

Fields:

Lin

Line Number. This field is for your information only and cannot be amended.

External Text

Enter text on each line as required.

Position To

Enter the line number you want to display at the top of the screen.

Insert

Enter the number of blank lines you want to insert, and the line number after which they should be inserted.

Delete

Enter the number of lines you want to delete, and the line number from which you want to start the delete.



Select **F8=Update** to update the text file and display the 856 Maintenance Header Screen.

Resend, Replace or Send Cancellation



3/STASP

This option lists 856 ASNs which have either already been sent, or cancelled via the Maintenance & Send option. You can maintain the details or resend the 856 ASN.

The Resend ANSIX12 856s selection screen is the same as the ANSIX12 856s Maintenance & Send screen except it only lists 856 ASNs which have previously been sent or cancelled. The maintenance functions are identical, and re-sending an 856 ASN works in exactly the same way as sending an 856 ASN.

The Resend screens do not provide a cancel facility, or a Manual Add 856 ASN facility. 856 ASNs may be sent / resent up to eight times.