

-
-
-
-
-

Chapter 1

Maintenance



Maintain Documents



1/AIM



Select Maintain documents on the menu to display the Maintain Document IDs screen.

Use this option to define the types of documents that can be sent to and from the EDI network and the System 21 database e.g. purchase order, sales invoice.

Within this, the document ID must be defined for each EDI message standard used e.g. the most common ones for purchase orders are:

Document ID	Type	Standard
ORDFL ORDERS 850 ORDERR	PO	Tradacoms EDifact ANSI X12 Odette

So, if purchase orders are sent to some suppliers via Tradacoms and others via EDIFACT, they should both be defined via this option.

When passing documents into EDI/400, the module uses these document IDs to determine which standard messages are to be used.



Note: Once entered, these documents IDs will be shared by all companies defined to the module.

Maintain Document IDs Screen 1



Select Maintain Documents to display the first Maintain Document IDs screen.

Select the document type to be maintained.

```

AI005                                     User GBJBAJNO   14/08/97
                                           10:31:17

Maintain Document IDs

Document type . . . . █ 1=Orders
                        2=Order acknowledgements
                        3=Despatch advice
                        4=Invoices
                        5=Credits
                        6=Customer schedules
                        7=Vendor schedules
                        8=Intrastat/ESL report
                        9=Advanced shipment notice (ASN)
                       10=Payment order/Remittance Advice
                       11=Price Sales Catalog
                       12=Order Status Report
                       13=Lockboxes

F3=Exit

-----
5-24  SA  MW  KS  CL  IN  DN  II  EDN400H  KB  PET178S1
  
```

Fields:

Document Type

Enter a valid document type in the range, as follows:

- 1 - Orders
- 2 - Order Acknowledgements
- 3 - Despatch Advice
- 4 - Invoices
- 5 - Credits
- 6 - Customer Schedules
- 7 - Vendor Schedules
- 8 - Intrastat/ESL Report
- 9 - Advanced Shipment Notice (ASN)
- 10 - Payment Order/Remittance Advice (Tradacom Document Types 820 for sending and receiving.)
- 11 - Price Sales Catalogue
- 12 - Order Status Report
- 13 - Lockboxes (Tradacom Document type 823 for receiving payment advice.)



Select an option in the Document Type field on the first Maintain Document IDs screen to display the second maintenance screen.

Maintain Document IDs Screen 2



When you enter an option in the Document Type field on the first Maintain Document IDs screen, the second screen is displayed.

This screen enables all document IDs to be defined, one per message standard, for the selected document type.

AI005		User GBJBAPH2	30/11/95
			10:35:34
Maintain Document IDs			
Document type Advanced shipment notice (ASN)			
Document ID	Type	Description	
AVIEXP	—	Advanced shipment notice (ASN)	
	—		
	—		
	—		
	—		
	—		
	—		
	—		
	—		
	—		
	—		
	—		
F3=Exit F12=Cancel			
09-02	SF	MW	KS IM II KENB20A PET087S1

Fields:

Document ID

The document ID, as defined by the relevant EDI standards organisation, must be entered for each standard (Tradacoms, EDIFACT etc.) to be used. This is what the translator calls this document.

Type

Some standards, ANSI X.12 in particular, require that the Document ID is appended by a document type. This should be left blank for other standards.

The Document ID and Type are not validated as the number of standard documents is constantly growing, and indeed trading partners may create their own document standards. Any invalid document references will simply be ignored.

Description

This may be entered for information only.



Press **Enter** to save the new entries to the database.

Maintain Trading Partners



2/AIM



Select Maintain Trading Partners to display the first Maintain Trading Partners screen.

All trading partners, either customers or suppliers, who are to be sent EDI documents must be defined via this option.

Within this, the document types to be sent to this particular partner must be selected. The document types displayed will be restricted to those defined via the Maintain Documents option.

The print functions check if the supplier or customer is defined, via this option, as a trading partner for the relevant document. The decision to print the document or not is then based on the following table.

Document Active	In Production	Send Via EDI	Print
Yes	Yes	Yes	No
Yes	No	Yes	Yes
No	Yes	No	Yes
No	No	No	Yes



Note: Further trading partner details are required to handle the translation and communications aspects of EDI. These are maintained within the EDI/400 module.

Maintain Trading Partners Screen 1



Select Maintain Trading Partners to display the first Maintain Trading Partners screen.

This screen allows selection of a trading partner to be maintained.

```
AI006      Distribution V3 -> V3 Financials      User GBJBAPH2      27/10/95
                                                15:10:30

Maintain Trading Partners

Trading partner . . . . . ? _____

Based on trading partner. . ? _____

F3=Exit  F4=Prompt

05-32    SF    MW    KS    IM    II    KENB20A    PET158S1
```

Fields:

Trading Partner

Enter a valid customer, or supplier code, and sequence number. If adding a new partner, this may be selected from a standard prompt on Customers or Suppliers. If amending an existing partner, then a prompt is available on partners already defined via this option.

The sequence number for the trading partner corresponds to the location, where this document is to be transmitted.



Note: For invoices, this may be the delivery point or statement address (as defined to Sales Order Processing).

Based On Trading Partner

A new trading partner may be copied from an existing one by entering a valid partner or selecting one from the prompt.



Press **Enter** on the first Maintain Trading Partners screen to display the second screen.

Maintain Trading Partners Screen 2



Press **Enter** on the first Maintain Trading Partners screen to display the second screen.

This screen allows selection of documents to be sent to the selected partner, and is achieved by entering values in the corresponding Test/Production and Active/Inactive entries.

AI006		Z1 - UK Demonstration Company		User GBJBAJND		14/08/97	
						10:03:59	
Maintain Trading Partners							
Trading partner		EDISUP2 000		SDQ Required . . . 0		(0=No, 1=Yes)	
VAT Registration Number . . .		[REDACTED]					
EAN location Number		6					
Document name	Test/ production	Active/ inactive	Generation number	Tradacons standards			
Orders	1	1	1	1			
Despatch advices	1	1	0	1			
Invoices	1	1	0	-			
Vendor schedule	-	-	0	-			
Advanced shipment notice	-	-	0	-			
Payment Order/Remittance Advice	1	1	0	-			
Credits	1	1	0	-			
Lockboxes	1	1	0	-			
F3=Exit F11=Delete F12=Cancel F16=EDI partner maintenance							
9-53 SA HW KS CL IM DM II EDN4000 KB PET178S1							

Fields:

Trading Partner

The name of the trading partner is displayed for your information only and cannot be amended.

VAT Registration Number

You can enter the VAT registration number of the trading partner in this field.



This field is not displayed if the current country code is USA.

SDQ Required

You can decide whether or not outbound invoices and credits require Specified Destination Quantity (SDQ) details. You can enter one of the following:

0 - No. SDQ is not required.

1 - Yes. SDQ is required.

EAN Location Number

You can enter the European Article Number (EAN) location number of the trading partner in this field.



This field is not displayed if the current country

code is USA.

Document Name

The follow documents may be listed:

- Orders
- Order Acknowledgements
- Despatch Advices
- Invoices
- Intrastat/ESL
- Customer Schedule
- Vendor Schedule
- Advanced Shipment Notice
- Payment Order / Remittance Advice. (Tradacom Document Types 820). Note: If an EDI payment method is used and this item is active then remittance details will be sent to the supplier via EDI i.e. no paper remittances will be produced. If inactive, payment advice details will be sent to the bank and remittance prints may be produced
- Credits
- Price Sales Catalogue
- Order Status Report. Not implemented.
- Lockboxes. Receive lockbox payment advices. (Tradacom Document type 823).

Test/Production

You can enter the following:

- 1 - Test. The document is in test, or parallel mode.
- 2 - Production. It is in full production.

Active/Inactive

You can enter the following:

- 1 - Active. The document is currently active.
- 2 - Inactive. Deactivates the document for a period of time whilst any current 'issues' are resolved, e.g. for communication line problems.

Generation Number

This displays the last file generation number used for this trading partner/document type combination.

Each time a file is sent to the trading partner containing this document type the file generation number is incremented by 1 and included in the transmitted message header for reference.

Tradacoms Standards

You can enter the following:

Blank - Do not use tradacoms standard.

1 - If the document is to be sent to this trading partner using Tradacoms standards.

Functions:

F11

Delete. If you want to delete the trading partner, select this option. Select **F11=Delete** again to confirm the deletion.

F16

EDI Partner Maintenance. Select this option to display the Trading Partner Maintenance screen. EDI/400 must be available on the system.



Press **Enter** to update the data file, or **F16=EDI Partner Maintenance** for partner maintenance.

Trading Partner Maintenance Screen (F16)



Select **F16=EDI Partner Maintenance** on the second Maintain Trading Partners screen to display the Trading Partner Maintenance screen.

This screen allows additional information to be maintained for the Trading Partner to enable documents to be exchanged via EDI. The additional information is necessary for translation into EDI message standards and communications to take place.

```

SED130-A                      Trading Partner Maintenance          30/11/95
                                Trading Partner Selection          10:44:58

Position to. . . . . Partner ID

Type options, press Enter.
  2=Change  3=Add duplicate  4=Delete  5=Print

Opt Net Document  S/R Partner ID      Partner Company          Sts
-  IA  ORDFL      R  3FEDICUST 000    EDI CUSTOMER              A
-  IA  DELINS     R  3FEDICUST 000    EDI CUSTOMER              A
-  IA  ACKFL      S  3FEDICUST 000    EDI CUSTOMER              A
-  IA  DELFL      S  3FEDICUST 000    EDI CUSTOMER              A
-  IA  INVFL      S  3FEDICUST 000    EDI CUSTOMER              A
-  IA  888      IG  S  3FEDICUST 000    EDI CUSTOMER              A
-  IA  INVFL      S  3FEDICUSTB000    EDI CUSTOMER IN GBP      A
-  IA  INVFL      S  3FEDICUSTB001    EDI CUSTOMER IN ITL      A
-  IA  INVFL      S  3FEDICUST2000    EDI CUSTOMER 2           A
-  IA  INVFL      R  3FEDISUPB000    EDI SUPPLIER IN ITL      A
-  IA  ACKFL      R  3FEDISUPP 000    EDI SUPPLIER             A
-  IA  INVFL      R  3FEDISUPP 000    EDI SUPPLIER             A +

F3=Exit  F12=Previous  F14=Add  F15=Extended display  F20=Print

10-03  SF  MW  KS  IM  II  KENB20A  PET007S1
  
```

Fields:

Partner ID

The partner ID must be structured as follows:

Positions:

1-2 = Company code

3-10 = Customer or supplier code

11-13 = Sequence number

14-15 = Blanks

This is necessary for translating external trading partner IDs for incoming documents into a form that the system will recognise.



Warning: Refer to the *EDI/400 User Guide* for details on defining trading partners to this application.



Note: The sequence number is only used if the documents received are for a single delivery location. For multiple locations, the Location References Maintenance option must be used to

define the location references.

Maintain Location References



3/AIM

When trading in a multiple location environment, it is necessary to be able to identify the location by a mutually agreed location reference.

For incoming documents, the alternative reference received in the EDI message is converted into the delivery address code for the customer.

For outgoing documents, the receiving address code is converted into the alternative reference code and output in the EDI message to the supplier.



Note: Location references are not required if the document exchange is between single locations.

Alternative Location References Maintenance Screen 1



When Maintain Location References is selected
the first Alternative Location References
Maintenance screen is displayed.

The screen enables selection of the trading partner to be maintained.

```
AI002      Distribution V3 -> V3 Financials      User GBJBAPH2      27/10/95
                                           15:10:10

Alternative Location References Maintenance

Trading partner . . . . . ? _____

F3=Exit  F4=Prompt

05-32    SF      MW      KS      IM      II  KENB20A  PET158S1
```


Fields:

Trading Partner

Enter a valid customer or supplier code. Alternatively, the partner may be selected via the appropriate prompt.



When **Enter** is pressed on the first Alternative
Location References Maintenance screen, the
second screen is displayed.



```

AI003                Z1 - GB Demonstration Company      User: GBJBACHG      30/10/97
                                                           9:35:04

Alternative Location References Maintenance

Trading partner . . . . . BCUS01      Bens Testing Customer
                                           External
Line  Loc  Alternative reference      Trading      Delete
      code
1  000  LOC1
2  001  LOC2

Line  Loc  Alternative reference      External Trading
      code      Partner ID
____  █  _____

F3=Exit  F5=Refresh  F8=Update  F12=Previous

_____
21-8      SA      HW      KS  CL  IM  DM  II      EDN400A      KB      PET178S1

```

This screen displays the selected trading partner and a list of locations under the Line, Location Code, Alternative Reference and External Trading Partner ID fields. You can add and edit locations on the list by entering details in the following fields:

Enter the corresponding number for the line to be amended or deleted.

Enter a unique delivery address or receiving address code for the Trading Partner.

Enter a unique code which represents the location and is recognised by both Trading Partners. This code is the one included in the EDI message.

You can enter the ID for an external trading partner for any location/alternative reference. The ID is placed into the outbound document header records so that the

trading partner identifier can be used by a third party other than the System 21 customer or supplier number.

If you leave this field blank, the default, which is normally used, is a combination of the company code, customer number and delivery sequence. You can enter your own ID for outbound documents.



Press **F8=Update** to update values on the database.

Maintain Company Profile

1...
2... 4/AIM

This option allows you to enter the VAT and EAN (European Article Number) location numbers for the company.

-  Select Maintain Company Profile to display the Maintain EDI Company Details screen.

AI001 Distribution V3 -> V3 Financials USER GBJBAPH2 30/11/95
10:55:25

Maintain EDI Company Details

Name.....

ACME Distribution Ltd

Address line 1....

Needles House

Address line 2....

Stratford Road

Address line 3....

Solihull

Address line 4....

West Midlands

Post Code.....

B91 8DS

VAT Number.....

EAN Location Number.....

F3=Exit

F8=Update

13-35

SF

MW

KS

IM

II

KENB20A

PET007S1

Fields:

VAT Number

Enter the company's VAT number. This is used for reporting purposes for SPEX and Intrastat.

EAN Location Number

Enter the EAN (European Article Number Association) location number of the company.

-  Press **F8=Update** to update the values in the database.


Maintain Common Codes Cross Reference



5/AIM

This option provides a means of translating customer code values to the equivalent System 21 code values. For example, a customer may call a unit of measure of thousands M but you may use TH. Common Codes Cross Reference intercepts and maps this inbound data from the customer to System 21 values. This option will also intercept and map outbound data from System 21 to the customer values.

The cross reference is used by routines processing EDI messages received from / sent to trading partners set up in the Trading Partner Maintenance option.




Fields:

Enter a code mapping standard identifier which groups together customers, groups of customers or whole EDI messages. Mapping codes are defined on the Inventory Descriptions file.

Enter a common code type identifier defined on the Inventory Descriptions file. This is the class of code that is to be translated to/from its System 21 value.

Enter a trading partner code when you want to define cross references specific to a trading partner. The trading partner must be an existing supplier/customer.



Common Codes Cross Reference Maintenance Screen 2

This screen displays existing cross reference data which you can amend. You can also add new cross reference data.



Press **Enter** from the first Common Codes Cross Reference screen to display the second Common Code Cross Reference Maintenance screen.

AI009	Z1 - GB Demonstration Company	User GBJBACHG	22/10/97
			10:34:02
Common Codes Cross Reference Maintenance			
Code Mapping Standard.... ANSI		ANSI X.12	
Common Code Type..... CNTRY		Country Code	
Trading Partner.....			
S21 Value	Alternate Value	Description	
GB	001		
USA	012		
1=Amend 4=Delete			
F3=Exit F6=Add F12=Previous			
10-2	SA	AW	KS CL IH DM II EDN4000 KB PET178S1

Fields:

Code Mapping Standard

This field is displayed from the first Common Code Cross Reference Maintenance screen and is for your information only.

Common Code Type

This field is displayed from the first Common Code Cross Reference Maintenance screen and is for your information only.

Trading Partner

This field is displayed from the first Common Code Cross Reference Maintenance screen and is for your information only.

S

Select. Enter one of the following:

1 - Amend. Displays the Amend Cross Reference window which allows you to make any changes to the line selected.

4 - Delete. Allows you to select a line to delete. The Confirm Delete window is displayed which allows you to confirm or cancel the deletion.

Functions:

F6

Add. Displays the Add New Cross Reference window which allows you to add further cross references.

Amend Cross Reference Window (Option 1)

This window allows you to amend existing cross reference data.



Select option 1 from the second Common Codes Cross Reference Maintenance screen to display the Amend Cross Reference window.

AI009	Z1 - GB Demonstration Company	User GBJBACHG	22/10/97 10:34:02
Common Codes Cross Reference Maintenance			
Code Mapping Standard... ANSI		ANSI X.12	
Common Code Type..... CNTRY		Country Code	
Trading Partner.....			
S21 Value	Alternate Value	Description	
1 GB			
- USA			
System 21 Value... GB Alternate Value... 001 Description..... Alteration			
1=Amend 4=Delete			
F3=Exit F6=Add F12=Previous			
14-46 SA HW KS CL IN DN II EDN400H KB PET178S1			

Fields:

System 21 Value

The system displays this value which is protected. You cannot change this value.

Alternate Value

The system displays this value, you can override it.

Description

The system displays this value, you can override it.

Add New Cross Reference Window (F6)

This window allows you to add new common code cross references.

-  Select **F6=Add** from the second Common Codes Cross Reference Maintenance screen to display the Add New Cross Reference window.

AI009 Z1 - GB Demonstration Company User GBJBACHG 22/10/97
Common Codes Cross Reference Maintenance 10:34:02

Code Mapping Standard... ANSI ANSI X.12
Common Code Type..... CNTRY Country Code
Trading Partner.....

S21 Value Alternate Value Description

- GB

- USA

System 21 Value...

Alternate Value...

Description.....

1=Amend 4=Delete

F3=Exit F6=Add F12=Previous

12-36 SA HW KS CL IN DM II EDN4000 KB PET178S1

Fields:

System 21 Value

Enter the System 21 value that you want to match to the customer value.

Alternate Value

Enter the alternate value that you want to match to the System 21 value.

Description

Enter the description. This is a free format field.


Maintain Interface Trading Partner



6/AIM


Interface Trading Partner allows you to enter additional trading partner EDI information and provides a simple route into System 21 for EDI messages. EDI trading partner ID values are matched to System 21 Customer/Delivery codes using the Simple Interface Trading partner file and not the Multiple Interface files.

This option allows you to determine a Customer/Delivery code based on a Trading Partner ID, a delivery ID (such as a plant code) and a receiving location.



Fields:

Enter the trading partner identifier code.



Maintain Interface Trading Partners Screen 2



Press **Enter** from the first Maintain Interface Trading Partners screen to display the second Maintain Interface Trading Partners screen.

AI920	Z1 - GB Demonstration Company	User GBJBACHG	22/10/97 11:52:22
Maintain Interface Trading Partner			
Trading partner Identifier.... FORDNET1 000			
Trading Partner Name..... <u>Last Customer For FORD NET</u>			
Trading Partner Status..... 1 (0=Inactive, 1=Active)			
Mapping Method.....? <u>VDAEMC</u> VDA Specific to FORD			
Partner Specific Map Utility : Inbound <u>ACS10</u> Outbound <u>ACS10</u>			
<u>External Mapping Keys</u>			
Interchange Partner ID <u>FORD1</u>			
Interchange Our ID.... <u>D19TA</u>			
Delivery ID..... <u>EY</u>			
Location ID..... <u>EY</u>			
F3=Exit F4=Prompt F11=Delete F12=Previous			
7-33 <u>SA</u> MW KS CL IH DM II EDN400H KB PET178S1			

Fields:

Trading Partner Identifier

This is displayed from the first Maintain Interface Trading Partners screen.

Trading Partner Name

The system displays the name associated with the trading partner identifier.

Trading Partner Status

Enter one of the following:

0 - Active.

1 - Inactive.

Mapping Method

Enter the code for the mapping type to use for this partner. The mapping code is defined in the descriptions file (CMAP). It is used to find the appropriate set of translation entries for inbound and outbound messages.

Partner Specific Map Utility

Enter the name of the program to call from the primary outbound/inbound Simple Interface File Mapping program.

External Mapping Keys

Customer Id

Enter the external customer identifier.

Supplier Id

Enter the external supplier identifier.

Delivery Id

Enter the external delivery identifier.

Location Id

Enter the external location identifier.



Press **Enter** to confirm the data and display the first Maintain Interface Trading Partners screen.