

-
-
-
-
-

Chapter 9

Execute Applications



Executing Applications

Application Manager allows the software developer to create additional environments to:

1. System-test amended programs without having any potential effect on the live application.
2. Develop bespoke or tailor-made applications.
3. Develop enhancements to existing applications.

Each environment is identified via a three-character environment code. This forms part of the key to access library lists, application-defined tasks, menus and menu and task authorisation. The environment code associated with the standard-application data is blank.

Never alter the data associated with the standard application.

As part of the installation routine, you are issued with a personal environment code or customer code. Any new library lists, application-defined tasks or menus which you create or maintain are associated with this environment code.



Note: The section Environment Usage describes the way in which the environment code is used to access Application Manager data.

You can develop amendments, enhancements and bespoke applications in a test environment. This involves using a supplementary environment code. Use this you to set up test versions of library lists, and so on. This means that any data which has been created using your normal environment code is not available, but the standard application data is



Note: If you create a menu or task with the same name as a standard application menu or task then, when signing on, this new data would be accessed. Authorisation must be allocated again.

System Testing Amended Programs

The user must set up a new set of library lists within Application Manager using an environment code different to the default code, replacing the live data files library with the test data files library, and placing the test programs and display or print file libraries above their live counterparts in the library list.

Bespoke Applications

For new applications it is recommended that your assigned personal code is used as the environment code when using Application Manager to create library lists, tasks or menus.

Application Enhancements

Develop enhancements to existing applications using a test environment code. This test environment then overlays the existing application.

Execute Applications Without Help Text Update

Use this option to sign-on to the applications running under the control of Application Manager.



Select option 8 from the Main Menu and then select sub-menu option 1.

Your initial menu is displayed, (as specified in your User Profile, see the User Profiles section of the Administration Functions Documentation). Alternatively, if your profile has been established with a default application task, this is initiated.

To enter Application Manager you must have:

- Created your User Profile with an initial menu or a single task specified.
- Granted user authority to options on the menu or to the single task.
- Entered the valid Application Manager authorisation code(s) to enable the application(s).
- Granted user authority to companies within the applications.

If you have signed on to a menu then the following facilities are available:

1. Enter an option in the option field and press **Enter**.
2. Select a function.
3. If the application task search facility is available, as a function of the menu, enter the search key words and press **Enter**.
4. Enter a valid command in the option field, if you have been authorised to enter commands on your Application Manager User Profile.
5. Use expert mode. This takes you to another menu or directly into an option on another menu. To do this, enter a command in the form: OO/MMM.

(Where OO is the option number, if required, and MMM is the menu name. In order to go to a menu, simply enter: /MMM)

For a further explanation of these facilities see the Maintain Menus section.



Note: Accessing Application Manager in this way, your environment code is taken to be your default code (your personal code).

Execute Applications With Help Text Update

This procedure provides the same facilities as described in the Execute Applications Without Help Text Update section, with the additional ability to maintain the provided Help text.

Field-level Help is available throughout the range of applications. You can display help by pressing either the Help or F1 keys. Not only is standard application Help Text available, but it may be extended by the user. The help is displayed in a variable size window positioned on the screen so that it does not obscure the field for which it is providing information.

When you press Help or F1, a window appears displaying:

- Help Text definition of this screen has been created but no text currently exists. Press **F21** to create text.
- Help Text definition of this screen has been created and Help Text exists. The text will be displayed. Press **F21** to maintain the text.

If you decide to maintain help text, the changes you make are held in your own user help files; the standard help files are not updated. When you next display the help text files, you will see your changes.



Note: If you are working on a JBA development machine, a screen may appear which asks you whether you wish to maintain standard or user text.

You can also maintain screen level and function key help. Screen level help is displayed by selecting **F2** from a field level help screen. If no text exists and you press **F21** you can maintain text.

Text Addition Help Text Header Details Window

Use this screen to enter the help text header details.

PL005	USER BRIGHTM	4/07/91 16:22:36																								
Maintain Company Profile																										
Company number.....: __																										
<table border="1"> <tr> <th colspan="3">Text Addition - Help Text Header Details</th> </tr> <tr> <td>File: PL005FT</td> <td>Format: F00</td> <td>Field: CONODS</td> </tr> <tr> <td>Text Type:</td> <td colspan="2">Field Level Help Text</td> </tr> <tr> <td>Text Description:</td> <td colspan="2"></td> </tr> <tr> <td>Window Width:</td> <td>60</td> <td>20,40,60,74</td> </tr> <tr> <td>Window Length:</td> <td>8</td> <td>8,16</td> </tr> <tr> <td>Window Position:</td> <td>—</td> <td>1,2,3,4</td> </tr> <tr> <td colspan="3">F12=Previous</td> </tr> </table>			Text Addition - Help Text Header Details			File: PL005FT	Format: F00	Field: CONODS	Text Type:	Field Level Help Text		Text Description:			Window Width:	60	20,40,60,74	Window Length:	8	8,16	Window Position:	—	1,2,3,4	F12=Previous		
Text Addition - Help Text Header Details																										
File: PL005FT	Format: F00	Field: CONODS																								
Text Type:	Field Level Help Text																									
Text Description:																										
Window Width:	60	20,40,60,74																								
Window Length:	8	8,16																								
Window Position:	—	1,2,3,4																								
F12=Previous																										
F3=Exit																										

Fields:

Text Description

Enter a description of the help text.

Window Width

Enter the required width of the help text window; the value is given as the number of characters.

Window Length

The number of lines to be occupied by the help text window.

Window Position

Enter the screen position for the help text window:

- 1 - For the top left corner of the screen.
- 2 - For the top right corner of the screen.
- 3 - For the bottom right corner of the screen
- 4 - For the help text window in the bottom left corner of the screen.

If this field is left blank the help text window defaults to the opposite corner of the screen to the current cursor position.



Press **Enter** to display the Maintain Help Text
For File Screen.

Copy Help Text specified for another field.

F17

Use this to specify a browse or list program for this field. This is only available for field level help.

F22

Use this to switch between the maintenance of text at screen and function key level. This function key is only available for screen level help.



When you have finished entering the help text press **Enter**. The next screen displays your help text in its appropriate screen position.

Help Text Window



This window is displayed from within the application, when you select Help or F1.

Use this window to display the help text.

XA150 Application Manager System: STUDB30A

Maintain Library Lists

Application ID _ _ _ _

Library List code to maintain . . . _ _ _

If the above Library List is to be based on an existing Library List, then the based on Library List code may be entered below. You may optionally enter an alternative

Based on Library List code. .
from application . . .

Help Text

Library List Code
Enter the 4 character library list code to be maintained.

F3=Exit F4=Browse F12=Prev Bottom
F12=Previous F21=Update F14=Print

Functions:

F14

Use this to print of your help text.

F21

Use this to update the help text for this field.

Test Mode Without Help Text Update (Option 3)

Use this option to enter Application Manager and use the facilities described in the Execute Applications Without Help Text Update section. However with this option you can change the environment code from your default personal environment code.

Test Mode Without Help Text Update Window (Option 3)



Select option 3 from the Execute Applications menu and press **Enter**.

Use this screen to enter the environment you want to access.

The screenshot shows the 'Application Manager' interface. At the top, it displays 'XA200' on the left, 'Application Manager' in the center, and 'System: STUDB30A' on the right. The 'Main Menu' is visible on the left, with options 1 through 9. Option 8, 'Execute Application', is highlighted. Below the main menu, there is a 'Selection or command' field with an arrow pointing to the number '4'. To the right of the main menu, the 'Execute Applications' sub-menu is displayed, with options 1 through 5. Option 3, 'Test Mode', is highlighted. Below the sub-menu, there is a text box that reads: 'You are currently using environment OSL. Please select the environment code to be used during this session OSL'. Below this text box, there are instructions: '* Press F3 to exit' and '* Press Enter to continue'. At the bottom of the screen, there is a row of function key shortcuts: F3=Exit, F4=Browse, F6=Messages, F9=Retrieve, F10=Command Entry, F12=Previous, F14=View Jobs, and F24=More Keys.

```
XA200                      Application Manager                      System: STUDB30A

Main Menu
1. Maintain Applicati
2. Maintain Library L
3. Maintain Tasks
4. Maintain Menus
5. Operational Enquir
6. Documentation
7. Utilities
8. Execute Application
9. Exit

Selection or command
=> 4

Execute Applications
1. Without Help Text Update
2. Test Mode
3.
4. You are currently using environment OSL
5. Please select the environment code to
   be used during this session OSL

* Press F3 to exit
* Press Enter to continue

F3=Exit
```



Enter the new environment code; for example, to change to a test environment.

Test Mode With Help Update (Option 4)

Use this option to enter Application Manager and use the facilities described in the Execute Applications With Help Text Update section, but to change the environment code from your default personal environment code.

Test Mode With Help Update Window (Option 4)



Select option 4 from the Execute Applications menu and press **Enter**.

Use this screen to enter the new environment.

XA200 Application Manager System: STUDB30A

Main Menu

1. Maintain Applicati
2. Maintain Library L
3. Maintain Tasks
4. Maintain Menus
5. Operational Enquir
6. Documentation
7. Utilities
8. Execute Application
9. Exit

Execute Applications

1. Without Help Text Update
2. Test Mode
- 3.
4. You are currently using environment OSL
5. Please select the environment code to be used during this session OSL

* Press F3 to exit
* Press Enter to continue

F3=Exit

Selection or command
=> 4

F3=Exit F4=Browse F6=Messages F9=Retrieve
F10=Command Entry F12=Previous F14=View Jobs F24=More Keys



Enter the new environment code, for example to change to a test environment.