Proxmox VE Setup and Configuration

1. Download Proxmox ISO

Get the ISO from the official website:

[Proxmox VE Downloads]



2. Create a Bootable USB

You used **Ventoy**, so the steps are:

1. Install Ventoy on USB.
2. Copy proxmox-ve-*.iso to the USB.
3. Boot the PC from the USB.
4. Select the Proxmox ISO.



3. Install Proxmox VE

During installation:

- Accept License Agreement
- Select target disk
- Select country and timezone
- Set:
    - Root password
    - Email address
- Configure network:
    - Hostname
    - IP address
    - Gateway
    - DNS

Then click **Install**.



4. After Installation

Login from the console:

root

Then update the package list:

apt update

Upgrade packages:

apt full-upgrade -y





5. Check Network Configuration

Show IP addresses:

```
ip a
```

Check gateway:

```
ip route
```

Test internet:

```
ping 8.8.8.8
```

Test DNS:

```
ping google.com
```

6. Check Proxmox Services

Check web proxy:

systemctl status pveproxy

Restart web proxy:

systemctl restart pveproxy

Check cluster service:

systemctl status pve-cluster

Check firewall:

pve-firewall status

Disable firewall temporarily:

pve-firewall stop



7. Access Web Interface

From another PC:

https://YOUR_PROXMOX_IP:8006

Example:

https://172.18.8.5:8006

Login:

Username : root
Realm : Linux PAM standard authentication
Password : <your root password>



8. Create Ubuntu VM

After logging into Proxmox:

1. Upload Ubuntu ISO
2. Click **Create VM**
3. Configure:
   - BIOS → OVMF (UEFI)
   - CPU → Host, 4 Cores
   - RAM → 4096 MB
   - Disk → 40–45 GB
4. Start VM
5. Install Ubuntu





Not secure
https://172.18.8.5:8006/#v1:0:=qemu%2F100:4::::9::
Virtual Environment 9.1.1
Search
Virtual Machine 100 (ubuntu-radius) on node 'prox'
No Tags
Start
center
100 (ubuntu-radius)
101 (ubuntu-snipeit)
localnetwork (prox)
local (prox)
local-lvm (prox)
Summary
Console
Hardware
Cloud-Init
Options
Task History
Monitor
Backup
Replication
Snapshots
Firewall
Permissions
Edit
Revert
Name
ubuntu-radius
Start at boot
No
Start/Shutdown order
order=any
OS Type
Linux 6.x - 2.6 Kernel
Boot Order
scsi0, ide2, net0
Use tablet for pointer
Yes
Hotplug
Disk, Network, USB
ACPI support
Edit: Start at boot
Start at boot:
OK
RTC start date
SMBIOS settings (type1)
uuid=3e145949-60fb-4cf8-b29d-4cb1b28d3559
QEMU Guest Agent
Default (Disabled)
Protection
No
Spice Enhancements
none
VM State storage
Automatic
AMD SEV
Default (Disabled)
Intel TDX
Default (Disabled)
Cluster log
Search

9. Your Project Architecture

Your project can be summarized as:

```
Server 1 (Physical Machine)
│
├── pfSense
│   ├── DHCP Server
│   ├── Routing
│   ├── Firewall
│   └── IP Address Management
│


Server 2 (Physical Machine)
│
└── Proxmox VE
│
├── Ubuntu VM 1
│   ├── FreeRADIUS
│   ├── daloRADIUS
│   └── MariaDB
│
└── Ubuntu VM 2
├── Docker
└── Snipe-IT
```