Gmail IMAP & POP Setup

Gmail Account: vanshajrawat698@gmail.com

---

1. IMAP Setup

Gmail — What to Allow

Go to:

Gmail → Settings → See all settings → Forwarding and POP/IMAP

Under **IMAP access**:

Enable IMAP

If Gmail does not show an enable/disable option for IMAP, IMAP is already available for the account.

IMAP Configuration

Setting	Value
Protocol	IMAP
Incoming Server	imap.gmail.com
Port	993
Security	SSL/TLS
Username	vanshajrawat698@gmail.com

SMTP (for Sending Mail)

Setting	Value
SMTP Server	smtp.gmail.com
Port	587
Security	STARTTLS/TLS
Authentication	Required
Username	vanshajrawat698@gmail.com

2. POP Setup

Gmail — What to Allow

Go to:

Gmail → Settings → See all settings → Forwarding and POP/IMAP

Under **POP Download**:

- Select **Enable POP for all mail**, or
- Select **Enable POP for mail that arrives from now on**

Then save the changes.

POP Configuration

Setting	Value
Protocol	POP3
Incoming Server	pop.gmail.com
Port	995
Security	SSL/TLS
Username	vanshajrawat698@gmail.com

SMTP (for Sending Mail)

Setting	Value
SMTP Server	smtp.gmail.com
Port	587
Security	STARTTLS/TLS
Authentication	Required
Username	vanshajrawat698@gmail.com

3. What Needs to Be Allowed in Gmail

For IMAP

Gmail → Settings → See all settings → Forwarding and POP/IMAP
IMAP: **Enabled**

For POP

POP Download: **Enabled**

That's it.

> *Note: Gmail's current interface may not display an IMAP enable/disable switch. If there is no IMAP option, IMAP access is already available.*

4. Quick Reference

IMAP

IMAP Server: **imap.gmail.com**

Port: **993**

Security: **SSL/TLS**

POP3

POP3 Server: **pop.gmail.com**

Port: **995**

Security: **SSL/TLS**

SMTP

SMTP Server: **smtp.gmail.com**

Port: **587**

Security: **STARTTLS/TLS**

Authentication: **Required**