






```
PNETLab | Topology x Terminal x NAT x +
labs.surenetwork.com/store/public/admin/labs/terminal?terminals=eyJ0YWJzljpbeyJuYW11IjoieSE8tRURHRSlInVybCI6Ii9odG1sNS8jL2NsaWVudC9NekE0T...
HO-EDGE x DC-EDGE x VPC1 x Win1 x
HO-EDGE#
HO-EDGE#
*Aug 5 13:03:01.062: %LINEPROTO-5-UPDOWN: Line protocol on Interface NVI0, changed state to up
HO-EDGE(config)#int e0/1
HO-EDGE(config-if)#ip nat outside
HO-EDGE(config-if)#exit
HO-EDGE(config)#
HO-EDGE(config)#access-list 10 permit 10.0.0.0 0.255.255.255
HO-EDGE(config)#ip nat inside source list 10 interface e0/1 overload
HO-EDGE(config)#exit
HO-EDGE#
*Aug 5 13:06:57.166: %SYS-5-CONFIG_I: Configured from console by console
HO-EDGE#conf t
Enter configuration commands, one per line. End with CNTL/Z.
HO-EDGE(config)#ip dhcp pool LAN
HO-EDGE(dhcp-config)#network 10.0.0.0 255.0.0.0
HO-EDGE(dhcp-config)#default-router 10.0.0.1
HO-EDGE(dhcp-config)#dns-server 8.8.8.8
HO-EDGE(dhcp-config)#exit
HO-EDGE(config)#exit
HO-EDGE#
*Aug 5 13:16:45.321: %SYS-5-CONFIG_I: Configured from console by console
HO-EDGE#show ip int brief
Interface IP-Address OK? Method Status Protocol
Ethernet0/0 10.0.0.1 YES manual up up
Ethernet0/1 20.0.0.1 YES manual up up
Ethernet0/2 unassigned YES TFTP down down
Ethernet0/3 unassigned YES TFTP down down
NVI0 10.0.0.1 YES unset up up
HO-EDGE#
```

HO-EDGE x DC-EDGE x VPC1 x Win1 x

```
DC-EDGE(config)#ip route 0.0.0.0 0.0.0.0 30.0.0.1
DC-EDGE(config)#
DC-EDGE(config)#int e0/0
DC-EDGE(config-if)#ip nat inside exit
^
% Invalid input detected at '^' marker.
DC-EDGE(config-if)#ip nat inside
DC-EDGE(config-if)#ex
*Aug 5 13:11:38.379: %LINEPROTO-5-UPDOWN: Line protocol on Interface NVI0, changed state to up
DC-EDGE(config-if)#exit
DC-EDGE(config)#
DC-EDGE(config)#int e0/1
DC-EDGE(config-if)#ip nat outside
DC-EDGE(config-if)#exit
DC-EDGE(config)#
DC-EDGE(config)#ip nat inside source static 192.168.1.10 30.0.0.10
DC-EDGE(config)#ip nat inside source static 192.168.1.20 30.0.0.11
DC-EDGE(config)#
*Aug 5 13:14:22.387: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
DC-EDGE(config)#show ip route
^
% Invalid input detected at '^' marker.
DC-EDGE(config)#exit
DC-EDGE#sh
*Aug 5 13:19:55.539: %SYS-5-CONFIG_I: Configured from console by console
DC-EDGE#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
```



