

Tab search

⚠ Not secure 49.204.127.18/legacy/topology



VPC-3

```
VPC-3> ip dhcp
DDD
Can't find dhcp server

VPC-3> █
```

R3

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#int e0/0

Router(config-if)#ip helper-address 50.0.1.198

Router(config-if)#exit

Router(config)#exit

Router#s

*Jul 31 07:33:40.164: %SYS-5-CONFIG_I: Configured from console by console

Router#sh ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP

a - application route

+ - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is 50.0.1.197 to network 0.0.0.0

S* 0.0.0.0/0 [1/0] via 50.0.1.197

50.0.0.0/8 is variably subnetted, 4 subnets, 3 masks

C 50.0.0.0/24 is directly connected, Ethernet0/0

L 50.0.0.1/32 is directly connected, Ethernet0/0

*Jul 31 07:25:15.911: %SYS-5-CONFIG_I: Configured from console by console

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#int e 0/0

Router(config-if)#ip helper-address 50.0.1.198

Router(config-if)#exit

Router(config)#int e 0/0

Router(config-if)#ip helper-address 50.0.1.197

Router(config-if)#exit

Router(config)#exit

Router#sh

*Jul 31 07:28:21.375: %SYS-5-CONFIG_I: Configured from console by console

Router#sh ip int brief

Interface	IP-Address	OK?	Method	Status	Prot
ocol					
Ethernet0/0	50.0.0.1	YES	manual	up	up
Ethernet0/1	50.0.1.198	YES	manual	up	up
Ethernet0/2	unassigned	YES	unset	administratively down	down
Ethernet0/3	unassigned	YES	unset	administratively down	down

```
50.0.1.198/32 is already connected, Ethernet0/1
L 50.0.1.198/32 is directly connected, Ethernet0/1
Router#
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 50.0.1.128 255.255.255.192 50.0.1.197
Router(config)#ip route 50.0.1.192 255.255.255.252 50.0.1.197
Router(config)#ip route 50.0.1.0 255.255.255.128 50.0.1.197
Router(config)#int e0/0
Router(config-if)#ip helper-address 50.0.1.194
Router(config-if)#exit
```

```
R1
Router>
Router>
Router>en
Router#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#exiy
      ^
% Invalid input detected at '^' marker.


Router(config)#exit
Router#
*Jul 31 07:45:36.063: %SYS-5-CONFIG_I: Configured from console by console
Router#sh ip int brief
Interface                IP-Address      OK? Method Status      Prot
ocol
Ethernet0/0              50.0.1.129      YES manual  up          up
Ethernet0/1              50.0.1.193      YES manual  up          up
Ethernet0/2              unassigned      YES unset   administratively down down
Ethernet0/3              unassigned      YES unset   administratively down down
Router#
```

SUBNETTING

HR 50-PC

PRODUCTION 120-PC

SALES 250-PC



R1

```
Router#
Router#
Router#
Router#
Router#sh ip int brief
Interface          IP-Address      OK? Method Status      Prot
ocol
Ethernet0/0        50.0.1.129      YES manual up          up
Ethernet0/1        50.0.1.193      YES manual up          up
Ethernet0/2        unassigned      YES unset  administratively down down
Ethernet0/3        unassigned      YES unset  administratively down down
Router#
```

R1


```
!  
!  
!  
!  
!  
  
!  
!  
ip dhcp pool hr  
network 50.0.1.128 255.255.255.192  
default-router 50.0.1.129  
!  
ip dhcp pool pro  
network 50.0.1.0 255.255.255.128  
default-router 50.0.1.1  
!  
ip dhcp pool sales  
network 50.0.0.0 255.255.255.0  
default-router 50.0.0.1  
!  
!  
!  
ip cef
```



```
R2
R2(config)#
R2(config)#
R2(config)#
R2(config)#
R2(config)#exit
R2#sh i
*Jul 31 07:53:59.920: %SYS-5-CONFIG_I: Configured from console by console
R2#sh ip int brief
Interface                IP-Address      OK? Method Status      Prot
ocol
Ethernet0/0              50.0.1.1        YES manual  up          up
Ethernet0/1              50.0.1.194      YES manual  up          up
Ethernet0/2              50.0.1.197      YES manual  up          up
Ethernet0/3              unassigned      YES TFTP   down        down
R2#
```

R3

```
Router(config)#
Router(config)#
Router(config)#
Router(config)#
Router(config)#exit
Router#sh
*Jul 31 07:54:20.278: %SYS-5-CONFIG_I: Configured from console by console
Router#sh ip int brief
Interface                IP-Address      OK? Method Status      Prot
ocol
Ethernet0/0              50.0.0.1        YES manual  up          up
Ethernet0/1              50.0.1.198      YES manual  up          up
Ethernet0/2              unassigned      YES unset   administratively down down
Ethernet0/3              unassigned      YES unset   administratively down down
Router#
```



```
VPC-1> ip dhcp
DORA IP 50.0.1.131/26 GW 50.0.1.129
VPC-1> 
```

The image shows a terminal window with a title bar that includes a file icon and the text 'VPC-1'. The window has standard minimize, maximize, and close buttons. The terminal content shows a command 'ip dhcp' being executed, which returns the output 'DORA IP 50.0.1.131/26 GW 50.0.1.129'. A new line 'VPC-1>' is shown with a green cursor, indicating the prompt is ready for the next command.

QEMU (Win-2)



My Documents

My Computer

My Network Places

Recycle Bin

Internet Explorer

Cisco
ASDM 1

C:\WINDOWS\system32\cmd.exe

Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

Connection-specific DNS Suffix	:	:
IP Address	:	50.0.1.2
Subnet Mask	:	255.255.255.128
Default Gateway	:	50.0.1.1

C:\Documents and Settings\user>_

QEMU (Win-1)



C:\WINDOWS\system32\cmd.exe

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

Connection-specific DNS Suffix	:	:
IP Address	:	50.0.1.130
Subnet Mask	:	255.255.255.192
Default Gateway	:	50.0.1.129


C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

Connection-specific DNS Suffix	:	:
IP Address	:	50.0.1.130
Subnet Mask	:	255.255.255.192
Default Gateway	:	50.0.1.129


C:\Documents and Settings\user>




```
VPC-3> ip dhcp
DDORA IP 50.0.0.3/24 GW 50.0.0.1

VPC-3> 
```

The image shows a terminal window with a title bar that includes a small icon and the text "VPC-3". The window has standard minimize, maximize, and close buttons. The terminal content shows a command prompt "VPC-3>" followed by the command "ip dhcp". The output of this command is "DDORA IP 50.0.0.3/24 GW 50.0.0.1". Below the output, the prompt "VPC-3>" is shown again, followed by a green cursor block, indicating the terminal is ready for further input.





A terminal window titled "VPC-2" with standard window controls (minimize, maximize, close) on the right. The terminal has a black background with white text. It shows the command "ip dhcp" being executed, followed by the output "DORA IP 50.0.1.3/25 GW 50.0.1.1". Below this, the prompt "VPC-2>" is followed by a red cursor block.

```
VPC-2> ip dhcp
DORA IP 50.0.1.3/25 GW 50.0.1.1
VPC-2> █
```