

@config

Appears in: [DL-08](#)

server/config.py:13-30, 33-52

"The settings live in @config as plain module values that are read from environment variables at start-up and can be changed at runtime through a settings endpoint ..."

@config

server/config.py:13-30

```
13 # — Desktop notifications (plyer) —————
14 NOTIFY_DESKTOP = os.getenv("NOTIFY_DESKTOP", "true").lower() == "true"
15
16 # — Email notifications (SMTP) —————
17 NOTIFY_EMAIL = os.getenv("NOTIFY_EMAIL", "")
18 SMTP_HOST = os.getenv("SMTP_HOST", "smtp.gmail.com")
19 SMTP_PORT = int(os.getenv("SMTP_PORT", "587"))
20 SMTP_USER = os.getenv("SMTP_USER", "")
21 SMTP_PASS = os.getenv("SMTP_PASS", "")
22
23 # — Per-trigger toggles —————
24 NOTIFY_ON_APPROVAL = os.getenv("NOTIFY_ON_APPROVAL", "true").lower() == "true"
25 NOTIFY_ON_AUTO_PO = os.getenv("NOTIFY_ON_AUTO_PO", "false").lower() == "true"
26 NOTIFY_ON_SCORE_DROP = os.getenv("NOTIFY_ON_SCORE_DROP", "true").lower() == "true"
27 NOTIFY_ON_DUPLICATE = os.getenv("NOTIFY_ON_DUPLICATE", "true").lower() == "true"
28
29 # Score must cross below this threshold (not just be below it) to trigger an alert
30 SCORE_DROP_THRESHOLD = float(os.getenv("SCORE_DROP_THRESHOLD", "0.6"))
```

...

server/config.py:33-52

```
33 def update(settings: dict) -> None:
34     """Apply a dict of setting overrides to this module's globals at runtime."""
35     import server.config as _self
36     bool_keys = {
37         "NOTIFY_DESKTOP", "NOTIFY_ON_APPROVAL", "NOTIFY_ON_AUTO_PO",
38         "NOTIFY_ON_SCORE_DROP", "NOTIFY_ON_DUPLICATE",
39     }
40     int_keys = {"SMTP_PORT"}
41     float_keys = {"SCORE_DROP_THRESHOLD"}
42     for key, val in settings.items():
43         if not hasattr(_self, key):
44             continue
45         if key in bool_keys:
46             setattr(_self, key, bool(val))
47         elif key in int_keys:
48             setattr(_self, key, int(val))
49         elif key in float_keys:
50             setattr(_self, key, float(val))
51         else:
52             setattr(_self, key, str(val))
```

What it shows: Plain module-level values (not frozen constants) so `update()` can mutate them at runtime; `update()` type-coerces known keys and ignores unknown ones.

Source: server/config.py:13-30, 33-52 · image rendered by [build_snippets.py](#)